
FASTR Documentation

Release 2.0.0

Fastr contributors

Sep 28, 2017

Contents

1 FASTR Documentation	3
1.1 Introduction	3
1.1.1 Philosophy	3
1.1.2 System overview	3
1.2 Quick start guide	5
1.2.1 Installation	5
1.2.2 Configuration	6
1.2.3 Creating a simple network	6
1.2.4 Running a Network	9
1.3 User Manual	9
1.3.1 Tools	10
1.3.2 Network	12
1.3.3 Data Flow	15
1.3.4 DataTypes	20
1.3.5 Execution	21
1.3.6 IOPlugins	22
1.3.7 Secrets	22
1.3.8 Debugging	22
1.3.9 Naming Convention	27
1.3.10 Provenance	28
1.4 Command Line Tools	29
1.4.1 fastr cat	29
1.4.2 fastr dump	29
1.4.3 fastr execute	30
1.4.4 fastr extract_argparse	30
1.4.5 fastr prov	30
1.4.6 fastr run	31
1.4.7 fastr test	31
1.4.8 fastr trace	32
1.4.9 fastr verify	32
1.4.10 fastr webapp	33
1.5 Resource File Formats	33
1.5.1 Config file	33
1.5.2 Tool description	36
1.6 Resource Reference	36
1.6.1 CollectorPlugin Reference	36

1.6.2	ExecutionPlugin Reference	38
1.6.3	FlowPlugin Reference	41
1.6.4	IOPlugin Reference	41
1.6.5	Interface Reference	46
1.6.6	Target Reference	48
1.7	Development and Design Documentation	50
1.7.1	Sample flow in Fastr	50
1.7.2	Network Execution	53
1.7.3	Secrets	55
1.8	Changelog	57
1.8.1	2.0.0 - 28-09-2017	57
1.8.2	1.2.2 - 2017-08-24	58
1.8.3	1.2.1 - 2017-04-04	58
1.8.4	1.2.0 - 2017-03-15	59
1.8.5	1.1.2 - 2016-12-22	60
1.8.6	1.1.1 - 2016-12-22	60
1.8.7	1.1.0 - 2016-12-08	60
2	FASTR User reference	61
2.1	Fastr User Reference	61
3	FASTR Developer Module reference	65
3.1	fastr Package	65
3.1.1	fastr Package	65
3.1.2	configmanager Module	77
3.1.3	datatypes Module	79
3.1.4	exceptions Module	89
3.1.5	plugins Module	95
3.1.6	version Module	115
3.1.7	Subpackages	116
4	Indices and tables	241
	Python Module Index	243

FASTR is a framework that helps creating workflows of different tools. The workflows created in FASTR are automatically enhanced with flexible data input/output, execution options (local, cluster, etc) and solid provenance.

We chose to create tools by creating wrappers around executables and connecting everything with Python.

Fastr is open-source (licensed under the Apache 2.0 license) and hosted on bitbucket at https://bitbucket.org/bigr_erasmusmc/fastr

For support, go to <https://groups.google.com/d/forum/fastr-users>

To get yourself a copy, see the [*Installation*](#)

The official documentation can be found at fastr.readthedocs.io

The Fastr workflow system is presented in the following article:

Hakim Achterberg, Marcel Koek, and Wiro Niessen. “Fastr: a workflow engine for advanced data flows in medical image analysis.” *Frontiers in ICT* 3 (2016): 15.

Fastr is made possible by contributions from the following people: Hakim Achterberg, Marcel Koek, Adriaan Versteeg, Thomas Phil, Mattias Hansson, Baldur van Lew, Marcel Zwiers, and Coert Metz

CHAPTER 1

FASTR Documentation

Introduction

Fastr is a system for creating workflows for automated processing of large scale data. A processing workflow might also be called a processing pipeline, however we feel that a pipeline suggests a linear flow of data. Fastr is designed to handle complex flows of data, so we prefer to use the term network. We see the workflow as a network of processing tools, through which the data will flow.

The original authors work in a medical image analysis group at Erasmus MC. They often had to run analysis that used multiple programs written in different languages. Every time a experiment was set up, the programs had to be glued together by scripts (often in bash or python).

At some point the authors got fed up by doing these things again and again, and so decided to create a flexible, powerful scripting base to easily create these scripts. The idea evolved to a framework in which the building blocks could be defined in XML and the networks could be constructed in very simple scripts (similar to creating a GUI).

Philosophy

Researchers spend a lot of time processing data. In image analysis, this often includes using multiple tools in succession and feeding the output of one tool to the next. A significant amount of time is spent either executing these tools by hand or writing scripts to automate this process. This process is time consuming and error-prone. Considering all these tasks are very similar, we wanted to write one elaborate framework that makes it easy to create pipelines, reduces the risk of errors, generates extensive logs, and guarantees reproducibility.

The Fastr framework is applicable to multiple levels of usage: from a single researcher who wants to design a processing pipeline and needs to get reproducible results for publishing; to applying a consolidated image processing pipeline to a large population imaging study. On all levels of application the pipeline provenance and managed execution of the pipeline enables you to get reliable results.

System overview

There are a few key requirements for the design of the system:

- Any tool that your computer can run using the command line (without user interaction) should be usable by the system without modifying the tool.
- The creation of a workflow should be simple, conceptual and require no real programming.
- Networks, once created, should be usable by anyone like a simple program. All processing should be done automatically.
- All processing of the network should be logged extensively, allowing for complete reproducibility of the system (guaranteeing data provenance).

Using these requirements we define a few key elements in our system:

- A `fastr.Tool` is a definition of any program that can be used as part of a pipeline (e.g. a segmentation tool)
- A `fastr.Node` is a single operational step in the workflow. This represents the execution of a `fastr.Tool`.
- A `fastr.Link` indicates how the data flows between nodes.
- A `fastr.Network` is an object containing a collection of `fastr.Node` and `fastr.Link` that form a workflow.

With these building blocks, the creation of a pipeline will boil down to just specifying the steps in the pipeline and the flow of the data between them. For example a simple neuro-imaging pipeline could look like:




Fig. 1.1: A simple workflow that registers two images and uses the resulting transform to resample the moving image.

In Fastr this translates to:

- Create a `fastr.Network` for your pipeline
- Create a `fastr.SourceNode` for the fixed image

- Create a `fastr.SourceNode` for the moving image
- Create a `fastr.SourceNode` for the registration parameters
- Create a `fastr.Node` for the registration (in this case elastix)
- Create a `fastr.Node` for the resampling of the image (in this case transformix)
- Create a `fastr.SinkNode` to save the transformations
- Create a `fastr.SinkNode` to save the transformed images
- `fastr.Link` the output of the fixed image source node to the fixed image input of the registration node
- `fastr.Link` the output of the moving image source node to the moving image input of the registration node
- `fastr.Link` the output of the registration parameters source node to the registration parameters input of the registration node
- `fastr.Link` the output transform of the registration node to the transform input of the resampling node
- `fastr.Link` the output transform of the registration node to the input of transformation SinkNode
- `fastr.Link` the output image of the resampling node to the input of image SinkNode
- Run the `fastr.Network` for subjects X

This might seem like a lot of work for a registration, but the Fastr framework manages all other things, executes the pipeline and builds a complete paper trail of all executed operations. The execution can be on any of the supported execution environments (local, cluster, etc). The data can be imported from and exported to any of the supported data connections (file, XNAT, etc). It is also important to keep in mind that this is a simple example, but for more complex pipelines, managing the workflow with Fastr will be easier and less error-prone than writing your own scripts.

Quick start guide

This manual will show users how to install Fastr, configure Fastr, construct and run simple networks, and add tool definitions.

Installation

You can install Fastr either using pip, or from the source code.

Installing via pip

You can simply install fastr using pip:

```
pip install fastr
```

Note: You might want to consider installing `fastr` in a `virtualenv`

Installing from source code

To install from source code, use Mercurial via the command-line:

```
hg clone https://<yourusername>@bitbucket.org/bigr_erasmusmc/fastr # for http  
hg clone ssh://hg@bitbucket.org/bigr_erasmusmc/fastr # for ssh
```

If you prefer a GUI you can try [TortoiseHG](#) (Windows, Linux and Mac OS X) or [SourceTree](#) (Windows and Mac OS X). The address of the repository is (given for both http and ssh):

```
https://<yourusername>@bitbucket.org/bigr_erasmusmc/fastr  
ssh://hg@bitbucket.org/bigr_erasmusmc/fastr
```

To install to your current Python environment, run:

```
cd fastr/  
pip install .
```

This installs the scripts and packages in the default system folders. For windows this is the python site-packages directory for the fastr python library and Scripts directory for the executable scripts. For Ubuntu this is in the /usr/local/lib/python2.7/dist-packages/ and /usr/local/bin/ respectively.

Note: If you want to develop fastr, you might want to use `pip install -e .` to get an editable install

Note: You might want to consider installing fastr in a [virtualenv](#)

Note:

- On windows python and the Scripts directory are not on the system PATH by default. You can add these by going to System -> Advanced Options -> Environment variables.
 - On mac you need the Xcode Command Line Tools. These can be installed using the command `xcode-select --install`.
-

Configuration

Fastr has defaults for all settings so it can be run out of the box to test the examples. However, when you want to create your own Networks, use your own data, or use your own Tools, it is required to edit your config file.

Fastr will search for a config file named `config.py` in the `$FASTRHOME` and `~/.fastr/` directories. If both config files contain values for a single setting, the version in `~/.fastr/` has priority.


For a sample configuration file and a complete overview of the options in `config.py` see the [Config file](#) section.

Creating a simple network

If Fastr is properly installed and configured, we can start creating networks. Creating a network is very simple:

```
>>> import fastr  
  
>>> network = fastr.Network()
```

Now we have an empty network, the next step is to create some nodes and links. Imagine we want to create the following network:



Creating nodes

We will create the nodes and add them to the network. The easiest way to do this is via the network `create_` methods. Let's create two source nodes, one normal node, and one sink:

```

>>> source1 = network.create_source('Int', id_='source1')
>>> constant1 = network.create_constant('Int', [1, 3, 3, 7], id_='const1')
>>> sink1 = network.create_sink('Int', id_='sink1')
>>> addint = network.create_node('AddInt', id_='addint')

```

The functions `Network.create_source`, `Network.create_constant`, `Network.create_source` and `Network.create_sink` are shortcut functions for calling the `SourceNodeRun`, `ConstantNodeRun`, `SinkNodeRun` and `NodeRun` constructors and adding them to the network. A `SourceNodeRun` and `SinkNodeRun` only require the datatype to be specified. A `ConstantNodeRun` requires both the datatype and the data to be set on creation. A `NodeRun` requires a `Tool` template to be instantiated from. The `id_` option is optional for all three, but makes it easier to identify the nodes and read the logs.

There is an easier way to add a constant to an input, by using a shortcut method. If you assign a list or tuple to an item in the input list, it will automatically create a `ConstantNodeRun` and a `Link` between the contant and the input:

```

>>> addint.inputs['right_hand'] = [1, 3, 3, 7]

```

The created constant would have the id `addint_right_hand_const` as it automatically names the new constant `$nodeid$inputid const`.

In an interactive python session we can simply look at the basic layout of the node using the `repr` function. Just type the name of the variable holding the node and it will print a human readable representation:

```

>>> source1
SourceNodeRun source1 (tool: source v1.0)
    Inputs           |       Outputs
    -----
                    |   output   (Int)
>>> addint
NodeRun addint (tool: AddInt v1.0)
    Inputs           |       Outputs
    -----
left_hand (Int)    |   result   (Int)
right_hand (Int)  | 

```

This tool has inputs of type Int, so the sources and sinks need to have a matching datatype.

The tools and datatypes available are stored in `fastr.toollist` and `fastr.typelist`. These variables are

created when `fastr` is imported for the first time. They contain all the datatype and tools specified by the xml files in the search paths. To get an overview of the tools and datatypes loaded by `fastr`:

```
>>> fastr.toollist
ToolManager
Add v0.1 : /home/hachterberg/dev/fastr-develop/
  ↵fastr/fastr/resources/tools/add/v1_0/add.xml
AddImages v0.1 : /home/hachterberg/dev/fastr-develop/
  ↵fastr/fastr/resources/tools/addimages/v1_0/addimages.xml
AddInt v0.1 : /home/hachterberg/dev/fastr-develop/
  ↵fastr/fastr/resources/tools/addint/v1_0/addint.xml

>>> fastr.typeplist
DataTypeManager
AnyType : <class 'fastr.datatypes.AnyType'>
Boolean : <class 'fastr.datatypes.Boolean'>
Directory : <class 'fastr.datatypes.Directory'>
Float : <class 'fastr.datatypes.Float'>
Int : <class 'fastr.datatypes.Int'>
String : <class 'fastr.datatypes.String'>
```

The `fastr.toollist` variable contains all tools that Fastr could find during initialization. Tools can be chosen in two tways:

- `toollist[id]` which returns the newest version of the tool
- `toollist[id, version]` which returns the specified version of the tool

Creating links

So now we have a network with 4 nodes defined, however there is no relation between the nodes yet. For this we have to create some links.

```
>>> link1 = network.create_link(sourcel.output, addint.inputs['left_hand'])
>>> link2 = network.create_link(constant1.output, addint.inputs['right_hand'])
>>> link3 = network.create_link(addint.outputs['result'], sink1.inputs['input'])
```

This asks the network to create links and immediatly store them inside the network. A link always points from an Output to an Input (note that SubOutput or SubInputs are also valid). A `SourceNodeRun` has only 1 output which is fixed, so it is easy to find. However, `addImage` has two inputs and one output, this requires us to specify which output we need. A normal node has a mapping with Inputs and one with Outputs. They can be indexed with the approriate id's. The function returns the links, but you only need that if you are planning to change a link. If not, it is possible to use a short-hand which creates a link but gives you no easy access to it for later.


```
>>> addint.inputs['left_hand'] = sourcel.output
>>> addint.inputs['right_hand'] = constant1.output
>>> sink1.inputs['input'] = addint.outputs['result']
```

Create an image of the Network

For checking your Network it is very useful to have a graphical representation of the network. This can be achieved using the `Network.draw_network` method.

```
>>> network.draw_network()
'/home/username/network_layout.dot.svg'
```

This will create a figure in the path returned by the function that looks like:



Note: for this to work you need to have graphviz installed

Running a Network

Running a network locally is almost as simple as calling the `Network.execute` method:

```

>>> source_data = {'source1': {'s1': 4, 's2': 5, 's3': 6, 's4': 7}}
>>> sink_data = {'sink1': 'vfs://tmp/fastr_result_{sample_id}.txt'}
>>> network.execute(source_data, sink_data)
  
```

As you can see the execute method needs data for the sources and sinks. This has to be supplied in two `dict` that have keys matching every source/sink id in the network. Not supplying data for every source and sink will result in an error, although it is possible to pass an empty `list` to a source.

Note: The values of the source data have to be simple values or urls and values of the sink data have to be url templates. To see what url schemes are available and how they work see [IOPPlugin Reference](#). For the sink url templates see `SinkNodeRun.set_data`

For source nodes you can supply a `list` or a `dict` with values. If you supply a `dict` the keys will be interpreted as sample ids and the values as the corresponding values. If you supply a `list`, keys will be generated in the form of `id_{N}` where N will be index of the value in the list.

Warning: As a `dict` does not have a fixed order, when a `dict` is supplied the samples are ordered by key to get a fixed order! For a `list` the original order is retained.

For the sink data, an url template has to be supplied that governs how the data is stored. The mini-language (the replacement fields) are described in the `SinkNodeRun.set_data` method.

To rerun a stopped/crashed pipeline check the user manual on [Continuing a Network](#)

User Manual

In this chapter we will discuss the parts of Fastr in more detail. We will give a more complete overview of the system and describe the more advanced features.

Tools

The [Tools](#) in Fastr are the building blocks of each workflow. A tool represents a program/script/binary that can be called by Fastr and can be seen as a template. A [Node](#) can be created based on a [Tool](#). The Node will be one processing step in a workflow, and the tool defines what the step does.

On the import of Fastr, all available [Tools](#) will be loaded in a default [ToolManager](#) that can be accessed via `fastr.toollist`. To get an overview of the tools in the system, just print the `repr()` of the [ToolManager](#):

```
>>> fastr.toollist
AddImages           v0.1      : /home/hachterberg/dev/fastr/fastr/resources/tools/
  ↳ addimages/v1_0/addimages.xml
AddInt              v0.1      : /home/hachterberg/dev/fastr/fastr/resources/tools/
  ↳ addint/v1_0/addint.xml
```

As you can see it gives the tool id, version and the file from which it was loaded for each tool in the system. To view the layout of a tool, just print the `repr()` of the tool itself.

```
>>> fastr.toollist['AddInt']
Tool AddInt v0.1 (Add two integers)
    Inputs          |       Outputs
-----
left_hand (Int)   |   result   (Int)
right_hand (Int) |
```

To add a [Tool](#) to the system a file should be added to one of the path in `fastr.config.tools_path`. The structure of a tool file is described in [Tool description](#)

Create your own tool

There are 4 steps in creating a tool:

1. **Create folders.** We will call the tool ThrowDie. Create the folder `throw_die` in the folder `fastr-tools`. In this folder create another folder called `bin`.
2. **Place executable in correct place.** In this example we will use a snippet of executable python code:

```
#!/usr/bin/env python
import sys
import random
import json

if (len(sys.argv) > 1):
    sides = int(sys.argv[1])
else:
    sides = 6
result = [int(random.randint(1, sides))]

print ('RESULT={}'.format(json.dumps(result)))
```

Save this text in a file called `throw_die.py`

Place the executable python script in the folder `throw_die/bin`

3. **Create and edit xml file for tool.** See [tool definition reference](#) for all the fields that can be defined in a tool.

Put the following text in file called `throw_die.xml`.

```

<tool id="ThrowDie" description="Simulates a throw of a die. Number of sides of the die is provided by user"
      name="throw_die" version="1.0">
  <authors>
    <author name="John Doe" />
  </authors>
  <command version="1.0" >
    <authors>
      <author name="John Doe" url="http://a.b/c" />
    </authors>
    <targets>
      <target arch="*" bin="throw_die.py" interpreter="python" os="*" paths='bin/' />
    </targets>
    <description>
      throw_die.py number_of_sides
      output = simulated die throw
    </description>
  </command>
  <interface>
    <inputs>
      <input cardinality="1" datatype="Int" description="Number of die sides" id="die_sides" name="die sides" nospace="False" order="0" required="True"/>
    </inputs>
    <outputs>
      <output id="output" name="output value" datatype="Int" automatic="True" cardinality="1" method="json" location="^RESULT=(.*)$" />
    </outputs>
  </interface>
</tool>

```

Put throw_die.xml in the folder example_tool. All Attributes in the example above are required. For a complete overview of the xml Attributes that can be used to define a tool, check the [Tool description](#). The most important Attributes in this xml are:

<pre> id : The id is used in in FASTR to create an instance of your tool, this name will appear in the toollist when you type fastr.toollist. targets : This defines where the executables are located and on which platform they are available. inputs : This defines the inputs that you want to be used in FASTR, how FASTR should use them and what data is allowed to be put in there. </pre>
--

More xml examples can be found in the fastr-tools folder.

4. **Edit configuration file.** Append the line [PATH TO LOCATION OF FASTR-TOOLS]/fastr-tools/throw_die/ to the config.py (located in ~/.fastr/ directory) to the tools_path. See [Config file](#) for more information on configuration.

You should now have a working tool. To test that everything is ok do the following in python:

<pre> >>> import fastr >>> fastr.toollist </pre>
--

Now a list of available tools should be produced, including the tool throw_die

To test the tool create the script test_throwdie.py:

<pre> import fastr network = fastr.Network() </pre>

```

source1 = network.create_source(fastr.typeplist['Int'], id_='source1')
sink1 = network.create_sink(fastr.typeplist['Int'], id_='sink1')
throwdie = network.create_node(fastr.toollist['ThrowDie'], id_='throwdie')
link1 = network.create_link(source1.output, throwdie.inputs['die_sides'])
link2 = network.create_link(throwdie.outputs['output'], sink1.inputs['input
    ↵'])
source_data = {'source1': {'s1': 4, 's2': 5, 's3': 6, 's4': 7}}
sink_data = {'sink1': 'vfs://tmp/fastr_result_{sample_id}.txt'}
network.draw_network()
network.execute(source_data, sink_data)

```

Call the script from commandline by

```
$ python test_throwdie.py
```

An image of the network will be created in the current directory and result files will be put in the tmp directory. The result files are called `fastr_result_s1.txt`, `fastr_result_s2.txt`, `fastr_result_s3.txt`, and `fastr_result_s4.txt`

Note: If you have code which is operating system depend you will have to edit the xml file. The following gives an example of how the elastix tool does this:

```


<targets>
  <target os="windows" arch="*" bin="elastix.exe">
    <paths>
      <path type="bin" value="vfs://apps/elastix/4.7/install/" />
      <path type="lib" value="vfs://apps/elastix/4.7/install/lib" />
    </paths>
  </target>
  <target os="linux" arch="*" modules="elastix/4.7" bin="elastix">
    <paths>
      <path type="bin" value="vfs://apps/elastix/4.7/install/" />
      <path type="lib" value="vfs://apps/elastix/4.7/install/lib" />
    </paths>
  </target>
  <target os="darwin" arch="*" modules="elastix/4.7" bin="elastix">
    <paths>
      <path type="bin" value="vfs://apps/elastix/4.7/install/" />
      <path type="lib" value="vfs://apps/elastix/4.7/install/lib" />
    </paths>
  </target>
</targets>

```

`vfs` is the virtual file system path, more information can be found at [VirtualFileSystem](#).

Network

A *Network* represented an entire workflow. It hold all *Nodes*, *Links* and other information required to execute the workflow. Networks can be visualized as a number of building blocks (the Nodes) and links between them:



An empty network is easy to create, all you need is to name it:

```
>>> network = fastr.Network(id_="network_name")
```

The *Network* is the main interface to Fastr, from it you can create all elements to create a workflow. In the following sections the different elements of a *Network* will be described in more detail.

Node

Nodes are the point in the *Network* where the processing happens. A *Node* takes the input data and executes jobs as specified by the underlying *Tool*. A *Nodes* can be created in a two different ways:

```
>>> node1 = fastr.Node(tool, id_='node1', parent=network)
>>> node2 = network.create_node(tool, id_='node2', stepid='step1')
```

In the first way, we specifically create a *Node* object. We pass it an *id* and the parent *network*. If the *parent* is *None* the *fastr.current_network* will be used. The *Node* constructor will automatically add the new node to the parent *network*.

Note: For a Node, the tool can be given both as the *Tool* class or the id of the

tool.

The second way, we tell the *network* to create a *Node*. The *network* will automatically assign itself as the parent. Optionally you can add define a *stepid* for the node which is a logical grouping of *Nodes* that is mostly used for visualization.

A *Node* contains *Inputs* and *Outputs*. To see the layout of the *Node* one can simply look at the *repr()*.

```
>>> addint = fastr.Node(fastr.toollist['AddInt'], id_='addint')
>>> addint
Node addint (tool: AddInt v1.0)
    Inputs           |       Outputs
    -----
    left_hand (Int) | result   (Int)
    right_hand (Int)|
```

The inputs and outputs are located in mappings with the same name:

```
>>> addint.inputs
InputDict([('left_hand', <Input: fastr:///networks/unnamed_network/nodelist/addint/
           ↪inputs/left_hand>), ('right_hand', <Input: fastr:///networks/unnamed_network/
           ↪nodelist/addint/inputs/right_hand>) ])

>>> addint.outputs
OutputDict([('result', Output fastr:///networks/unnamed_network/nodelist/addint/
           ↪outputs/result)])
```

The `InputDict` and `OutputDict` are classes that behave like mappings. The `InputDict` also facilitates the linking shorthand. By assigning an `Output` to an existing key, the `InputDict` will create a `Link` between the `InputDict` and `Output`.

SourceNode

A `SourceNode` is a special kind of node that is the start of a workflow. The `SourceNodes` are given data at run-time that fetched via `IOPugins`. On create, only the datatype of the data that the `SourceNode` supplied needs to be known. Creating a `SourceNode` is very similar to an ordinary node:

```
>>> source1 = fastr.SourceNode('Int', id_='source1')
>>> source2 = network.create_source(fastr.typeList['Int'], id_='source2', stepid=
   ↪'step1')
```

In both cases, the source is automatically automatically assigned to a network. In the first case to the `fastr.current_network` and in the second case to the `network` used to call the method. A `SourceNode` only has a single output which has a short-cut access via `source.output`.

Note: For a source or constant node, the datatype can be given both as the `BaseDataType` class or the id of the datatype.

ConstantNode

A `ConstantNode` is another special node. It is a subclass of the `SourceNode` and has a similar function. However, instead of setting the data at run-time, the data of a constant is given at creation and saved in the object. Creating a `ConstantNode` is similar as creating a source, but with supplying data:

```
>>> constant1 = fastr.ConstantNode('Int', [42], id_='constant1')
>>> constant2 = network.create_constant('Int', [42], id_='constant2', stepid='step1')
```

Often, when a `ConstantNode` is created, it is created specifically for one input and will not be reused. In this case there is a shorthand to create and link a constant to an input:

```
>>> addint.inputs['value1'] = [42]
```

will create a constant node with the value 42 and create a link between the output and input `addint.value1`.

SinkNode

The `SinkNode` is the counter-part of the source node. Instead of get data into the workflow, it saves the data resulting from the workflow. For this a rule has to be given at run-time that determines where to store the data. The information about how to create such a rule is described at `SinkNode.set_data`. At creation time, only the datatype has to be specified:

```
>>> sink1 = fastr.Sink('Int', id_='sink1')
>>> sink2 = network.create_sink(fastr.typelist['Int'], id_='sink2', stepid='step1')
```

Link

`Links` indicate how the data flows between `Nodes`. Links can be created explicitly using one of the following:

```
>>> link = fastr.Link(node1.outputs['image'], node2.inputs['image'])
>>> link = network.create_link(node1.outputs['image'], node2.inputs['image'])
```


or can be created implicitly by assigning an `Output` to an `Input` in the `InputDict`.

```
# This style of assignment will create a Link similar to above
>>> node2.inputs['image'] = node1.outputs['image']
```

Note that a `Link` is also created automatically when using the short-hand for the `ConstantNode`

Data Flow

The data enters the `Network` via `SourceNodes`, flows via other `Nodes` and leaves the `Network` via `SinkNodes`. The flow between `Nodes` goes from an `Output` via a `Link` to an `Input`. In the following image it is simple to track the data from the `SourceNodes` at the left to the `SinkNodes` at right side:



Note that the data in Fastr is stored in the `Output` and the `Link` and `Input` just give access to it (possibly while transforming the data).

Data flow inside a Node


In a `Node` all data from the `Inputs` will be combined and the jobs will be generated. There are strict rules to how this combination is performed. In the default case all inputs will be used pair-wise, and if there is only a single value for an input, it will be considered as a constant.

To illustrate this we will consider the following `Tool` (note this is a simplified version of the real tool):


```
>>> fastr.toollist['Elastix']
Tool Elastix v4.8 (Elastix Registration)
Inputs | Outputs
-----
fixed_image      (ITKImageFile) | transform_
  ↵(ElastixTransformFile)
moving_image     (ITKImageFile)
parameters       (ElastixParameterFile)
```

Also it is important to know that for this tool (by definition) the cardinality of the `transform` *Output* will match the cardinality of the parameters *Inputs*


If we supply a *Node* based on this *Tool* with a single sample on each *Input*, there will be one single matching *Output* sample created:




If the cardinality of the parameters sample would be increased to 2, the resulting `transform` sample would also become 2:



Now if the number of samples on `fixed_image` would be increased to 3, the `moving_image` and `parameters` will be considered constant and be repeated, resulting in 3 `transform` samples.



Then if the amount of samples for `moving_image` is also increased to 3, the `moving_image` and `fixed_image` will be used pairwise and the `parameters` will be constant.




Advanced flows in a Node

Sometimes the default pairwise behaviour is not desirable. For example if you want to test all combinations of certain input samples. To achieve this we can change the `input_group` of `Inputs` to set them apart from the rest. By default all `Inputs` are assigned to the default input group. Now let us change that:

```
>>> node = network.create_node('Elastix', id_='elastix')
>>> node.inputs['moving_image'].input_group = 'moving'
```

This will result in `moving_image` to be put in a different input group. Now if we would supply `fixed_image` with 3 samples and `moving_image` with 4 samples, instead of an error we would get the following result:




Warning: TODO: Expand this section with the merging dimensions

Data flows in a Link

As mentioned before the data flows from an `Output` to an `Input` through a `Link`. By default the `Link` passes the data as is, however there are two special directives that change the shape of the data:

1. Collapsing flow, this collapses certain dimensions from the sample array into the cardinality. As a user you have to specify the dimension or tuple of dimensions you want to collapse.




This is useful in situation where you want to use a tool that aggregates over a number of samples (e.g. take a mean or sum).

To achieve this you can set the `collapse` property of the `Link` as follows:

```
>>> link.collapse = 'dim1'
>>> link.collapse = ('dim1', 'dim2') # In case you want to collapse multiple dimensions
```

2. Expanding flow, this turns the cardinality into a new dimension. The new dimension will be named after the `Output` from which the link originates. It will be in the form of `{nodeid}__{outputid}`




This flow directive is useful if you want to split a large sample in multiple smaller samples. This could be because processing the whole sample is not feasible because of resource constraints. An example would be splitting a 3D image into slices to process separately to avoid high memory use or to achieve parallelism.

To achieve this you can set the `expand` property of the `Link` to True:

```
>>> link.expand = True
```

Note: both collapsing and expanding can be used on the same link, it will executes similar to a expand-collapse sequence, but the newly created expand dimension is ignored in the collapse.



```
>>> link.collapse = 'dim1'  
>>> link.expand = True
```

Data flows in an Input

If an `Inputs` has multiple `Links` attached to it, the data will be combined by concatenating the values for each corresponding sample in the cardinality.


Broadcasting (matching data of different dimensions)

Sometimes you might want to combine data that does not have the same number of dimensions. As long as all dimensions of the lower dimensional datasets match a dimension in the higher dimensional dataset, this can be achieved using *broadcasting*. The term *broadcasting* is borrowed from NumPy and described as:


“The term broadcasting describes how numpy treats arrays with different shapes during arithmetic operations. Subject to certain constraints, the smaller array is “broadcast” across the larger array so that they have compatible shapes.”

—NumPy manual on broadcasting

In fastr it works similar, but to combined different Inputs in an InputGroup. To illustrate broadcasting it is best to use an example, the following network uses broadcasting in the `transformix` Node:



As you can see this visualization prints the dimensions for each Input and Output (e.g. the `elastix.fixed_image` Input has dimensions [N]). To explain what happens in more detail, we present an image illustrating the details for the samples in `elastix` and `transformix`:



In the figure the `moving_image` (and references to it) are identified with different colors, so they are easy to track across the different steps.

At the top the Inputs for the `elastix` Node are illustrated. Because the input groups a set differently, output samples are generated for all combinations of `fixed_image` and `moving_image` (see [Advanced flows in a Node](#) for details).

In the `transformix` Node, we want to combine a list of samples that is related to the `moving_image` (it has the same dimension name and sizes) with the resulting `transform` samples from the `elastix` Node. As you can see the sizes of the sample collections do not match ($[N]$ vs $[N \times M]$). This is where *broadcasting* comes into play, it allows the system to match these related sample collections. Because all the dimensions in $[N]$ are known in $[N \times M]$, it is possible to match them uniquely. This is done automatically and the result is a new $[N \times M]$ sample collection. To create a matching sample collections, the samples in the `transformix.image` Input are reused as indicated by the colors.

Warning: Note that this might fail when there are data-blocks with non-unique dimension names, as it will be not be clear which of the dimensions with identical names should be matched!

DataTypes

In Fastr all data is contained in object of a specific type. The types in Fastr are represented by classes that subclass `BaseDataType`. There are a few different other classes under `BaseDataType` that are each a base class for a family of types:

- `DataType` – The base class for all types that hold data
 - `ValueType` – The base class for types that contain simple data (e.g. Int, String) that can be represented as a str
 - `EnumType` – The base class for all types that are a choice from a `set` of options
 - `URLType` – The base class for all types that have their data stored in files (which are referenced by URL)
- `TypeGroup` – The base class for all types that actually represent a group of types




Fig. 1.2: The relation between the different `DataType` classes

The types are defined in xml files and created by the `DataTypeManager`. The `DataTypeManager` acts as a container containing all Fastr types. It is automatically instantiated as `fastr.typelist`. In fastr the created `DataType`s classes are also automatically placed in the `fastr.datatypes` module once created.

Resolving Datatypes

`Outputs` in fastr can have a `TypeGroup` or a number of `DataType`s associated with them. The final `DataType`

used will depend on the linked *Inputs*. The *DataType* resolving works as a two-step procedure.

1. All possible *DataTypes* are determined and considered as *options*.
2. The best possible *DataType* from *options* is selected for non-automatic Outputs

The *options* are defined as the intersection of the set of possible values for the *Output* and each separate *Input* connected to the *Output*. Given the resulting *options* there are three scenarios:

- If there are no valid *DataTypes* (*options* is empty) the result will be None.
- If there is a single valid *DataType*, then this is automatically the result (even if it is not a preferred *DataType*).
- If there are multiple valid *DataTypes*, then the preferred *DataTypes* are used to resolve conflicts.

There are a number of places where the preferred *DataTypes* can be set, these are used in the order as given:

1. The *preferred* keyword argument to *match_types*
2. The preferred types specified in the *fastr.config*

Execution

Executing a Network is very simple:

```
>>> source_data = {'source_id1': ['val1', 'val2'],
                   'source_id2': {'id3': 'val3', 'id4': 'val4'}}
>>> sink_data = {'sink_id1': 'vfs://some_output_location/{sample_id}/file.txt'}
>>> network.execute(source_data, sink_data)
```

The *Network.execute* method takes a *dict* of source data and a *dict* sink data as arguments. The dictionaries should have a key for each *SourceNode* or *SinkNode*.

TODO: add .. figure:: images/execution_layers.*

The execution of a Network uses a layered model:

- *Network.execute* will analyze the Network and call all Nodes.
- *Node.execute* will create jobs and fill their payload
- *execute_job* will execute the job on the execute machine and resolve any deferred values (val:// urls).
- *Tool.execute* will find the correct target and call the interface and if required resolve vfs:// urls
- *Interface.execute* will actually run the required command(s)

The *ExecutionPlugin* will call the *executionscript.py* for each job, passing the job as a gzipped pickle file. The *executionscript.py* will resolve deferred values and then call *Tool.execute* which analyses the required target and executes the underlying *Interface*. The Interface actually executes the job and collect the results. The result is returned (via the Tool) to the *executionscript.py*. There we save the result, provenance and profiling in a new gzipped pickle file. The execution system will use a callback to load the data back into the Network.

The selection and settings of the *ExecutionPlugin* are defined in the *fastr config*.

Continuing a Network

Normally a random temporary directory is created for each run. To continue a previously stopped/crashed network, you should call the *Network.execute* method using the same temporary directory(tmp dir). You can set the temporary directory to a fixed value using the following code:

```
>>> tmpdir = '/tmp/example_network_rerun'  
>>> network.execute(source_data, sink_data, tmpdir=tmpdir)
```

Warning: Be aware that at this moment, Fastr will rerun only the jobs where not all output files are present or if the job/tool parameters have been changed. It will not rerun if the input data of the node has changed or the actual tools have been adjusted. In these cases you should remove the output files of these nodes, to force a rerun.

IOPugins

Sources and sink are used to get data in and out of a *Network* during execution. To make the data retrieval and storage easier, a plugin system was created that selects different plugins based on the URL scheme used. So for example, a url starting with `vfs://` will be handles by the `VirtualFileSystem` plugin. A list of all the `IOPugins` known by the system and their use can be found at [IOPugin Reference](#).

Secrets

Fastr uses a secrets system for storing and retrieving login credentials. Currently the following keyrings are supported:

- Python keyring and keyrings.alt lib:
 - Mac OS X Keychain - Freedesktop Secret Service (requires secretstorage)
 - KWallet (requires dbus) - Windows Credential Vault - Gnome Keyring - Google Keyring (stores keyring on Google Docs)
 - Windows Crypto API (File-based keyring secured by Windows Crypto API)
 - Windows Registry Keyring (registry-based keyring secured by Windows Crypto API)
 - PyCrypto File Keyring - Plaintext File Keyring (not recommended)
- Netrc (not recommended)

When a password is retrieved trough the fastr SecretService it loops trough all of the available SecretProviders (currently keyring and netrc) until a match is found.

The Python keyring library automatically picks the best available keyring backend. If you wish to choose your own python keyring backend it is possible to do so by make a keyring configuration file according to the keyring library documentation. The python keyring library connects to one keyring. Currently it cannot loop trough all available keyrings until a match is found.

Debugging

This section is about debugging Fastr tools wrappers, Fastr Networks (when building a Network) and Fastr Network Runs.

Debugging a Fastr tool

When wrapping a Tool in Fastr sometimes it will not work as expected or not load properly. Fastr is shipped with a command that helps checking Tools. The `fastr verify` command can try to load a Tool in steps to make it more easy to understand where the loading went wrong.

The `fastr verify` command will use the following steps:

- Try to load the tool with and without compression
- Try to find the correct serializer and make sure the format is correct
- Try to validate the Tool content against the json_schema of a proper Tool

- Try to create a Tool object
- If available, execute the tool test

An example of the use of `fastr verify`:

```
$ fastr verify tool fastr/resources/tools/fastr/math/0.1/add.xml
[INFO]     verify:0020 >> Trying to read file with compression OFF
[INFO]     verify:0036 >> Read data from file successfully
[INFO]     verify:0040 >> Trying to load file using serializer "xml"
[INFO]     verify:0070 >> Validating data against Tool schema
[INFO]     verify:0080 >> Instantiating Tool object
[INFO]     verify:0088 >> Loaded tool <Tool: Add version: 1.0> successfully
[INFO]     verify:0090 >> Testing tool...
```

If your Tool is loading but not functioning as expected you might want to easily test your Tool without building an entire Network around it that can obscure errors. It is possible to run a tool from the Python prompt directly using `tool.execute`:

```
>>> tool.execute(left_hand=40, right_hand=2)
[INFO] localbinarytarget:0090 >> Changing ./bin
[INFO]     tool:0311 >> Target is <Plugin: LocalBinaryTarget>
[INFO]     tool:0318 >> Using payload: {'inputs': {'right_hand': (2,), 'left_hand': (40,)}, 'outputs': {}}
[INFO] localbinarytarget:0135 >> Adding extra PATH: ['/home/hachterberg/dev/fastr-develop/fastr/resources/tools/fastr/math/0.1/bin']
[INFO] fastrinterface:0393 >> Execution payload: {'inputs': {'right_hand': (2,), 'left_hand': (40,)}, 'outputs': {}}
[INFO] fastrinterface:0496 >> Adding (40,) to argument list based on <fastrinterface> InputParameterDescription object at 0x7fc950fa8850>
[INFO] fastrinterface:0496 >> Adding (2,) to argument list based on <fastrinterface> InputParameterDescription object at 0x7fc950fa87d0>
[INFO] localbinarytarget:0287 >> Options: ['/home/hachterberg/dev/fastr-develop/fastr/resources/tools/fastr/math/0.1/bin']
[INFO] localbinarytarget:0201 >> Calling command arguments: ['python', '/home/hachterberg/dev/fastr-develop/fastr/resources/tools/fastr/math/0.1/bin/addint.py', '--in1', '40', '--in2', '2']
[INFO] localbinarytarget:0205 >> Calling command: "'python' '/home/hachterberg/dev/fastr-develop/fastr/resources/tools/fastr/math/0.1/bin/addint.py' '--in1' '40' '--in2' '2'"
[INFO] fastrinterface:0400 >> Collecting results
[INFO] executionpluginmanager:0467 >> Callback processing thread ended!
[INFO] executionpluginmanager:0467 >> Callback processing thread ended!
[INFO] executionpluginmanager:0467 >> Callback processing thread ended!
[INFO] jsoncollector:0076 >> Setting data for result with [42]
<fastr.core.interface.InterfaceResult at 0x7fc9661ccfd0>
```

In this case an `AddInt` was ran from the python shell. As you can see it shows the payload it created based on the call, followed by the options for the directories that contain the binary. Then the command that is called is given both as a list and string (for easy copying to the prompt yourself). Finally the collected results is displayed.

Note: You can give input and outputs as keyword arguments for `execute`. If an input and output have the same name, you can disambiguate them by prefixing them with `in_` or `out_` (e.g. `in_image` and `out_image`)

Debugging an invalid Network

The simplest command to check if your Network is considered valid is to use the `Network.is_valid` method. It will simply check if the Network is valid:

```
>>> network.is_valid()
True
```

It will return a boolean that only indicates the validity of the Network, but it will print any errors it found to the console/log with the ERROR log level, for example when datatypes on a link do not match:


```
>>> invalid_network.is_valid()
[WARNING] datatypemanager:0388 >> No matching DataType available (args (<ValueType:_  
↳Float class [Loaded]>, <ValueType: Int class [Loaded]>))
[WARNING]         link:0546 >> Cannot match datatypes <ValueType: Float class [Loaded]>_  
↳and <ValueType: Int class [Loaded]> or not preferred datatype is set! Abort linking_
↳fastr://networks/add_ints/0.0/nodelist/source/outputs/output to fastr://networks/_  
↳add_ints/0.0/nodelist/add/inputs/left_hand!
[WARNING] datatypemanager:0388 >> No matching DataType available (args (<ValueType:_  
↳Float class [Loaded]>, <ValueType: Int class [Loaded]>))
[ERROR]   network:0571 >> [add] Input left_hand is not valid: SubInput fastr://_
↳networks/add_ints/0.0/nodelist/add/inputs/left_hand/0 is not valid: SubInput source_
↳(link_0) is not valid
[ERROR]   network:0571 >> [add] Input left_hand is not valid: SubInput fastr://_
↳networks/add_ints/0.0/nodelist/add/inputs/left_hand/0 is not valid: [link_0] source_
↳and target have non-matching datatypes: source Float and Int
[ERROR]   network:0571 >> [link_0] source and target have non-matching datatypes:_
↳source Float and Int
False
```

Because the messages might not always be enough to understand errors in the more complex Networks, we would advice you to create a plot of the network using the `network.draw_network` method:

```
>>> network.draw_network(network.id, draw_dimensions=True, expand_macro=True)
'add_ints.svg'
```

The value returned is the path of the output image generated (it will be placed in the current working directory. The `draw_dimensions=True` will make the drawing add indications about the sample dimensions in each Input and Output, whereas `expand_macro=True` causes the draw to expand MacroNodes and draw the content of them. If you have many nested MacroNodes, you can set `expand_macro` to an integer and that is the depth until which the MacroNodes will be drawn in detail.

An example of a simple multi-atlas segmentation Network nicely shows the use of drawing the dimensions, the dimensions vary in certain Nodes due to the use of `input_groups` and a collapsing link (drawn in blue):



Debugging a Network run with errors

If a Network run did finish but there were errors detected, Fastr will report those at the end of the execution. We included an example of a Network that has failing samples in `fastr/examples/failing_network.py` which can be used to test debugging. An example of the output of a Network run with failures:

```

[INFO] networkrun:0604 >> #####
[INFO] networkrun:0605 >> #      network execution FINISHED      #
[INFO] networkrun:0606 >> #####
[INFO] networkrun:0618 >> ===== RESULTS =====
[INFO] networkrun:0627 >> sink_1: 2 success / 2 failed
[INFO] networkrun:0627 >> sink_2: 2 success / 2 failed
[INFO] networkrun:0627 >> sink_3: 1 success / 3 failed
[INFO] networkrun:0627 >> sink_4: 1 success / 3 failed
[INFO] networkrun:0627 >> sink_5: 1 success / 3 failed
[INFO] networkrun:0628 >> =====
[WARNIN] networkrun:0651 >> There were failed samples in the run, to start debugging_
→ you can run:

    fastr trace $RUNDIR/_sink_data__.json --sinks

see the debug section in the manual at https://fastr.readthedocs.io/en/default/static/user\_manual.html#debugging for more information.

```

As you can see, there were failed samples in every sink. Also you already get the suggestion to use `fastr trace`. This command helps you inspect the staging directory of the Network run and pinpoint the errors.

The suggested command will print a similar summary as given by the network execution:

```

$ fastr trace $RUNDIR/_sink_data__.json --sinks
sink_1 -- 2 failed -- 2 succeeded
sink_2 -- 2 failed -- 2 succeeded
sink_3 -- 3 failed -- 1 succeeded
sink_4 -- 3 failed -- 1 succeeded
sink_5 -- 3 failed -- 1 succeeded

```

Since this is not given us new information we can add the `-v` flag for more output and limit the output to one sink, in this case `sink_5`:

```
$ fastr trace $RUNDIR/__sink_data__.json --sinks sink_5
sink_5 -- 3 failed -- 1 succeeded
  sample_1_1: Encountered error: [FastrOutputValidationError] Could not find result
  ↵for output out_2 (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.
  ↵py:970)
  sample_1_2: Encountered error: [FastrOutputValidationError] Could not find result
  ↵for output out_1 (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.
  ↵py:970)
  sample_1_3: Encountered error: [FastrOutputValidationError] Could not find result
  ↵for output out_1 (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.
  ↵py:970)
  sample_1_3: Encountered error: [FastrOutputValidationError] Could not find result
  ↵for output out_2 (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.
  ↵py:970)
```

Now we are given one error per sample, but this does not yet give us that much information. To get a very detailed report we have to specify one sink and one sample. This will make the `fastr trace` command print a complete error report for that sample:

```
$ fastr trace $RUNDIR/__sink_data__.json --sinks sink_5 --sample sample_1_1 -v
Tracing errors for sample sample_1_1 from sink sink_5
Located result pickle: /home/hachterberg/FastrTemp/fastr_failing_network_2017-09-
  ↵04T10-44-58_uMWeMV/step_1/sample_1_1/__fastr_result__.pickle.gz

===== JOB failing_network__step_1__sample_1_1 =====
Network: failing_network
Run: failing_network_2017-09-04T10-44-58
Node: step_1
Sample index: (1)
Sample id: sample_1_1
Status: JobState.execution_failed
Timestamp: 2017-09-04 08:45:19.238192
Job file: /home/hachterberg/FastrTemp/fastr_failing_network_2017-09-04T10-44-58_
  ↵uMWeMV/step_1/sample_1_1/__fastr_result__.pickle.gz

Command:
List representation: [u'python', u'/home/hachterberg/dev/fastr-develop/fastr/fastr/
  ↵resources/tools/fastr/util/0.1/bin/fail.py', u'--in_1', u'1', u'--in_2', u'1', u'--
  ↵fail_2']
String representation: 'python' '/home/hachterberg/dev/fastr-develop/fastr/fastr/
  ↵resources/tools/fastr/util/0.1/bin/fail.py' '--in_1' '1' '--in_2' '1' '--fail_2'

Output data:
{'out_1': [<Int: 2>]}

Status history:
2017-09-04 08:45:19.238212: JobState.created
2017-09-04 08:45:21.537417: JobState.running
2017-09-04 08:45:31.578864: JobState.execution_failed

----- ERRORS -----
- FastrOutputValidationError: Could not find result for output out_2 (/home/
  ↵hachterberg/dev/fastr-develop/fastr/fastr/execution/job.py:970)
- FastrValueError: [failing_network__step_1__sample_1_1] Output values are not
  ↵valid! (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.py:747)
```

```
-----
----- STDOUT -----
Namespace(fail_1=False, fail_2=True, in_1=1, in_2=1)
in 1 : 1
in 2 : 1
fail_1: False
fail_2: True
RESULT_1=[2]

-----
----- STDERR -----
-----
```

As shown above, it finds the result files of the failed job(s) and prints the most important information. The first paragraph shows the information about the Job that was involved. The second paragraph shows the command used both as a list (which is clearer and internally used in Python) and as a string (which you can copy/paste to the shell to test the command). Then there is the output data as determined by Fastr. The next section shows the status history of the Job which can give an indication about wait and run times. Then there are the errors that Fastr encountered during the execution of the Job. In this case it could not find the output for the Tool. Finally the stdout and stderr of the subprocess are printed. In this case we can see that RESULT_2=[...] was not in the stdout, and so the result could not be located.

Note: Sometimes there are no Job results in a directory, this usually means the process got killed before the Job could finished. On cluster environments, this often means that the process was killed due to memory constraints.

Asking for help with debugging

If you would like help with debugging, you can contact us via the [fastr-users google group](#). To enable us to track the errors please include the following:

- The entire log of the fastr run (can be copied from console or from the end of `~/.fastr/logs/info.log`).
- A dump of the network run, which can be created that by using the `fastr dump` command like:

```
$ fastr dump $RUNDIR fastr_run_dump.zip
```

This will create a zip file including all the job files, logs, etc but not the actual data files.

These should be enough information to trace most errors. In some cases we might need to ask for additional information (e.g. tool files, datatype files) or actions from your side.

Naming Convention

For the naming convention of the tools we tried to stay close to the Python [PEP 8](#) coding style. In short, we defined toolnames as classes so they should be UpperCamelCased. The inputs and outputs of a tool we considered as functions or method arguments, these should be named lower_case_with_underscores.

An overview of the mapping of Fastr to [PEP 8](#):

Fastr construct	Python PEP8 equivalent	Examples
Network.id	module	brain_tissue_segmentation
Tool.id	class	BrainExtractionTool, ThresholdImage
Node.id	variable name	brain_extraction, threshold_mask
Input/Output.id	method	image, number_of_classes, probability_image

Furthermore there are some small guidelines:

- No input or output in the input or output names. This is already specified when setting or getting the data.
- Add the type of the output that is named. i.e. enum, string, flag, image,
 - No File in the input/output name (Passing files around is what Fastr was developed for).
 - No type necessary where type is implied i.e. lower_threshold, number_of_levels, max_threads.
- Where possible/useful use the fullname instead of an abbreviation.

Provenance

For every data derived data object, Fastr records the **Provenance**. The *SinkNode* write provenance records next to every data object it writes out. The records contain information on what operations were performed to obtain the resulting data object.

W3C Prov

The provenance is recorded using the **W3C Prov Data Model (PROV-DM)**. Behind the scenes we are using the python **prov** implementation.

The PROV-DM defines 3 Starting Point Classes and their relating properties. See Fig. 1.3 for a graphic representation of the classes and the relations. *

Fig. 1.3: The three Starting Point classes and the properties that relate them. The diagrams in this document depict Entities as yellow ovals, Activities as blue rectangles, and Agents as orange pentagons. The responsibility properties are shown in pink.⁰

Implementation

In the workflow document the provenance classes map to fastr concepts in the following way:

Agent Fastr, *Networks, Tools, Nodes*

Activity *Jobs*

Entities Data

⁰ This picture and caption is taken from <http://www.w3.org/TR/prov-o/>. “Copyright © 2011-2013 World Wide Web Consortium, (MIT, ERCIM, Keio, Beihang). <http://www.w3.org/Consortium/Legal/2015/doc-license>“

Usage

The provenance is stored in ProvDocument objects in pickles. The convenience command line tool `fastr prov` can be used to extract the provenance in the [PROV-N](#) notation and can be serialized to [PROV-JSON](#) and [PROV-XML](#). The provenance document can also be visualized using the `fastr prov` command line tool.

Command Line Tools

Fastr is shipped with a number of command line tools to perform common tasks and greatly simplify things such as debugging. The list of command line tools that is included in Fastr:

command	description
<code>cat</code>	Print information from a job file
<code>dump</code>	Dump the contents of a network run tempdir into a zip for remote assistance
<code>execute</code>	Execute a fastr job file
<code>extract_argparse</code>	Create a stub for a Tool based on a python script using argparse
<code>prov</code>	Get PROV information from the result pickle.
<code>run</code>	Run a Network from the commandline
<code>test</code>	Run the tests of a tool to verify the proper function
<code>trace</code>	Trace samples/sinks from a run
<code>verify</code>	Print information from a job file
<code>webapp</code>	Start the fastr webapp and open in a new browser tab

fastr cat

Extract selected information from the extra job info. The path is the selection of the data to retrieve. Every part of the path (separated by a /) is seen as the index for the previous object. So for example to get the stdout of a job, you could use ‘`fastr cat __fastr_extra_job_info__.json process/stdout`’.

```
usage: fastr cat [-h] __fastr_extra_job_info__.json path
```

Positional Arguments

__fastr_extra_job_info__.json result file to cat

path path of the data to print

fastr dump

Create a dump of a network run directory that contains the most important information for debugging. This includes a serialization of the network, all the job command and result files, the extra job information files and the provenance files. No data files will be included, but note that if jobs get sensitive information passed via the command line this will be included in the job files.

```
usage: fastr dump [-h] RUNDIR DUMP.zip
```

Positional Arguments

RUNDIR The run directory to dump

DUMP.zip The file to place the dump in

fastr execute

Execute a job from commandline.

```
usage: fastr execute [-h] [JOBFILE]
```

Positional Arguments

JOBFILE File of the job to execute (default ./fastr_command__.pickle.gz)

fastr extract_argparse

Extract basic information from argparse.

```
usage: fastr extract_argparse [-h] SCRIPT.py TOOL.xml
```

Positional Arguments

SCRIPT.py Python script to inspect

TOOL.xml created Tool stub

fastr prov

Export the provenance information from JSON to other formats or plot the provenance data as a graph.

```
usage: fastr prov [-h] [-so SYNTAX_OUT_FILE] [-sf SYNTAX_FORMAT] [-i INDENT]
                  [-vo VISUALIZE_OUT_FILE]
                  [RESULTFILE]
```

Positional Arguments

RESULTFILE File of the job to execute (default ./fastr_prov__.json)

Named Arguments

-so, --syntax-out-file Write the syntax to file.

-sf, --syntax-format Choices are: [json], provn or xml

Default: “json”

-i, --indent Indent size of the serialized documents.

Default: 2

-vo, --visualize-out-file Visualize the provenance. The most preferred format is svg. You can specify any format pydot supports. Specify the format by postfixing the filename with an extension.

fastr run

Execute a job or network from commandline.

```
usage: fastr run [-h] NETWORKFILE
```

Positional Arguments

NETWORKFILE File of the network to execute

fastr test

Run a tests for a fastr resource.

```
usage: fastr test [-h] {tool,tools,network,networks} ...
```

Sub-commands:

tool

Test a single tool

```
fastr test tool [-h] TOOL
```

Positional Arguments

TOOL Tool to test or directory with tool reference data

tools

Test all tools known to fastr

```
fastr test tools [-h]
```

network

Test a single network

```
fastr test network [-h] NETWORK
```

Positional Arguments

NETWORK The reference data to test the Network

networks

Test all network references inside subdirectories

```
fastr test networks [-h] [--result RESULT.json] REFERENCE
```

Positional Arguments

REFERENCE path of the directory containing subdirectories with reference data

Named Arguments

--result Write the results of the test to a JSON file

fastr trace

Fastr trace helps you inspect the staging directory of the Network run and pinpoint the errors.

```
usage: fastr trace [-h] [--verbose] [--sinks [SINKS [SINKS ...]]]
                   [--samples [SAMPLES [SAMPLES ...]]]
                   [__sink_data__.json]
```

Positional Arguments

__sink_data__.json result file to cat

Default: “/home/docs/checkouts/readthedocs.org/user_builds/fastr/checkouts/2.0.0/fastr/doc/__sink_data___.json”

Named Arguments

--verbose, -v set verbose output for more details

Default: False

--sinks list results for specified sinks

--samples list result for all samples

fastr verify

Verify fastr resources, at the moment only tool definitions are supported.

```
usage: fastr verify [-h] TYPE path
```

Positional Arguments

TYPE Possible choices: tool

Type of resource to verify (e.g. tool)

path path of the resource to verify

fastr webapp

Starts the fastr web client.

```
usage: fastr webapp [-h] [-d] [-o]
```

Named Arguments

-d, --debug	Debug mode. Default: False
-o, --openpage	Open web page after start. Default: False

Resource File Formats

This chapter describes the various files fastr uses. The function and format of the files is described allowing the user to configure fastr and add DataTypes and Tools.

Config file

Fastr reads the config files from the following locations by default (in order):

- \$FASTRHOME/config.py
- ~/.fastr/config.py

Reading a new config file change or override settings, making the last config file read have the highest priority. All settings have a default value, making config files and all settings within optional.

Example config file

Here is a minimal config file:

```
# Enable debugging output
debug = False

# Define the path to the tool definitions
tools_path = ['/path/to/tools',
              '/path/to/other/tools'] + tools_path
types_path = ['/path/to/datatypes',
              '/path/to/other/datatypes'] + types_path

# Specify what your preferred output types are.
preferred_types += ["NiftiImageFileCompressed",
                     "NiftiImageFile"]

# Set the tmp mount
mounts['tmp'] = '/path/to/tmpdir'
```

Format

The config file is actually a python source file. The next syntax applies to setting configuration values:

```
# Simple values
float_value = 1.0
int_value = 1
str_value = "Some value"
other_str_value = 'name'.capitalize()

# List-like values
list_value = ['over', 'ride', 'values']
other_list_value.prepend('first')
other_list_value.append('list')

# Dict-like values
dict_value = {'this': 1, 'is': 2, 'fixed': 3}
other_dict_value['added'] = 'this key'
```

Note: Dictionaries and list always have a default, so you can always append or assign elements to them and do not have to create them in a config file. Best practice is to only edit them unless you really want to block out the earlier config files.

Most operations will be assigning values, but for list and dict values a special wrapper object is used that allows manipulations from the default. This limits the operations allowed.

List values in the `config.py` have the following supported operators/methods:

- `+`, `__add__` and `__radd__`
- `+=` or `__iadd__`
- `append`
- `prepend`
- `extend`

Mapping (dict-like) values in the `config.py` have the following supported operators/methods:

- `update`
- `[]` or `__getitem__`, `__setitem__` and `__delitem__`

Configuration fields

This is a table the known config fields on the system:

name	type	description	default
debug	bool	Flag to enable/disable debugging	False
examplesdir	str	Directory containing the fastr examples	\$systemdir/examples
execution_plugin	str	The default execution plugin to use	'ProcessPoolExecution'
execution-script	str	Execution script location	\$systemdir/execution/executionscript.py
filesyncurl	str	Redis url e.g. redis://localhost:6379	"
logdir	str	Directory where the fastr logs will be placed	\$userdir/logs
logging_config	dict	Python logger config	{}
loglevel	int	The log level to use (as int), INFO is 20, WARNING is 30, etc	20
logtype	str	Type of logging to use	'default'
mounts	dict	A dictionary containing all mount points in the VFS system	{'tmp': '\$TMPDIR', 'home': '~', 'example_data': '\$systemdir/examples/data'}
networks_path	list	Directories to scan for networks	['\$userdir/networks', '\$resourcedir/networks']
pim_host	str	Host of the PIM server to report to	"
plugins_path	list	Directories to scan for plugins	['\$userdir/plugins', '\$resourcedir/plugins']
preferred_types	list	A list indicating the order of the preferred types to use. First item is most preferred.	[]
protected_modules	list	A list of modules in the environment modules that are protected against unloading	[]
resources-dir	str	Directory containing the fastr system resources	\$systemdir/resources
schemadir	str	Directory containing the fastr data schemas	\$systemdir/schemas
source_job_limit	int	The number of source jobs allowed to run concurrently	0
systemdir	str	Fastr installation directory	'/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg/fastr'
tools_path	list	Directories to scan for tools	['\$userdir/tools', '\$resourcedir/tools']
types_path	list	Directories to scan for datatypes	['\$userdir/datatypes', '\$resourcedir/datatypes']
userdir	str	Fastr user configuration directory	~/.fastr
warn_develop	bool	Warning users on import if this is not a production version of fastr	True
web_hostname	str	The hostname to expose the web app for	'localhost'
web_port	str	The port to expose the web app on	'5000'
web_secretkey	str	The secret key to use for the flask web app	'VERYSECRETKEY!'

Tool description

Tools are the building blocks in the fastr network. To add new *Tools* to fastr, XML/json files containing a *Tool* definition can be added. These files have the following layout:

Attribute	Description
id	The id of this Tool (used internally in fastr)
name	The name of the Tool, for human readability
version	The version of the Tool wrapper (not the binary)
url	The url of the Tool wrapper
authors[]	List of authors of the Tools wrapper
	name Name of the author
	email Email address of the author
	url URL of the website of the author
tags	tag[] List of tags describing the Tool
command	Description of the underlying command
	version Version of the tool that is wrapped
	url Website where the tools that is wrapped can be obtained
	targets[] Description of the target binaries/script of this Tool
	os OS targeted (windows, linux, macos or * (for any))
	arch Architecture targeted 32, 64 or * (for any)
	... Extra variables based on the target used, see <i>Targets</i>
	description Description of the Tool
	license License of the Tool, either full license or a clear name (e.g. LGPL, GPL v2)
	authors[] List of authors of the Tool (not the wrapper!)
interface	name Name of the authors
	email Email address of the author
	url URL of the website of the author
	The interface definition see <i>Interfaces</i>
help	Help text explaining the use of the Tool
cite	Bibtext of the Citation(s) to reference when using this Tool for a publication

Resource Reference

In this chapter we describe the different plugins bundled with Fastr (e.g. IOPlugins, ExecutionPlugins). The reference is build automatically from code, so after installing a new plugin the documentation has to be rebuild for it to be included in the docs.

CollectorPlugin Reference

CollectorPlugins are used for finding and collecting the output data of outputs part of a FastrInterface

scheme	CollectorPlugin
JsonCollector	<i>JsonCollector</i>
PathCollector	<i>PathCollector</i>
StdoutCollector	<i>StdoutCollector</i>

JsonCollector

The JsonCollector plugin allows a program to print out the result in a pre-defined JSON format. It is then used as values for fastr.

The working is as follows:

1. The location of the output is taken
2. If the location is `None`, go to step 5
3. The substitutions are performed on the location field (see below)
4. The location is used as a [regular expression](#) and matched to the `stdout` line by line
5. The matched string (or entire `stdout` if location is `None`) is [loaded as a json](#)
6. The data is parsed by `set_result`

The structure of the JSON has to follow the a predefined format. For normal `Nodes` the format is in the form:

```
[value1, value2, value3]
```

where the multiple values represent the cardinality.

For a `FlowNodes` the format is the form:

```
{
  'sample_id1': [value1, value2, value3],
  'sample_id2': [value4, value5, value6]
}
```

This allows the tool to create multiple output samples in a single run.

PathCollector

The PathCollector plugin for the FastrInterface. This plugin uses the location fields to find data on the filesystem. To use this plugin the method of the output has to be set to `path`

The general working is as follows:

1. The location field is taken from the output
2. The substitutions are performed on the location field (see below)
3. The updated location field will be used as a [regular expression](#) filter
4. The filesystem is scanned for all matching files/directory

The special substitutions performed on the location use the Format Specification Mini-Language [Format Specification Mini-Language](#). The predefined fields that can be used are:

- `inputs`, an objet with the input values (use like `{inputs.image[0]}`) The input contains the following attributes that you can access:
 - `.directory` for the directory name (use like `input.image[0].directory`) The directory is the same as the result of `os.path.dirname`
 - `.filename` is the result of `os.path.basename` on the path
 - `.basename` for the basename name (use like `input.image[0].basename`) The basename is the same as the result of `os.path.basename` and the extension stripped. The extension is considered to be everything after the first dot in the filename.

- .extension for the extension name (use like `input.image[0].extension`)
- output, an object with the output values (use like `{outputs.result[0]}`) It contains the same attributes as the input
 - `special.cardinality`, the index of the current cardinality
 - `special.extension`, is the extension for the output DataType

Example use:

```
<output ... method="path" location="{output.directory[0]}/TransformParameters.  
↪{special.cardinality}.{special.extension}" />
```

Given the output directory `./nodeid/sampleid/result`, the second sample in the output and filetype with a `.txt` extension, this would be translated into:

```
<output ... method="path" location="./nodeid/sampleid/result/TransformParameters.1.  
↪.txt" />
```

StdoutCollector

The StdoutCollector can collect data from the stdout stream of a program. It filters the `stdout` line by line matching a predefined regular expression.

The general working is as follows:

1. The location field is taken from the output
2. The substitutions are performed on the location field (see below)
3. The updated location field will be used as a `regular expression` filter
4. The `stdout` is scanned line by line and the `regular expression` filter is applied

The special substitutions performed on the location use the Format Specification Mini-Language [Format Specification Mini-Language](#). The predefined fields that can be used are:

- inputs, an object with the input values (use like `{inputs.image[0]}`)
- outputs, an object with the output values (use like `{outputs.result[0]}`)
- special which has two subfields:
 - `special.cardinality`, the index of the current cardinality
 - `special.extension`, is the extension for the output DataType

Note: because the plugin scans line by line, it is impossible to catch multi-line output into a single value

ExecutionPlugin Reference

This class is the base for all Plugins to execute jobs somewhere. There are many methods already in place for taking care of stuff.

There are fall-backs for certain features, but if a system already implements those it is usually preferred to skip the fall-back and let the external system handle it. There are a few flags to enable disable these features:

- `cls.SUPPORTS_CANCEL` indicates that the plugin can cancel queued jobs

- `cls.SUPPORTS_HOLD_RELEASE` indicates that the plugin can queue jobs in a hold state and can release them again (if not, the base plugin will create a hidden queue for held jobs). The plugin should respect the `Job.status == JobState.hold` when queueing jobs.
- `cls.SUPPORTS_DEPENDENCY` indicate that the plugin can manage job dependencies, if not the base plugin job dependency system will be used and jobs will only be submitted when all dependencies are met.
- `cls.CANCELS_DEPENDENCIES` indicates that if a job is cancelled it will automatically cancel all jobs depending on that job. If not the plugin traverse the dependency graph and kill each job manual.

Note: If a plugin supports dependencies it is assumed that when a job gets cancelled, the depending job also get cancelled automatically!

Most plugins should only need to redefine a few abstract methods:

- `__init__` the constructor
- `cleanup` a clean up function that frees resources, closes connections, etc
- `_queue_job` the method that queues the job for execution

Optionally an extra job finished callback could be added:

- `_job_finished` extra callback for when a job finishes

If `SUPPORTS_CANCEL` is set to True, the plugin should also implement:

- `_cancel_job` cancels a previously queued job

If `SUPPORTS_HOLD_RELEASE` is set to True, the plugin should also implement:

- `_hold_job` holds a job that is currently held
- `_release_job` releases a job that is currently held

If `SUPPORTED_DEPENDENCY` is set to True, the plugin should:

- Make sure to use the `Job.hold_jobs` as a list of its dependencies

Not all of the functions need to actually do anything for a plugin. There are examples of plugins that do not really need a `cleanup`, but for safety you need to implement it. Just using a `pass` for the method could be fine in such a case.

Warning: When overwriting other functions, extreme care must be taken not to break the plugins working, as there is a lot of bookkeeping that can go wrong.

<code>scheme</code>	<code>ExecutionPlugin</code>
<code>BlockingExecution</code>	<code>BlockingExecution</code>
<code>DRMAAExecution</code>	<code>DRMAAExecution</code>
<code>LinearExecution</code>	<code>LinearExecution</code>
<code>ProcessPoolExecution</code>	<code>ProcessPoolExecution</code>
<code>RQExecution</code>	<code>RQExecution</code>
<code>StrongrExecution</code>	<code>StrongrExecution</code>

BlockingExecution

The blocking execution plugin is a special plugin which is meant for debug purposes. It will not queue jobs but immediately execute them inline, effectively blocking fastr until the Job is finished. It is the simplest execution plugin

and can be used as a template for new plugins or for testing purposes.

DRMAAExecution

A DRMAA execution plugin to execute Jobs on a Grid Engine cluster. It uses a configuration option for selecting the queue to submit to. It uses the python drmaa package.

Note: To use this plugin, make sure the drmaa package is installed and that the execution is started on an SGE submit host with DRMAA libraries installed.

Note: This plugin is at the moment tailored to SGE, but it should be fairly easy to make different subclasses for different DRMAA supporting systems.

Configuration fields

name	type	description	default
drmaa_engine	str	The engine to use (options: grid_engine, torque)	'grid_engine'
drmaa_queue	str	The default queue to use for jobs send to the scheduler	'week'
drmaa_max_jobs	int	The maximum jobs that can be send to the scheduler at the same time (0 for no limit)	0

LinearExecution

An execution engine that has a background thread that executes the jobs in order. The queue is a simple FIFO queue and there is one worker thread that operates in the background. This plugin is meant as a fallback when other plugins do not function properly. It does not multi-processing so it is safe to use in environments that do not support that.

ProcessPoolExecution

A local execution plugin that uses multiprocessing to create a pool of worker processes. This allows fastr to execute jobs in parallel with true concurrency. The number of workers can be specified in the fastr configuration, but the default amount is the number of cores - 1 with a minimum of 1.

Warning: The ProcessPoolExecution does not check memory requirements of jobs and running many workers might lead to memory starvation and thus an unresponsive system.

Configuration fields

name	type	description	default
process_pool_worker_number	int	Number of workers to use in a process pool	3

RQExecution

A execution plugin based on Redis Queue. Fastr will submit jobs to the redis queue and workers will peel the jobs from the queue and process them.

This system requires a running redis database and the database url has to be set in the fastr configuration.

Note: This execution plugin required the `redis` and `rq` packages to be installed before it can be loaded properly.

Configuration fields

name	type	description	default
<code>rq_queue</code>	str	The redis queue to use	'default'
<code>rq_host</code>	str	The url of the redis serving the redis queue	'redis://localhost:6379/0'

StrongExecution

A execution plugin based on Redis Queue. Fastr will submit jobs to the redis queue and workers will peel the jobs from the queue and process them.

This system requires a running redis database and the database url has to be set in the fastr configuration.

Note: This execution plugin required the `redis` and `rq` packages to be installed before it can be loaded properly.

FlowPlugin Reference

Plugin that can manage an advanced data flow. The plugins override the execution of node. The execution receives all data of a node in one go, so not split per sample combination, but all data on all inputs in one large payload. The flow plugin can then re-order the data and create resulting samples as it sees fits. This can be used for all kinds of specialized data flows, e.g. cross validation.

To create a new FlowPlugin there is only one method that needs to be implemented: `execute`.

<code>scheme</code>	<code>FlowPlugin</code>
<code>CrossValidation</code>	<code>CrossValidation</code>

CrossValidation

Advanced flow plugin that generated a cross-validation data flow. The node need an input with data and an input number of folds. Based on that the outputs test and train will be supplied with a number of data sets.

IOPlugin Reference

IOPlugins are used for data import and export for the sources and sinks. The main use of the *IOPlugins* is during execution (see *Execution*). The *IOPlugins* can be accessed via `fastr.ioplugins`, but generally there should be no need for direct interaction with these objects. The use of is mainly via the URL used to specify source and sink data.

scheme	IOPPlugin
CommaSeperatedValueFile	<i>CommaSeperatedValueFile</i>
FileSystem	<i>FileSystem</i>
Null	<i>Null</i>
Reference	<i>Reference</i>
S3Filesystem	<i>S3Filesystem</i>
VirtualFileSystem	<i>VirtualFileSystem</i>
VirtualFileSystemRegularExpression	<i>VirtualFileSystemRegularExpression</i>
VirtualFileSystemValueList	<i>VirtualFileSystemValueList</i>
XNATStorage	<i>XNATStorage</i>

CommaSeperatedValueFile

The CommaSeperatedValueFile is an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs.

The `csv://` URL is a `vfs://` URL with a number of query variables available. The URL mount and path should point to a valid CSV file. The query variable then specifies what column(s) of the file should be used.

The following variable can be set in the query:

variable	usage
value	the column containing the value of interest, can be int for index or string for key
id	the column containing the sample id (optional)
header	indicates if the first row is considered the header, can be <code>true</code> or <code>false</code> (optional)
delimiter	the delimiter used in the csv file (optional)
quote	the quote character used in the csv file (optional)
reformat	a reformatting string so that <code>value = reformat.format(value)</code> (used before <code>relative_path</code>)
relative_path	indicates the entries are relative paths (for files), can be <code>true</code> or <code>false</code> (optional)

The header is by default `false` if neither the `value` and `id` are set as a string. If either of these are a string, the header is required to define the column names and it automatically is assumed `true`.

The delimiter and quote characters of the file should be detected automatically using the `Sniffer`, but can be forced by setting them in the URL.

Example of valid csv URLs:

```
# Use the first column in the file (no header row assumed)
csv://mount/some/dir/file.csv?value=0

# Use the images column in the file (first row is assumed header row)
csv://mount/some/dir/file.csv?value=images

# Use the segmentations column in the file (first row is assumed header row)
# and use the id column as the sample id
csv://mount/some/dir/file.csv?value=segmentations&id=id

# Use the first column as the id and the second column as the value
# and skip the first row (considered the header)
csv://mount/some/dir/file.csv?value=1&id=0&header=true

# Use the first column and force the delimiter to be a comma
csv://mount/some/dir/file.csv?value=0&delimiter=,
```

FileSystem

The FileSystem plugin is created to handle `file://` type or URLs. This is generally not a good practice, as this is not portable over between machines. However, for test purposes it might be useful.

The URL scheme is rather simple: `file://host/path` (see [wikipedia](#) for details)

We do not make use of the `host` part and at the moment only support localhost (just leave the host empty) leading to `file:///` URLs.

Warning: This plugin ignores the hostname in the URL and does only accept driver letters on Windows in the form `c:/`

Null

The Null plugin is created to handle `null://` type or URLs. These URLs are indicating the sink should not do anything. The data is not written to anywhere. Besides the scheme, the rest of the URL is ignored.

Reference

The Reference plugin is created to handle `ref://` type or URLs. These URLs are to make the sink just write a simple reference file to the data. The reference file contains the `DataType` and the `value` so the result can be reconstructed. It for files just leaves the data on disk by reference. This plugin is not useful for production, but is used for testing purposes.

S3Filesystem

Warning: As this IOPlugin is under development, it has not been thoroughly tested.

example url: `s3://bucket.server/path/to/resource`

VirtualFileSystem

The virtual file system class. This is an IOPlugin, but also heavily used internally in fastr for working with directories. The VirtualFileSystem uses the `vfs://` url scheme.

A typical virtual filesystem url is formatted as `vfs://mountpoint/relative/dir/from/mount.ext`

Where the `mountpoint` is defined in the [Config file](#). A list of the currently known mountpoints can be found in the `fastr.config` object

```
>>> fastr.config.mounts
{'example_data': '/home/username/fastr-feature-documentation/fastr/fastr/examples/data',
 'home': '/home/username/',
 'tmp': '/home/username/FastrTemp'}
```

This shows that a url with the mount `home` such as `vfs://home/tempdir/testfile.txt` would be translated into `/home/username/tempdir/testfile.txt`.

There are a few default mount points defined by Fastr (that can be changed via the config file).

mountpoint	default location
home	the users home directory (<code>expanduser('~/')</code>)
tmp	the fastr temporary dir, defaults to <code>tempfile.gettempdir()</code>
example_data	the fastr example data directory, defaults \$FASTRDIR/example/data

VirtualFileSystemRegularExpression

The VirtualFileSystemValueList an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs.

A `vfsregex://` URL is a vfs URL that can contain regular expressions on every level of the path. The regular expressions follow the `re module` definitions.

An example of a valid URLs would be:

```
vfsregex://tmp/network_dir/.*/.*/_fastr_result__.pickle.gz
vfsregex://tmp/network_dir/nodeX/(?P<id>.*)/_fastr_result__.pickle.gz
```

The first URL would result in all the `_fastr_result__.pickle.gz` in the working directory of a Network. The second URL would only result in the file for a specific node (nodeX), but by adding the named group `id` using `(?P<id>.*)` the sample id of the data is automatically set to that group (see [Regular Expression Syntax](#) under the special characters for more info on named groups in regular expression).

Concretely if we would have a directory `vfs://mount/somedir` containing:

```
image_1/Image.nii
image_2/image.nii
image_3/anotherimage.nii
image_5/inconsistentnamingftw.nii
```

we could match these files using `vfsregex://mount/somedir/(?P<id>image_\d+)/.*\.nii` which would result in the following source data after expanding the URL:

```
{'image_1': 'vfs://mount/somedir/image_1/Image.nii',
'image_2': 'vfs://mount/somedir/image_2/image.nii',
'image_3': 'vfs://mount/somedir/image_3/anotherimage.nii',
'image_5': 'vfs://mount/somedir/image_5/inconsistentnamingftw.nii'}
```

Showing the power of this regular expression filtering. Also it shows how the ID group from the URL can be used to have sensible sample ids.

Warning: due to the nature of regexp on multiple levels, this method can be slow when having many matches on the lower level of the path (because the tree of potential matches grows) or when directories that are parts of the path are very large.

VirtualFileSystemValueList

The VirtualFileSystemValueList an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs. A `vfslis://` URL basically is a url that points to a file using vfs. This file then contains a number lines each containing another URL.

If the contents of a file `vfs://mount/some/path/contents` would be:

```
vfs://mount/some/path/file1.txt
vfs://mount/some/path/file2.txt
vfs://mount/some/path/file3.txt
vfs://mount/some/path/file4.txt
```

Then using the URL `vfslist://mount/some/path/contents` as source data would result in the four files being pulled.

Note: The URLs in a `vfslist` file do not have to use the `vfs` scheme, but can use any scheme known to the Fastr system.

XNATStorage

Warning: As this IOPlugin is under development, it has not been thoroughly tested.

The XNATStorage plugin is an IOPlugin that can download data from and upload data to an XNAT server. It uses its own `xnat://` URL scheme. This is a scheme specific for this plugin and though it looks somewhat like the XNAT rest interface, a different type or URL.

Data resources can be access directly by a data url:

```
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/experiments/
  ↪experiment001/scans/T1/resources/DICOM
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/experiments/
  ↪*_BRAIN/scans/T1/resources/DICOM
```

In the second URL you can see a wildcard being used. This is possible at long as it resolves to exactly one item.

The `id` query element will change the field from the default experiment to subject and the `label` query element sets the use of the label as the fastr id (instead of the XNAT id) to True (the default is False)

To disable `https` transport and use `http` instead the query string can be modified to add `insecure=true`. This will make the plugin send requests over `http`:

```
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/experiments/
  ↪*_BRAIN/scans/T1/resources/DICOM?insecure=true
```

For sinks it is import to know where to save the data. Sometimes you want to save data in a new assessor/resource and it needs to be created. To allow the Fastr sink to create an object in XNAT, you have to supply the type as a query parameter:

```
xnat://xnat.bmia.nl/data/archive/projects/sandbox/subjects/S01/experiments/_BRAIN/
  ↪assessors/test_assessor/resources/IMAGE/files/image.nii.gz?resource_
  ↪type=xnat:resourceCatalog&assessor_type=xnat:qcAssessmentData
```

Valid options are: `subject_type`, `experiment_type`, `assessor_type`, `scan_type`, and `resource_type`.

If you want to do a search where multiple resources are returned, it is possible to use a search url:

```
xnat://xnat.example.com/search?projects=sandbox&subjects=subject[0-9][0-9][0-9]&
  ↪experiments=*_BRAIN&scans=T1&resources=DICOM
```

This will return all DICOMs for the T1 scans for experiments that end with _BRAIN that belong to a subjectXXX where XXX is a 3 digit number. By default the ID for the samples will be the experiment XNAT ID (e.g. XNAT_E00123). The wildcards that can be used are the same UNIX shell-style wildcards as provided by the module `fnmatch`.

It is possible to change the id to a different fields id or label. Valid fields are project, subject, experiment, scan, and resource:

```
xnat://xnat.example.com/search?projects=sandbox&subjects=subject[0-9][0-9][0-9]&  
→experiments=*_BRAIN&scans=T1&resources=DICOM&id=subject&label=true
```

The following variables can be set in the search query:

variable	default	usage
projects	*	The project(s) to select, can contain wildcards (see <code>fnmatch</code>)
subjects	*	The subject(s) to select, can contain wildcards (see <code>fnmatch</code>)
experiments	*	The experiment(s) to select, can contain wildcards (see <code>fnmatch</code>)
scans	*	The scan(s) to select, can contain wildcards (see <code>fnmatch</code>)
resources	*	The resource(s) to select, can contain wildcards (see <code>fnmatch</code>)
id	experiment	What field to use as the id, can be: project, subject, experiment, scan, or resource
label	false	Indicate the XNAT label should be used as fastr id, options true or false
insecure	false	Change the url scheme to be used to http instead of https
verify	true	(Dis)able the verification of SSL certificates
regex	false	Change search to use regex <code>re.match()</code> instead of fnmatch for matching
overwrite	false	Tell XNAT to overwrite existing files if a file with the name is already present

For storing credentials the `.netrc` file can be used. This is a common way to store credentials on UNIX systems. It is required that the file is only accessible by the owner only or a `NetrcParseError` will be raised. A `netrc` file is really easy to create, as its entries look like:

```
machine xnat.example.com  
login username  
password secret123
```

See the `netrc` module or the [GNU inet utils](#) website for more information about the `.netrc` file.

Note: On windows the location of the netrc file is assumed to be `os.path.expanduser('~/_.netrc')`. The leading underscore is because windows does not like filename starting with a dot.

Note: For scan the label will be the scan type (this is initially the same as the series description, but can be updated manually or the XNAT scan type cleanup).

Warning: labels in XNAT are not guaranteed to be unique, so be careful when using them as the sample ID.

For background on XNAT, see the [XNAT API DIRECTORY](#) for the REST API of XNAT.

Interface Reference

Abstract base class of all Interfaces. Defines the minimal requirements for all Interface implementations.

scheme	Interface
FastrInterface	<i>FastrInterface</i>
FlowInterface	<i>FlowInterface</i>
NipypeInterface	<i>NipypeInterface</i>

FastrInterface

The default Interface for fastr. For the command-line Tools as used by fastr. It build a commandline call based on the input/output specification.

The fields that can be set in the interface:

Attribute	Description
<code>id</code>	The id of this Tool (used internally in fastr)
<code>inputs[]</code>	List of Inputs that can are accepted by the Tool
	<code>id</code> ID of the Input
	<code>name</code> Longer name of the Input (more human readable)
	<code>datatype</code> The ID of the DataType of the Input ¹
	<code>enum[]</code> List of possible values for an EnumType (created on the fly by fastr) ¹
	<code>prefix</code> Commandline prefix of the Input (e.g. <code>-in</code> , <code>-i</code>)
	<code>cardinality</code> Cardinality of the Input
	<code>repeat_prefix</code> Flag indicating if for every value of the Input the prefix is repeated
	<code>required</code> Flag indicating if the input is required
	<code>nospace</code> Flag indicating if there is no space between prefix and value (e.g. <code>-in=val</code>)
	<code>format</code> For DataTypes that have multiple representations, indicate which one to use
	<code>default</code> Default value for the Input
	<code>description</code> Long description for an input
<code>outputs[]</code>	List of Outputs that are generated by the Tool (and accessible to fastr)
	<code>id</code> ID of the Output
	<code>name</code> Longer name of the Output (more human readable)
	<code>datatype</code> The ID of the DataType of the Output ¹
	<code>enum[]</code> List of possible values for an EnumType (created on the fly by fastr) ¹
	<code>prefix</code> Commandline prefix of the Output (e.g. <code>-out</code> , <code>-o</code>)
	<code>cardinality</code> Cardinality of the Output
	<code>repeat_prefix</code> Flag indicating if for every value of the Output the prefix is repeated
	<code>required</code> Flag indicating if the input is required
	<code>nospace</code> Flag indicating if there is no space between prefix and value (e.g. <code>-out=val</code>)
	<code>format</code> For DataTypes that have multiple representations, indicate which one to use
	<code>description</code> Long description for an input
	<code>action</code> Special action (defined per DataType) that needs to be performed before creating output value
	<code>automatic</code> Indicate that output doesn't require commandline argument, but is created automatically by a T
	<code>method</code> The collector plugin to use for the gathering automatic output, see the Collector plugins
	<code>location</code> Definition where to an automatically, usage depends on the method ²

FlowInterface

The Interface use for AdvancedFlowNodes to create the advanced data flows that are not implemented in the fastr. This allows nodes to implement new data flows using the plugin system.

The definition of FlowInterfaces are very similar to the default FastrInterfaces.

¹ datatype and enum are conflicting entries, if both specified datatype has precedence

² More details on defining automatica output are given in [TODO]

Note: A flow interface should be using a specific FlowPlugin

NipypeInterface

Experimental interfaces to using nipype interfaces directly in fastr tools, only using a simple reference.

To create a tool using a nipype interface just create an interface with the correct type and set the nipype argument to the correct class. For example in an xml tool this would become:

```
<interface class="NipypeInterface">
  <nipype_class>nipype.interfaces.elastix.Registration</nipype_class>
</interface>
```

Note: To use these interfaces nipype should be installed on the system.

Warning: This interface plugin is basically functional, but highly experimental!

Target Reference

The abstract base class for all targets. Execution with a target should follow the following pattern:

```
>>> with Target() as target:
...     target.run_command(['sleep', '10'])
...     target.run_command(['sleep', '10'])
...     target.run_command(['sleep', '10'])
```

The Target context operator will set the correct paths/initialization. Within the context command can be ran and when leaving the context the target reverts the state before.

scheme	Target
DockerTarget	<i>DockerTarget</i>
LocalBinaryTarget	<i>LocalBinaryTarget</i>

DockerTarget

A tool target that is located in a Docker images. Can be run using docker-py. A docker target only need two variables: the binary to call within the docker container, and the docker container to use.

```
{
  "arch": "*",
  "os": "*",
  "binary": "bin/test.py",
  "docker_image": "fastr/test"
}
```

```
<target os="*" arch="*" binary="bin/test.py" docker_image="fastr/test">
```

LocalBinaryTarget

A tool target that is a local binary on the system. Can be found using environmentmodules or a path on the executing machine. A local binary target has a number of fields that can be supplied:

- **binary** (required): the name of the binary/script to call, can also be called `bin` for backwards compatibility.
- **modules**: list of modules to load, this can be environmentmodules or lmod modules. If modules are given, the paths, environment_variables and initscripts are ignored.
- **paths**: a list of paths to add following the structure `{"value": "/path/to/dir", "type": "bin"}`. The types can be `bin` if the it should be added to `$PATH` or `lib` if it should be added to the library path (e.g. `$LD_LIBRARY_PATH` for linux).
- **environment_variables**: a dictionary of environment variables to set.
- **initscript**: a list of script to run before running the main tool
- **interpreter**: the interpreter to use to call the binary e.g. `python`

The LocalBinaryTarget will first check if there are modules given and the module subsystem is loaded. If that is the case it will simply unload all current modules and load the given modules. If not it will try to set up the environment itself by using the following steps:

1. Prepend the bin paths to `$PATH`
2. Prepend the lib paths to the correct environment variable
3. Setting the other environment variables given (`$PATH` and the system library path are ignored and cannot be set that way)
4. Call the initscripts one by one

The definition of the target in JSON is very straightforward:

```
{
  "binary": "bin/test.py",
  "interpreter": "python",
  "paths": [
    {
      "type": "bin",
      "value": "vfs://apps/test/bin"
    },
    {
      "type": "lib",
      "value": "./lib"
    }
  ],
  "environment_variables": {
    "othervar": 42,
    "short_var": 1,
    "testvar": "value1"
  },
  "initscripts": [
    "bin/init.sh"
  ],
  "modules": ["elastix/4.8"]
}
```

In XML the definition would be in the form of:


```
<target os="linux" arch="*" modules="elastix/4.8" bin="bin/test.py" interpreter=
  ↵ "python">
  <paths>
    <path type="bin" value="vfs://apps/test/bin" />
    <path type="lib" value=".lib" />
  </paths>
  <environment_variables short_var="1">
    <testvar>value1</testvar>
    <othervar>42</othervar>
  </environment_variables>
  <initscripts>
    <initscript>bin/init.sh</initscript>
  </initscripts>
</target>
```

Development and Design Documentation


In this chapter we will discuss the design of Fastr in more detail. We give pointers for development and add the design documents as we currently envision Fastr. This is both for people who are interested in the Fastr develop and for current developers to have an archive of the design decision agreed upon.

Sample flow in Fastr

The current Sample flow is the following:



The idea is that we make a common interface for all classes that are related to the flow of Samples. For this we propose the following mixin classes that provide the interface and allow for better code sharing. The basic structure of the classes is given in the following diagram:



The abstract and mixin methods are as follows:

ABC	Inherits from	Abstract Methods	Mixin methods
HasDimensions		dimensions	size dimnames
HasSamples	HasDimensions	__getitem__	__contains__ __iter__ iteritems items indexes ids
ContainsSamples	HasSamples	samples	__getitem__ __setitem__ dimensions
ForwardsSamples	HasSamples	source index_to_target index_to_source combine_samples combine_dimensions	__getitem__ dimensions

Note: Though the flow is currently working like this, the mixins are not yet created.


Network Execution

The network execution should contain a number of steps:

- Network
 - Creates a NetworkRun based on the current layout
- NetworkRun
 - Transform the Network (possibly joining Nodes of certain interface into a combined NodeRun etc)
 - Start generation of the Job Direct Acyclic Graph (DAG)
- SchedulingPlugin
 - Prioritize Jobs based on some predefined rules
 - Combine certain Jobs to improve efficiency (e.g. minimize i/o on a grid)
- ExecutionPlugin
 - Run a (list of) Jobs. If there is more than one jobs, run them sequentially on same execution host using a local temp for intermediate files.

- On finished callback: Updated DAG with newly ready jobs, or remove cancelled jobs

This could be visualized as the following loop:



The callback of the `ExecutionPlugin` to the `NetworkRun` would trigger the execution of the relevant `NodeRuns` and the addition of more `Jobs` to the `JobDAG`.

Note: The Job DAG should be thread-safe as it could be both read and extended at the same time.

Note: If a list of jobs is send to the `ExecutionPlugin` to be run as on Job on an external execution platform, the resources should be combined as follows: `memory=max`, `cores=max`, `runtime=sum`

Note: If there are execution hosts that have multiple cores the `ExecutionPlugin` should manage this (for example by using pilot jobs). The `SchedulingPlugin` creates units that should be run sequentially on the resources noted and will not attempt parallelization

A `NetworkRun` would contain similar information as the `Network` but not have functionality for editing/changing it. It would contain the functionality to execute the `Network` and track the status and samples. This would allow `Network.execute` to create multiple concurrent runs that operate independent of each other. Also editing a `Network` after the run started would have no effect on that run.

Note: This is a plan, not yet implemented

Note: For this to work, it would be important for a Jobs to have forward and backward dependency links.

SchedulingPlugins

The idea of the plugin is that it would give a priority on Jobs created by a `Network`. This could be done based on different strategies:

- Based on (sorted) sample id's, so that one sample is always prioritized over others. The idea is that samples are processed as much as possible in order, finishing the first sample first. Only processing other samples if there is left-over capacity.
- Based on distance to a (particular) `Sink`. This is to generate specific results as quick as possible. It would not focus on specific samples, but give priority to whatever sample is closest to being finished.
- Based on the distance to from a `Source`. Based on the sign of the weight it would either keep all samples on the same stage as much as possible, only progressing to a new `NodeRun` when all samples are done with the previous `NodeRun`, or it would push samples with accelerated rates.

Additionally it will group Jobs to be executed on a single host. This could reduce i/o and limit the number of jobs an external scheduler has to track.

Note: The interface for such a plugin has not yet been established.

Secrets

“Something that is kept or meant to be kept unknown or unseen by others.”

Using secrets

Fastr IOPlugins that need authentication data should use the Fastr SecretService for retrieving such data. The SecretService can be used as follows.

```
from fastr.utils.secrets import SecretService
from fastr.utils.secrets.exceptions import CouldNotRetrieveCredentials

secret_service = SecretService()

try:
    password = secret_service.find_password_for_user('testserver.lan:9000', 'john-doe')
except CouldNotRetrieveCredentials:
    # the password was not found
    pass
```

Implementing a SecretProvider

A SecretProvider is implemented as follows:

1. Create a file in fastr/utils/secrets/providers/<yourprovidername>.py
2. Use the template below to write your SecretProvider
3. Add the secret provider to fastr/utils/secrets/providers/__init__.py
4. Add the secret provider to fastr/utils/secrets/secretservice.py: import it and add it to the array in function __init_providers

```
from fastr.utils.secrets.secretprovider import SecretProvider
from fastr.utils.secrets.exceptions import CouldNotRetrieveCredentials, \
    CouldNotSetCredentials, CouldNotDeleteCredentials, NotImplemented

try:
    # this is where libraries can be imported
    # we don't want fastr to crash if a specific
    # library is unavailable
    # import my-library
except (ImportError, ValueError) as e:
    pass

class KeyringProvider(SecretProvider):
    def __init__(self):
        # if libraries are imported in the code above
        # we need to check if import was successful
        # if it was not, raise a RuntimeError
        # so that FASTR ignores this SecretProvider
        # if 'my-library' not in globals():
        #     raise RuntimeError("my-library module required")
        pass

    def get_password_for_user(self, machine, username):
        # This function should return the password as a string
        # or raise a CouldNotRetrieveCredentials error if the password
        # is not found.
        # In the event that this function is unsupported a
        # NotImplemented exception should be thrown
```

```

raise NotImplemented()

def set_password_for_user(self, machine, username, password):
    # This function should set the password for a specified
    # machine + user. If anything goes wrong while setting
    # the password a CouldNotSetCredentials error should be raised.
    # In the event that this function is unsupported a
    # NotImplemented exception should be thrown
    raise NotImplemented()

def del_password_for_user(self, machine, username):
    # This function should delete the password for a specified
    # machine + user. If anything goes wrong while setting
    # the password a CouldNotDeleteCredentials error should be raised.
    # In the event that this function is unsupported a
    # NotImplemented exception should be thrown
    raise NotImplemented()

```

Changelog

All notable changes to this project will be documented in this file.

The format is based on [Keep a Changelog](#) and this project adheres to [Semantic Versioning](#)

2.0.0 - 28-09-2017

Added

- The default python logger can now be configured from the fastr config file under key logging_config
- Support for MacroNodes, a Network can be used as a Node inside of another Network. There is should be no limitation on the internal Network used, but currently the MacroNode ignores input_groups on its inputs.
- A sync helper was added to assist in slow file synchronisation over NFS
- Source and Sink can now handle S3 URL's
- FastrInterface can now forward errors from a subprocess if they are dumped to stdout or stderr in a json identified by __FASTR_ERRORS__ = [] .
- A specials.workdir field in the location field of automatic outputs that gives the current working directory (e.g. job directory)
- Added support for Torque (using pbs-drmaa library) to DRMAAExecution
- Added option to set a limit for number of jobs submitted at same time be the DRMAAExecution
- Use of the ~/fastr/config.d directory for adding additional config files. Any .py file in there will be parsed in alphabetical order.
- XNATStorage IOPlugin now has a retry scheme for uploads, if an uploaded file could not be found on the server, it is retried up to 3 times.
- Added fastr dump command to create a zip containing all important debugging information.

Changed

- FilePrefix type does not have an extension anymore (avoids ugly dot in middle of filename)
- Allow expanding of link where samples have a non-uniform cardinality. This will not result in a sparse array.
- The default for `required` for the automatic outputs is now `False`
- Removed `testtool` commandline subcommand in favour of the `test` subcommand which can test both Tools and Networks
- Moved nodegroup specification into the Node for speedup

Fixed

- Stop Jobs from failing when a non-required, non-requested output is invalid
- Bug in boolean value parsing in the Boolean datatype
- Bug in target that caused paths not to be expanded properly in some cases
- Made sure failed sources also create a sample so the failure becomes visible and traceable.
- Bug in XNAT IOPlugin that made download from XNAT seem to fail (while getting the correct data).

Removed

- `fastr.current_network` has been removed as it was deemed to “magical” and could change things out of the sight of the user.

1.2.2 - 2017-08-24

Fixed

- Fixed a bug breaking the XNAT IOPlugin due to an `xnatpy` version update.

1.2.1 - 2017-04-04

Added

- A FastrInterface can now specify a `negate` flag on an automatic output that also has a prefix, which will negate the flag. This is useful for flag the suppress the creation of an output (e.g. `no_mask`). An example is given in the Tool `fastr.util.AutoPrefixNegateTest`.

Changed

- The provenance and extra information of a Job now is not serialized in the Job, but exported to separate files next to the job file `__fastr_prov__.json` and `__fastr_extra_job_info__.json` which makes the information more accessible and reduces the memory footprint of the main process hugely as it will not read this information back anymore.
- Most execution plugin will not overwrite the executionscript `stdout` and `stderr` but rather append it. This is only relevant when continuing a run in the an existing temporary directory, but avoids loss of information.

Fixed

- Bug that stopped the `Link.append` function from returning the newly created link
- Bugs that caused some cardinality computations of the output to fail during execution
- Bug in the `job.tmpurl` that caused double slashes somewhere. Some tools chocked on this when it was used for parameters.

1.2.0 - 2017-03-15

Added

- Failed sample annotation: when a job fails, the result is annotated and forwarded until a `SinkNode`, where we can determine the status and possibly point of failure of the Sample.
- Commandline tool `fastr trace` that can inspect a workflow run and help trace errors and print debug information
- Supported for Lmod modules environment next to the old environmentmodules
- `BaseDataType` descendants are now (un)picklable (including `EnumTypes`)
- Option to use `{extension}` field in `sink_data`, which differs from `{ext}` in that it doesn't include a leading dot.
- Support for Docker targets. A Docker target will execute a command inside of a specified docker container, allowing Tools to use Docker for distribution
- Using the right and left shift operator (`<<` and `>>`) for creating links to `Inputs` using `input << output` or `output >> input`.
- In the `FastrInterfaces`, automatic outputs can have a prefix for a flag that should be set for the output to be actually generated.
- Fastr is now able to limit the amount of `SourceJobs` that are allowed to run concurrently.
- Ability to report progress to PIM (use the `pim_host` field in the config)

Changed

- Version can now also accept a format based on a date (e.g. `2017-02-17_bananas`) which will be parsed the same way as `2017.02.17_bananas`
- Work on the `ExecutionPlugin` and the corresponding API. Has better fall-backs and a mechanism to advertise plugin capabilities.
- The collector plugins have the `input` and `input_parts` fields merged, and the `output` and `output_parts` fields merged.

Fixed

- In some cases the log directory was not created properly, causing an handled exception
- A bug making the handling of Booleans incorrect for the `FastrInterface`, when a Boolean was given a flag would also appear when it was `False`
- Serialization of the namespace of a Network was not correct

- Check version of Fastr that creates and executes a Job against each other
- load_gpickle helper can handle data with Enums that use to cause an AttributeError
- Output validation of Jobs did not work correctly for automatic outputs

1.1.2 - 2016-12-22

Fixed

- The example network in resources/networks/add_ints.json was using an old serialization format making it non-functions. Replaced by a new network file.

1.1.1 - 2016-12-22

Fixed

- Network runs called from an interpreter (and not file) caused a crash because the network tried to report the file used. Better handling of these situations.

1.1.0 - 2016-12-08

Added

- Namespaces for resources (tools and networks)
- Network manager located at `fastr.networklist`
- RQExecution plugin. This plugin uses python-rq to manage a job queue.
- LinearExecution plugin. This plugin uses a background thread for execution.
- BlockingExecution plugin. This plugin executes jobs in a blocking fashion.
- Automatic generation of documentation for all plugins, the configuration fields and all commandline tools.

Changed

- Provenance is updated with a network dump and used tool definitions.
- New configuration system that uses python files
- New plugin system that integrates with the new configuration system and enables automatic importing of plugins
- The fastr command line tools now use an entrypoint which is located in `fastr.utils.cmd`. This code also dispatches the sub commands.

Removed

- `fastr.config` file. This is replaced by the `config.py` file. Go to the docs!

Fixed

- Adds explicit tool namespace and version to the provenance document.

CHAPTER 2

FASTR User reference

Fastr User Reference

fastr.toollist

A ToolManager containing all versions of all Tools loaded into the FASTR environment. The ToolManager can be indexed using the Tool id string or a tool id string and a version. For example if you have two versions (4.5 and 4.8) of a tool called *Elastix*:

```
>>> fastr.toollist['elastix.Elastix']
Tool Elastix v4.8 (Elastix Registration)
    Inputs | |
    ↵Outputs | |
-----| |
fixed_image      (ITKImageFile) | directory_
    ↵(Directory) | |
moving_image     (ITKImageFile) | transform_
    ↵(ElastixTransformFile) | |
parameters       (ElastixParameterFile) | log_file_
    ↵(ElastixLogFile) | |
fixed_mask       (ITKImageFile) | |
moving_mask      (ITKImageFile) | |
initial_transform (ElastixTransformFile) | |
priority         (__Elastix_4.8_interface_priority__Enum__)
threads          (Int) | |
```



```
>>> fastr.toollist['elastix.Elastix', '4.5']
Tool Elastix v4.5 (Elastix Registration)
    Inputs | |
    ↵Outputs | |
-----| |
fixed_image      (ITKImageFile) | directory_
    ↵(Directory) | |
```

moving_image	(ITKImageFile)	transform
↳ (ElastixTransformFile)		
parameters	(ElastixParameterFile)	log_file
↳ (ElastixLogFile)		
fixed_mask	(ITKImageFile)	
moving_mask	(ITKImageFile)	
initial_transform	(ElastixTransformFile)	
priority	(__Elastix_4.5_interface_priority__Enum__)	
threads	(Int)	

fastr.typeList

A dictionary containing all types loaded into the FASTR environment. The keys are the typenames and the values are the classes.

class fastr.Network (*id_=’unnamed_network’, version=None, filename=None*)

The NetworkRun contains the entire Run state for a Network execution. It has a working copy of the network, but also includes all temporary data required for the execution. These objects are meant to be single use.

add_link (*link*)

Add a Link to the Network. Make sure the link is in the link list and the link parent is set to this Network

Parameters **link** (*Link*) – link to add

Raises

- **FastrTypeError** – if link is incorrectly typed
- **FastrNetworkMismatchError** – if the link already belongs to another Network

add_node (*node*)

Add a Node to the Network. Make sure the node is in the node list and the node parent is set to this Network

Parameters **node** (*Node*) – node to add

Raises **FastrTypeError** – if node is incorrectly typed

create_link (*source, target, id_=None, collapse=None, expand=None*)

Create a link between two Nodes and add it to the current Network.

Parameters

- **source** (*BaseOutput*) – the output that is the source of the link
- **target** (*BaseInput*) – the input that is the target of the link
- **id** (*str*) – the id of the link

Returns the created link

Type *Link*

create_node (*tool, id_=None, stepid=None, cores=None, memory=None, walltime=None, node-group=None*)

Create a Node in this Network. The Node will be automatically added to the Network.

Parameters

- **tool** (*Tool*) – The Tool to base the Node on
- **id** (*str*) – The id of the node to be created
- **stepid** (*str*) – The stepid to add the created node to

- **nodegroup** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Returns the newly created node

Return type *Node*

create_sink (*datatype*, *id_=None*, *stepid=None*)

Create a SinkNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (*BaseDataType*) – The DataType of the sink node
- **id** (*str*) – The id of the sink node to be created
- **stepid** (*str*) – The stepid to add the created sink node to

Returns the newly created sink node

Return type *SinkNode*

create_source (*datatype*, *id_=None*, *stepid=None*, *nodegroup=None*, *sourcegroup=None*)

Create a SourceNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (*BaseDataType*) – The DataType of the source source_node
- **id** (*str*) – The id of the source source_node to be created
- **stepid** (*str*) – The stepid to add the created source source_node to
- **nodegroup** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.
- **sourcegroup** (*str*) – *DEPRECATED!* The nodegroup this SourceNode will be added to

Returns the newly created source source_node

Return type *SourceNode*

draw_network (*name='network_layout'*, *img_format='svg'*, *draw_dimension=False*, *expand_macro=False*)

Output a dot file and try to convert it to an image file.

Parameters **img_format** (*str*) – extension of the image format to convert to

Returns path of the image created or None if failed

Return type *str* or *None*

class *fastr.Link* (*source*, *target*, *parent*, *id_=None*, *collapse=None*, *expand=None*)

Class for linking outputs (*BaseOutput*) to inputs (*BaseInput*)

Examples:

```
>>> import fastr
>>> network = fastr.Network()
>>> link1 = network.create_link( n1.outputs['out1'], n2.inputs['in2'] )

link2 = Link()
link2.source = n1.outputs['out1']
link2.target = n2.inputs['in2']
```

source

The source *BaseOutput* of the Link. Setting the source will automatically register the Link with the source BaseOutput. Updating source will also make sure the Link is unregistered with the previous source.

Raises *FastrTypeError* – if assigning a non *BaseOutput*

target

The target *BaseInput* of the Link. Setting the target will automatically register the Link with the target BaseInput. Updating target will also make sure the Link is unregistered with the previous target.

Raises *FastrTypeError* – if assigning a non *BaseInput*

CHAPTER 3

FASTR Developer Module reference

fastr Package

fastr Package

FASTR is a top level package which includes all parts required to create networks and edit networks.

class fastr.__init__.Network

The class representing a Network, this is in fact a reference to `fastr.core.network.Network`.

class fastr.__init__.NodeRun

The class representing a NodeRun, this is in fact a reference to `fastr.core.node.NodeRun`.

class fastr.__init__.Link

The class representing a Link, this is in fact a reference to `fastr.core.link.Link`.

class fastr.__init__.SourceNodeRun

The class representing a data source, this is in fact a reference to `fastr.core.node.SourceNodeRun`.

class fastr.__init__.SinkNodeRun

The class representing a data sink, this is in fact a reference to `fastr.core.node.SinkNodeRun`.

class fastr.__init__.ConstantNodeRun

The class representing a constant data source, this is in fact a reference to `fastr.core.node.ConstantNodeRun`.

fastr.__init__.toollist

A `fastr.core.toolmanager.ToolManager` containing all Tools known to the FASTR environment. The toollist can be accessed in a similar way to a dict. Indexing with a tool id will return the newest version of the Tool. If a specific version of the tool is required a tuple can be used as the index:

```
>>> import fastr
>>> fastr.toollist['testtool']
<Tool: testtool version: 4.2>
>>> fastr.toollist['testtool', '2.0']
<Tool: testtool version: 2.0>
```

`fastr.__init__.typelist`

A `fastr.core.datatypemanager.DataTypeManager` containing all Types known to the FASTR environment. This is usable as a dict where the key is the datatype id and the value is the datatype itself.

`class fastr.__init__.Network (id_='unnamed_network', version=None, filename=None)`

Bases: `fastr.core.serializable.Serializable`

The NetworkRun contains the entire Run state for a Network execution. It has a working copy of the network, but also includes all temporary data required for the execution. These objects are meant to be single use.

`NETWORK_DUMP_FILE_NAME = '__fastr_network__.json'`

`SINK_DUMP_FILE_NAME = '__sink_data__.json'`

`SOURCE_DUMP_FILE_NAME = '__source_data__.pickle.gz'`

`__dataschemafile__ = 'Network.schema.json'`

`__eq__ (other)`

Compare two Networks and see if they are equal.

Parameters `other` (`Network`) –

Returns flag indicating that the Networks are the same

Return type `bool`

`__getitem__ (item)`

Get an item by its fullid. The fullid can point to a link, node, input, output or even subinput/suboutput.

Parameters `item` (`str, unicode`) – fullid of the item to retrieve

Returns the requested item

`__getstate__ ()`

Retrieve the state of the Network

Returns the state of the object

Rtype `dict`

`__init__ (id_='unnamed_network', version=None, filename=None)`

Create a new, empty Network

Parameters `name` (`str`) – name of the Network

Returns newly created Network

Raises `OSError` – if the tmp mount in the config is not a writable directory

`__module__ = 'fastr.core.network'`

`__ne__ (other)`

Tests for non-equality, this is the negated version `__eq__`

`__repr__ ()`

`__setstate__ (state)`

Set the state of the Network by the given state. This completely overwrites the old state!

Parameters `state` (`dict`) – The state to populate the object with

Returns None

`add_link (link)`

Add a Link to the Network. Make sure the link is in the link list and the link parent is set to this Network

Parameters `link` (`Link`) – link to add

Raises

- **FastrTypeError** – if link is incorrectly typed
- **FastrNetworkMismatchError** – if the link already belongs to another Network

add_node(node)

Add a Node to the Network. Make sure the node is in the node list and the node parent is set to this Network

Parameters **node** (*Node*) – node to add

Raises **FastrTypeError** – if node is incorrectly typed

add_stepid(stepid, node)

Add a Node to a specific step id

Parameters

- **stepid** (*str*) – the stepid that the node will be added to
- **node** (*Node*) – the node to add to the stepid

check_id(id_)

Check if an id for an object is valid and unused in the Network. The method will always return True if it does not raise an exception.

Parameters **id** (*str*) – the id to check

Returns True

Raises

- **FastrValueError** – if the id is not correctly formatted
- **FastrValueError** – if the id is already in use

create_constant(datatype, data, id_=None, stepid=None, nodegroup=None, sourcegroup=None)

Create a ConstantNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (*BaseDataType*) – The DataType of the constant node
- **data** (*datatype or list of datatype*) – The data to hold in the constant node
- **id** (*str*) – The id of the constant node to be created
- **stepid** (*str*) – The stepid to add the created constant node to
- **nodegroup** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Returns the newly created constant node

Return type *ConstantNode*

create_link(source, target, id_=None, collapse=None, expand=None)

Create a link between two Nodes and add it to the current Network.

Parameters

- **source** (*BaseOutput*) – the output that is the source of the link
- **target** (*BaseInput*) – the input that is the target of the link
- **id** (*str*) – the id of the link

Returns the created link

Type [Link](#)

create_macro (*network*, *id*=*None*)

create_node (*tool*, *id*=*None*, *stepid*=*None*, *cores*=*None*, *memory*=*None*, *walltime*=*None*, *nodemgroup*=*None*)

Create a Node in this Network. The Node will be automatically added to the Network.

Parameters

- **tool** ([Tool](#)) – The Tool to base the Node on
- **id** ([str](#)) – The id of the node to be created
- **stepid** ([str](#)) – The stepid to add the created node to
- **nodegroup** ([str](#)) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Returns the newly created node

Return type [Node](#)

create_reference (*source_data*, *output_directory*)

create_sink (*datatype*, *id*=*None*, *stepid*=*None*)

Create a SinkNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** ([BaseDataType](#)) – The DataType of the sink node
- **id** ([str](#)) – The id of the sink node to be created
- **stepid** ([str](#)) – The stepid to add the created sink node to

Returns the newly created sink node

Return type [SinkNode](#)

create_source (*datatype*, *id*=*None*, *stepid*=*None*, *nodegroup*=*None*, *sourcegroup*=*None*)

Create a SourceNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** ([BaseDataType](#)) – The DataType of the source source_node
- **id** ([str](#)) – The id of the source source_node to be created
- **stepid** ([str](#)) – The stepid to add the created source source_node to
- **nodegroup** ([str](#)) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.
- **sourcegroup** ([str](#)) – *DEPRECATED!* The nodegroup this SourceNode will be added to

Returns the newly created source source_node

Return type [SourceNode](#)

draw (*name*=*None*, *image_format*=*None*, *draw_dimensions*=*False*, *context*=*None*, *graph*=*None*, *expand_macro*=*False*)

draw_network (*name*=’*network_layout*’, *img_format*=’*svg*’, *draw_dimension*=*False*, *expand_macro*=*False*)

Output a dot file and try to convert it to an image file.

Parameters **img_format** ([str](#)) – extension of the image format to convert to

Returns path of the image created or None if failed

Return type str or None

execute (*sourcedata*, *sinkdata*, *blocking=True*, ***kwargs*)

fullid

The fullid of the Network, within the network scope

global_id

The global id of the Network, this is different for networks used in macronodes, as they still have parents.

id

The id of the Network. This is a read only property.

is_valid()

nodegroups

Give an overview of the nodegroups in the network

remove (*value*)

Remove an item from the Network.

Parameters **value** (*Node* or *Link*) – the item to remove

classmethod test (*reference_data_dir*, *network=None*, *source_data=None*, *force_remove_temp=False*)

Execute the network with the source data specified and test the results against the refence data. This effectively tests the network execution.

Parameters

- **reference_data_dir** (*str*) – The path or vfs url of reference data to compare with
- **source_data** (*dict*) – The source data to use

class fastr.__init__.Link (*source*, *target*, *parent*, *id=None*, *collapse=None*, *expand=None*)

Bases: *fastr.core.dimension.HasDimensions*, *fastr.core.updateable.Updateable*, *fastr.core.serializable.Serializable*

Class for linking outputs (*BaseOutput*) to inputs (*BaseInput*)

Examples:

```
>>> import fastr
>>> network = fastr.Network()
>>> link1 = network.create_link( n1.outputs['out1'], n2.inputs['in2'] )

link2 = Link()
link2.source = n1.outputs['out1']
link2.target = n2.inputs['in2']
```

__abstractmethods__ = frozenset([])

__dataschemafile__ = ‘Link.schema.json’

__eq__ (*other*)

Test for equality between two Links

Parameters **other** (*Link*) – object to test against

Returns True for equality, False otherwise

Return type bool

`__getstate__()`

Retrieve the state of the Link

Returns the state of the object

Rtype dict

`__init__(source, target, parent, id_=None, collapse=None, expand=None)`

Create a new Link in a Network.

Parameters

- **source** (*BaseOutput*) – the source output
- **target** (*BaseInput*) – the target input
- **parent** (*Network* or None) – the parent network
- **id** (*str* or *None*) – the id of the link, if no **id_** is given, the id will be in the form of “link_{:d}”
- **collapse** (*int*, *str*, or tuple of *int/str*) – the dimensions that the link has to collapse on
- **expand** (*bool*) – Does this link need to expand the cardinality into a new sample dimension

Returns newly created Link

Raises

- **FastrValueError** – if parent is not given
- **FastrValueError** – if the source output is not in the same network as the Link
- **FastrValueError** – if the target input is not in the same network as the Link

`__module__ = 'fastr.core.link'`

`__repr__()`

Get a string representation for the Link

Returns the string representation

Return type str

`__setstate__(state)`

Set the state of the Link by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

Raises **FastrValueError** – if the parent network is not set

`cardinality(index=None)`

Cardinality for a Link is given by source Output and the collapse/expand settings

Parameters **key** (*SampleIndex*) – key for a specific sample (can be only a sample index!)

Returns the cardinality

Return type int, sympy.Symbol

Raises **FastrIndexError** – if the index length does not match the number of dimension in the data

collapse

The converging dimensions of this link. Collapsing changes some dimensions of sample lists into cardinality, reshaping the data.

Collapse can be set to a tuple or an int/str, in which case it will be automatically wrapped in a tuple. The int will be seen as indices of the dimensions to collapse. The str will be seen as the name of the dimensions over which to collapse.

Raises *FastrTypeError* – if assigning a collapse value of a wrong type

collapse_indexes

The converging dimensions of this link as integers. Dimension names are replaced with the corresponding int.

Collapsing changes some dimensions of sample lists into cardinality, reshaping the data

classmethod *createobj* (*state*, *network*=*None*)

Create object function for Link

Parameters

- **cls** – The class to create
- **state** – The state to use to create the Link
- **network** – the parent Network

Returns newly created Link

destroy()

The destroy function of a link removes all default references to a link. This means the references in the network, input and output connected to this link. If there is no references in other places in the code, it will destroy the link (reference count dropping to zero).

This function is called when a source for an input is set to another value and the links becomes disconnected. This makes sure there is no dangling links.

dimensions

The dimensions of the data delivered by the link. This can be different from the source dimensions because the link can make data collapse or expand.

draw (*context*, *graph*)**expand**

Flag indicating that the link will expand the cardinality into a new sample dimension to be created.

fullid

The full defining ID for the Input

parent

The Network to which this Link belongs.

source

The source *BaseOutput* of the Link. Setting the source will automatically register the Link with the source BaseOutput. Updating source will also make sure the Link is unregistered with the previous source.

Raises *FastrTypeError* – if assigning a non *BaseOutput*

status**target**

The target *BaseInput* of the Link. Setting the target will automatically register the Link with the target BaseInput. Updating target will also make sure the Link is unregistered with the previous target.

Raises *FastrTypeError* – if assigning a non *BaseInput*

```
class fastr.__init__.Node(tool, id=None, node_class=None, parent=None, cores=None, memory=None, walltime=None, nodegroup=None)
Bases: fastr.core.dimension.HasDimensions, fastr.core.updateable.Updateable, fastr.core.serializable.Serializable
```

The class encapsulating a node in the network. The node is responsible for setting and checking inputs and outputs based on the description provided by a tool instance.

__abstractmethods__ = frozenset([])

__dataschemafile__ = 'Node.schema.json'

__eq__ (other)

Compare two Node instances with each other. This function ignores the parent and update status, but tests rest of the dict for equality. equality

Parameters **other** (Node) – the other instances to compare to

Returns True if equal, False otherwise

__getstate__ ()

Retrieve the state of the Node

Returns the state of the object

Rtype dict

__init__ (tool, id=None, node_class=None, parent=None, cores=None, memory=None, walltime=None, nodegroup=None)

Instantiate a node.

Parameters

- **tool** ([Tool](#)) – The tool to base the node on
- **id** ([str](#)) – the id of the node
- **node_class** ([str](#)) – The class of the NodeRun to create (e.g. SourceNodeRun, NodeRun)
- **parent** ([Network](#)) – the parent network of the node
- **cores** ([int](#)) – number of cores required for executing this Node
- **memory** ([str](#)) – amount of memory required in the form d+[mG] where M is for megabyte and G for gigabyte
- **walltime** ([str](#)) – amount of time required in second or in the form HOURS:MINUTES:SECOND

Returns the newly created Node

__metaclass__

alias of ABCMeta

__module__ = 'fastr.core.node'

__repr__ ()

Get a string representation for the Node

Returns the string representation

Return type str

__setstate__ (state)

Set the state of the Node by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

__str__()
Get a string version for the Node

Returns the string version

Return type `str`

blocking
Indicate that the results of this Node cannot be determined without first executing the Node, causing a blockage in the creation of jobs. A blocking Nodes causes the Chunk borders.

classmethod `createobj` (`state, network=None`)

dimensions

dimnames
Names of the dimensions in the Node output. These will be reflected in the SampleIdList of this Node.

draw (`context, graph, color=None`)

draw_id (`context`)

draw_link_target (`context, port_name, input=True`)

find_source_index (`target_index, target, source`)

fullid
The full defining ID for the Node inside the network

get_sourced_nodes ()
A list of all Nodes connected as sources to this Node

Returns list of all nodes that are connected to an input of this node

global_id
The global defining ID for the Node from the main network (goes out of macro nodes to root network)

id
The id of the Node

input_groups
A list of input groups for this Node. An input group is `InputGroup` object filled according to the Node

listeners
All the listeners requesting output of this node, this means the listeners of all Outputs and SubOutputs

merge_dimensions

name
Name of the Tool the Node was based on. In case a Toolless Node was used the class name is given.

nodegroup

outputszie
The size of output of this SourceNode

parent
The parent network of this node.

required_cores
Number of cores required for the execution of this Node

required_memory

Amount of memory required for the execution of this Node. Follows the format d+[mMgG] so 500M or 4g would be valid ways to specify 500 megabytes or 4 gigabyte of memory.

required_time

Amount of time required for the execution of this Node. Follows the format of a number of second or H:M:S, with H the number of hours, M the number of minutes and S the number of seconds.

status**tool****update_input_groups()**

Update all input groups in this node

class fastr.__init__.**ConstantNode** (*datatype*, *data*, *id_=None*, *parent=None*, *nodegroup=None*)
Bases: *fastr.core.node.SourceNode*

Class encapsulating one output for which a value can be set. For example used to set a scalar value to the input of a node.

__abstractmethods__ = frozenset([])**__dataschemafile__ = 'ConstantNode.schema.json'****__getstate__()**

Retrieve the state of the ConstantNode

Returns the state of the object

Rtype dict

__init__ (*datatype*, *data*, *id_=None*, *parent=None*, *nodegroup=None*)

Instantiation of the ConstantNode.

Parameters

- **datatype** – The datatype of the output.
- **data** – the prefilled data to use.
- **id** – The url pattern.

This class should never be instantiated directly (unless you know what you are doing). Instead create a constant using the network class like shown in the usage example below.

usage example:

```
>>> import fastr
>>> network = fastr.Network()
>>> source = network.create_source(datatype=fastr.typelist['ITKImageFile'],
    ↪id_='sourceN')
```

or alternatively create a constant node by assigning data to an item in an InputDict:

```
>>> node_a.inputs['in'] = ['some', 'data']
```

which automatically creates and links a ConstantNode to the specified Input

__module__ = 'fastr.core.node'**__setstate__** (*state*)

Set the state of the ConstantNode by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

data

The data stored in this constant node

draw (*context, graph, color=None*)

set_data (*data=None, ids=None*)

Set the data of this constant node in the correct way. This is mainly for compatibility with the parent class SourceNode

Parameters

- **data** (*dict or list of urls*) – the data to use
- **ids** – if data is a list, a list of accompanying ids

class *fastr.__init__.SourceNode* (*datatype, id=None, parent=None, nodegroup=None*)

Bases: *fastr.core.node.FlowNode*

Class providing a connection to data resources. This can be any kind of file, stream, database, etc from which data can be received.

__abstractmethods__ = frozenset([])

__dataschemafile__ = ‘SourceNode.schema.json’

__eq__ (*other*)

Compare two Node instances with each other. This function ignores the parent and update status, but tests rest of the dict for equality. equality

Parameters **other** (*Node*) – the other instances to compare to

Returns True if equal, False otherwise

__getstate__()

Retrieve the state of the SourceNode

Returns the state of the object

Rtype dict

__init__ (*datatype, id=None, parent=None, nodegroup=None*)

Instantiation of the SourceNode.

Parameters

- **datatype** – The (id of) the datatype of the output.
- **id** – The url pattern.

This class should never be instantiated directly (unless you know what you are doing). Instead create a source using the network class like shown in the usage example below.

usage example:

```
>>> import fastr
>>> network = fastr.Network()
>>> source = network.create_source(datatype=fastr.typeлист['ITKImageFile'], ↴
    ↴id_='sourceN')
```

__module__ = ‘fastr.core.node’

__setstate__ (*state*)

Set the state of the SourceNode by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

datatype

The datatype of the data this source supplies.

dimensions

The dimensions in the SourceNode output. These will be reflected in the SampleIdLists.

draw (`context, graph, color=None`)

nodegroup

output

Shorthand for `self.outputs['output']`

set_data (`data, ids=None`)

Set the data of this source node.

Parameters

- **data** (`dict, OrderedDict or list of urls`) – the data to use
- **ids** – if data is a list, a list of accompanying ids

sourcegroup

valid

This does nothing. It only overloads the valid method of Node(). The original is intended to check if the inputs are connected to some output. Since this class does not implement inputs, it is skipped.

class `fastr.__init__.SinkNode` (`datatype, id_=None, parent=None, nodegroup=None`)

Bases: `fastr.core.node.Node`

Class which handles where the output goes. This can be any kind of file, e.g. image files, textfiles, config files, etc.

__abstractmethods__ = frozenset([])

__dataschemafile__ = ‘SinkNode.schema.json’

__getstate__()

__init__ (`datatype, id_=None, parent=None, nodegroup=None`)

Instantiation of the SourceNode.

Parameters

- **datatype** – The datatype of the output.
- **id** – the id of the node to create

Returns newly created sink node

usage example:

```
>>> import fastr
>>> network = fastr.Network()
>>> sink = network.create_sink(datatype=fastr.typelist['ITKImageFile'], id_=
    ↴'SinkN')
```

__module__ = ‘fastr.core.node’

__setstate__ (`state`)

datatype

The datatype of the data this sink can store.

draw (context, graph, color=None)**input**

The default input of the sink Node

configmanager Module

This module defines the Fastr Config class for managing the configuration of Fastr. The config object is stored directly in the fastr top-level module.

```
class fastr.configmanager.Config (*configfiles)
```

Bases: `object`

Class contain the fastr configuration

```
DEFAULT_FIELDS = {'resourcesdir': (<type 'str'>, '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/li
```

```
_dict_ = dict_proxy({'plugins_path': <property object>, '__dict__': <attribute '__dict__' of 'Config' objects>, '__we
```

```
_init_ (*configfiles)
```

```
_module_ = 'fastr.configmanager'
```

```
_repr_ ()
```

```
_weakref_
```

list of weak references to the object (if defined)

```
debug
```

```
examplesdir
```

```
execution_plugin
```

```
executionscript
```

```
filesynchelper_url
```

```
get_field(item)
```

```
logdir
```

```
logging_config
```

```
loglevel
```

```
logtype
```

```
mounts
```

```
networks_path
```

```
pim_host
```

```
plugins_path
```

```
preferred_types
```

```
process_pool_worker_number
```

```
protected_modules
```

```
read_config(filename)
```

Read a configuration and update the configuration object accordingly

Parameters `filename` – the configuration file to read

`read_config_files = None`
Trace of the config files read by this object

`read_config_string(value)`

`register_fields(fields_spec)`
Register extra fields to the configuration manager.

`resourcesdir`

`schemadir`

`set_field(item, value)`

`source_job_limit`

`systemdir`

`tools_path`

`types_path`

`userdir`

`warn_develop`

`web_hostname`

`web_port`

`web_secret_key`

`web_url()`
Construct a fqdn from the web[‘hostname’] and web[‘port’] settings. :return: FQDN :rtype: str

`x = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg/fastr/configmanager.py'`

`class fastr.configmanager.EmptyDefault(data=None)`
Bases: `object`

Empty defaultdict.

`__add__(right)`

`__delitem__(key)`

`__dict__ = dict_proxy({'extend': <function extend>, '__delitem__': <function __delitem__>, '__module__': 'fastr.configmanager'})`

`__getitem__(item)`

`__iadd__(right)`

`__init__(data=None)`

`__module__ = 'fastr.configmanager'`

`__radd__(other)`

`__setitem__(key, value)`

`__weakref__`
list of weak references to the object (if defined)

`append(value)`

`asdict()`

`aslist()`

```
extend(other)
prepend(value)
update(other)
```

datatypes Module

The datatypes module holds all DataTypes generated by fastr and all the base classes for these datatypes.

```
class fastr.datatypes.AnalyzeImageFile(value=None, format_=None)
    Bases: fastr.datatypes.URLType
```

```
__abstractmethods__ = frozenset([])
```

```
__module__ = 'fastr.datatypes'
```

```
classmethod content(invalue, outvalue=None)
```

```
description = 'Analyze Image file formate'
```

```
extension = 'hdr'
```

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
```

```
module = <module 'AnalyzeImageFile' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/pyth
```

```
class fastr.datatypes.AnyFile(value=None)
```

```
Bases: fastr.datatypes.TypeGroup
```

Special Datatype in fastr that is a TypeGroup with all known DataTypes as its members.

```
__abstractmethods__ = frozenset([])
```

```
__module__ = 'fastr.datatypes'
```

```
description = 'TypeGroup AnyFile\nAnyFile (AnyFile) is a group of consisting of all URLTypes known by fastr, currentl
```

```
class fastr.datatypes.AnyType(value=None)
```

```
Bases: fastr.datatypes.TypeGroup
```

Special Datatype in fastr that is a TypeGroup with all known DataTypes as its members.

```
__abstractmethods__ = frozenset([])
```

```
__module__ = 'fastr.datatypes'
```

```
description = 'TypeGroup AnyType\nAnyType (AnyType) is a group of consisting of all DataTypes known by fastr, currentl
```

```
class fastr.datatypes.BaseDataType(value=None, format_=None)
```

```
Bases: fastr.core.baseplugin.BasePlugin
```

The base class for all datatypes in the fastr type system.

```
__abstractmethods__ = frozenset(['__init__'])
```

```
__eq__(other)
```

Test the equality of two DataType objects

Parameters `other` (`DataType`) – the object to compare against

Returns flag indicating equality

Return type `bool`

```
__getstate__()
```

`__init__(value=None, format_=None)`

The BaseDataType constructor.

Parameters

- **value** – value to assign to the new BaseDataType object
- **format** – the format used for the ValueType

Returns new BaseDataType object

Raises `FastrNotImplementedError` – if `id`, `name`, `version` or `description` is None

`__module__ = 'fastr.datatypes'`

`__ne__(other)`

Test if two objects are not equal. This is by default done by negating the `__eq__` operator

Parameters `other` (`DataType`) – the object to compare against

Returns flag indicating equality

Return type `bool`

`__reduce_ex__(*args, **kwargs)`

`__repr__()`

Returns string representation of the BaseDataType

Returns string representation

Return type `str`

`__setstate__(state)`

`__str__()`

Returns the string version of the BaseDataType

Returns string version

Return type `str`

`checksum()`

Generate a checksum for the value of this DataType

Returns the checksum of the value

Return type `str`

`description = ''`

`extension = None`

`filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p`

`fullId = 'fastr://typelist/BaseDataType'`

`id = 'BaseDataType'`

`classmethod isinstance(value)`

Indicate whether value is an instance for this DataType.

Returns the flag indicating the value is of this DataType

Return type `bool`

`name = 'BaseDataType'`

`parent = DataTypeManager AnalyzeImageFile : <URLType: AnalyzeImageFile> AnyFile : <TypeGroup: AnyFile> Any`

parsed_value

The parsed value of object instantiation of this DataType.

raw_value

The raw value of object instantiation of this DataType. For datatypes that override value (like Deferred) this is the way to access the _value field.

classmethod test()

Define the test for the BasePluginManager. Make sure we are not one of the base classes

valid

A boolean flag that indicates weather or not the value assigned to this DataType is valid. This property is generally overwritten by implementation of specific DataTypes.

value

The value of object instantiation of this DataType.

version = <Version: 1.0>

class fastr.datatypes.**Boolean** (*value=None, format_=None*)

Bases: *fastr.datatypes.ValueType*

Datatype representing a boolean

__abstractmethods__ = frozenset([])

__module__ = 'fastr.datatypes'

__str__ ()

description = 'A boolean value (True or False)'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

module = <module 'Boolean' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-

value

The value of object instantiation of this DataType.

class fastr.datatypes.**DataType** (*value=None, format_=None*)

Bases: *fastr.datatypes.BaseDataType*

This class is the base class for all DataTypes that can hold a value.

__abstractmethods__ = frozenset(['__init__'])

__init__ (*value=None, format_=None*)

The DataType constructor.

Parameters

- **value** – value to assign to the new DataType object
- **format** – the format used for the ValueType

Returns new DataType object

__module__ = 'fastr.datatypes'

action (*name*)

This function can be overwritten by subclasses to implement certain action that should be performed. For example, the *Directory* DataType has an action *ensure*. This method makes sure the Directory exists. A Tool can indicate an action that should be called for an Output which will be called before execution.

Parameters **name** (*str*) – name of the action to execute

Returns None

```
class fastr.datatypes.Deferred(value=None,format_=None)
Bases: fastr.datatypes.DataType
```

```
__abstractmethods__ = frozenset([])
```

```
__getstate__()
```

```
__init__(value=None,format_=None)
```

The Deferred constructor.

Parameters

- **value** – value to assign to the new DataType object
- **format** – This is ignore but here for compatibility

Returns new Deferred object

```
__module__ = 'fastr.datatypes'
```

```
__repr__()
```

Returns string representation of the BaseDataType

Returns string represenation

Return type str

```
__setstate__(state)
```

```
checksum()
```

Generate a checksum for the value of this DataType

Returns the checksum of the value

Return type str

job

```
classmethod lookup(value)
```

Look up the deferred target and return that object

Param value

Returns The value the deferred points to

Return type DataType

Raises

- **FastrKeyError** – if the deferred is not available (yet)
- **FastrValueError** – if the value is not a valid deferrred url

parsed_value

The value of object instantiation of this DataType.

provenance

target

Target object for this deferred.

Raises

- **FastrKeyError** – if the deferred is not available (yet)
- **FastrValueError** – if the value is not a valid deferrred url

value

The value of object instantiation of this DataType.

```

class fastr.datatypes.Directory(value=None, format_=None)
Bases: fastr.datatypes.URLType

    DataType representing a directory.

    __abstractmethods__ = frozenset([])

    __eq__ (other)
        Directories are equal by default as long as the validity matches.

            Parameters other (Directory) – other to compare against
            Returns equality flag

    __module__ = 'fastr.datatypes'

    action (name)
        This method makes sure the Directory exists. A Tool can indicate an action that should be called for an Output which will be called before execution.

            Parameters name (str) – name of the action to execute
            Returns None

    description = 'A directory on the disk'

    extension = None

    filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
    module = <module 'Directory' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/sit

class fastr.datatypes.EnumType(value=None, format_=None)
Bases: fastr.datatypes.DataType

    The EnumType is the base for DataTypes that can have a value which is an option from a predefined set of possibilities (similar to an enum type in many programming languages).

    __abstractmethods__ = frozenset([])

    __init__ (value=None, format_=None)
        The EnumType constructor.

            Parameters
                • value – value to assign to the new EnumType object
                • format – the format used for the ValueType

            Returns new EnumType object

            Raises FastrDataTypeNotInstantiableError – if not subclassed

    __module__ = 'fastr.datatypes'

    __reduce_ex__ (*args, **kwargs)

    description = 'EnumType (EnumType) is a enumerate type with options:\n\n\nEnumType can take the value of any of
    options = frozenset([])
    version = <Version: 1.0>

class fastr.datatypes.FilePrefix(value=None, format_=None)
Bases: fastr.datatypes.URLType

    __abstractmethods__ = frozenset([])

    __module__ = 'fastr.datatypes'

```

```
checksum()
description = 'Prefix for another file, including the path'
extension = None
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'FilePrefix' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-p
class fastr.datatypes.Float (value=None, format_=None)
Bases: fastr.datatypes.ValueType
__abstractmethods__ = frozenset(())
__module__ = 'fastr.datatypes'
description = 'A floating point value'
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'Float' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-p
value
The value of object instantiation of this DataType.

class fastr.datatypes.ITKImageFile (value=None)
Bases: fastr.datatypes.TypeGroup
__abstractmethods__ = frozenset(())
__module__ = 'fastr.datatypes'
description = 'Text file to store point coordinates'
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'ITKImageFile' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-p
class fastr.datatypes.Int (value=None, format_=None)
Bases: fastr.datatypes.ValueType
__abstractmethods__ = frozenset(())
__module__ = 'fastr.datatypes'
description = 'an integer value'
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'Int' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-p
value
The value of object instantiation of this DataType.

class fastr.datatypes.JsonFile (value=None, format_=None)
Bases: fastr.datatypes.URLType
__abstractmethods__ = frozenset(())
__module__ = 'fastr.datatypes'
checksum()
description = 'json file'
extension = 'json'
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
```

```

module = <module ‘JsonFile’ from ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-
```

```

class fastr.datatypes.MetaImageFile (value=None, format_=None)
    Bases: fastr.datatypes.URLType

        _abstractmethods_ = frozenset([])

        _eq_ (other)
        _module_ = ‘fastr.datatypes’

        checksum()
            Return the checksum of this MetaImageFile

            Returns checksum string

            Return type str

        classmethod content (invalue, outvalue=None)
            description = ‘Meta Image file format’

            extension = ‘mhd’

            filename = ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

            module = <module ‘MetaImageFile’ from ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-
```

```

class fastr.datatypes.NiftiImageFile (value=None)
    Bases: fastr.datatypes.TypeGroup

        _abstractmethods_ = frozenset([])

        _module_ = ‘fastr.datatypes’

        description = ‘NiftiTypeGroup’

        filename = ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

        module = <module ‘NiftiImageFile’ from ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-
```

```

class fastr.datatypes.NiftiImageFileCompressed (value=None, format_=None)
    Bases: fastr.datatypes.URLType

        _abstractmethods_ = frozenset([])

        _module_ = ‘fastr.datatypes’

        description = ‘Compressed Nifti Image File format’

        extension = ‘nii.gz’

        filename = ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

        module = <module ‘NiftiImageFileCompressed’ from ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-
```

```

class fastr.datatypes.NiftiImageFileUncompressed (value=None, format_=None)
    Bases: fastr.datatypes.URLType

        _abstractmethods_ = frozenset([])

        _module_ = ‘fastr.datatypes’

        description = ‘Nifti Image File format’

        extension = ‘nii’

        filename = ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

        module = <module ‘NiftiImageFileUncompressed’ from ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-
```

```
class fastr.datatypes.Number(value=None)
Bases: fastr.datatypes.TypeGroup

__abstractmethods__ = frozenset([])
__module__ = 'fastr.datatypes'
description = 'an numeric value'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'Number' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-


class fastr.datatypes.ProvNFile(value=None, format_=None)
Bases: fastr.datatypes.URLType

__abstractmethods__ = frozenset([])
__module__ = 'fastr.datatypes'
description = 'Provenance file in the prov N format'
extension = 'provn'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'ProvNFile' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-


class fastr.datatypes.String(value=None, format_=None)
Bases: fastr.datatypes.ValueType

__abstractmethods__ = frozenset([])
__module__ = 'fastr.datatypes'
description = 'A simple string value'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'String' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-


class fastr.datatypes.TifImageFile(value=None, format_=None)
Bases: fastr.datatypes.URLType

__abstractmethods__ = frozenset([])
__module__ = 'fastr.datatypes'
description = 'Tif Image File format'
extension = 'tif'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'TifImageFile' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-


class fastr.datatypes.TxtFile(value=None, format_=None)
Bases: fastr.datatypes.URLType

__abstractmethods__ = frozenset([])
__module__ = 'fastr.datatypes'
description = 'General text file'
extension = 'txt'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'TxtFile' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-
```

```
class fastr.datatypes.TypeGroup (value=None)
Bases: fastr.datatypes.BaseDataType
```

The TypeGroup is a special DataType that does not hold a value of its own but is used to group a number of DataTypes. For example ITK has a list of supported file formats that all tools build on ITK support. A group can be used to conveniently specify this in multiple Tools that use the same set DataTypes.

```
__abstractmethods__ = frozenset(['_members'])
```

```
__init__ (value=None)
```

Dummy constructor. TypeGroups are not instantiable and cannot hold a value of its own.

Raises *FastrDataTypeNotInstantiableError* – if called

```
__module__ = 'fastr.datatypes'
```

```
static __new__ (value=None, format_=None)
```

Instantiate a TypeGroup. This will for match the value to the best matching type and instantiate that. Note that the returned object will not be of type TypeGroup but one of the TypeGroup members.

```
classmethod isinstance (value)
```

members

A descriptor that can act like a property for a class.

```
class fastr.datatypes.URLType (value=None, format_=None)
```

Bases: *fastr.datatypes.DataType*

The URLType is the base for DataTypes that point to a resource somewhere else (typically a filesystem). The true value is actually the resource referenced by the value in this object.

```
__abstractmethods__ = frozenset([])
```

```
__eq__ (other)
```

Test the equality of two DataType objects

Parameters *other* (*URLType*) – the object to compare against

Returns flag indicating equality

Return type *bool*

```
__init__ (value=None, format_=None)
```

The URLType constructor

Parameters

- **value** – value to assign to the new URLType

- **format** – the format used for the ValueType

Returns new URLType object

```
__module__ = 'fastr.datatypes'
```

```
checksum()
```

Return the checksum of this URL type

Returns checksum string

Return type *str*

```
classmethod content (inval, outval=None)
```

Give the contents of a URLType, this is generally useful for filetypes that consists of multiple files (e.g. AnalyzeImageFile, DICOM). The value will indicate the main file, and the contents function can determine all files that form a single data value.

Parameters

- **inval** – a value to figure out contents for this type
- **outval** – the place where the copy should point to

Returns a list of all files part of the value (e.g. header and data file)

Return type list

parsed_value

The parsed value of object instantiation of this DataType.

valid

A boolean flag that indicates weather or not the value assigned to this DataType is valid. This property is generally overwritten by implementation of specific DataTypes.

class *fastr.datatypes.UnsignedInt* (*value=None, format_=None*)

Bases: *fastr.datatypes.ValueType*

__abstractmethods__ = frozenset([])

__module__ = ‘fastr.datatypes’

description = ‘an unsigned integer value’

filename = ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

module = <module ‘UnsignedInt’ from ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

value

The value of object instantiation of this DataType.

class *fastr.datatypes.ValueType* (*value=None, format_=None*)

Bases: *fastr.datatypes.DataType*

The ValueType is the base for DataTypes that hold simple values (not an EnumType and not a file/URL). The values is generally represented by a string.

__abstractmethods__ = frozenset([])

__init__ (*value=None, format_=None*)

The ValueType constructor

Parameters

- **value** – value to assign to the new ValueType
- **format** – the format used for the ValueType

Returns new ValueType object

__module__ = ‘fastr.datatypes’

fastr.datatypes.fastr_isinstance (*obj, datatype*)

Check if an object is of a specific datatype.

Parameters

- **obj** – Object to inspect
- **datatype** (*tuple, BaseDataType*) – The datatype(s) to check

Returns flag indicating object is of datatype

Return type bool

exceptions Module

This module contains all Fastr-related Exceptions

exception `fastr.exceptions.FastrAttributeError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError, exceptions.AttributeError`

AttributeError in the fastr system

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrCannotChangeAttributeError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

Attempting to change an attribute of an object that can be set only once.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrCardinalityError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

The description of the cardinality is not valid.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrCollectorError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

Cannot collect the results from a Job because of an error

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrDataTypeFileNotFoundException(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

Could not read the datatype file.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrDataTypeMismatchError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

When using a DataType as the key for the DataTypeManager, the DataTypeManager found another DataType with the same name already in the DataTypeManager. This means fastr has two version of the same DataType in the system, which should never happen!

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrDataTypeNotFoundError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

The DataType requested is not found by the fastr system. Typically this means that no matching DataType is found in the DataTypeManager.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrDataTypeNotInstantiableError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

The base classes for DataTypes cannot be instantiated and should always be sub-classed.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrDataTypeValueError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

This value in fastr did not pass the validation specified for its DataType, typically means that the data is missing or corrupt.

`__module__ = 'fastr.exceptions'`

`exception fastr.exceptions.FastrError(*args, **kwargs)`

Bases: `exceptions.Exception`

This is the base class for all fastr related exceptions. Catching this class of exceptions should ensure a proper execution of fastr.

`__init__(*args, **kwargs)`

Constructor for all exceptions. Saves the caller object fullid (if found) and the file, function and line number where the object was created.

`__module__ = 'fastr.exceptions'`

`__str__()`

String representation of the error

Returns error string

Return type `str`

`__weakref__`

list of weak references to the object (if defined)

`excerpt()`

Return a excerpt of the Error as a tuple.

`exception fastr.exceptions.FastrErrorInSubprocess(*args, **kwargs)`

Bases: `fastr.exceptions.FastrExecutionError`

Encountered an error in the subprocess started by the execution script

`__module__ = 'fastr.exceptions'`

`exception fastr.exceptions.FastrExecutableNotFoundError(executable=None, *args, **kwargs)`

Bases: `fastr.exceptions.FastrExecutionError`

The executable could not be found!

`__init__(executable=None, *args, **kwargs)`

`__module__ = 'fastr.exceptions'`

`__str__()`

String representation of the error

`exception fastr.exceptions.FastrExecutionError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

Base class for all fastr execution related errors

`__module__ = 'fastr.exceptions'`

`exception fastr.exceptions.FastrIOError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError, exceptions.IOError`

IOError in the fastr system

`__module__ = 'fastr.exceptions'`

`__weakref__`

list of weak references to the object (if defined)

```

exception fastr.exceptions.FastrImportError (*args, **kwargs)
    Bases: fastr.exceptions.FastrError, exceptions ImportError
    ImportError in the fastr system
    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrIndexError (*args, **kwargs)
    Bases: fastr.exceptions.FastrError, exceptions IndexError
    IndexError in the fastr system
    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrIndexNonexistent (*args, **kwargs)
    Bases: fastr.exceptions.FastrIndexError
    This is an IndexError for samples requested from a sparse data array. The sample is not there but is probably
    not there because of sparseness rather than being a missing sample (e.g. out of bounds).
    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrKeyError (*args, **kwargs)
    Bases: fastr.exceptions.FastrError, exceptions KeyError
    KeyError in the fastr system
    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrLookupError (*args, **kwargs)
    Bases: fastr.exceptions.FastrError
    Could not find specified object in the fastr environment.
    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrMountUnknownError (*args, **kwargs)
    Bases: fastr.exceptions.FastrKeyError
    Trying to access an undefined mount
    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrNetworkMismatchError (*args, **kwargs)
    Bases: fastr.exceptions.FastrError
    Two interacting objects belong to different fastr network.
    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrNetworkUnknownError (*args, **kwargs)
    Bases: fastr.exceptions.FastrKeyError
    Reference to a Tool that is not recognised by the fastr system. This typically means the specific id/version
    combination of the requested tool has not been loaded by the ToolManager.
    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrNoValidTargetException (*args, **kwargs)
    Bases: fastr.exceptions.FastrKeyError
    Cannot find a valid target for the tool
    __module__ = 'fastr.exceptions'

```

exception `fastr.exceptions.FastrNodeAlreadyPreparedError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrStateError`

A attempt is made at preparing a NodeRun for the second time. This is not allowed as it would wipe the current execution data and cause data-loss.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrNodeNotPreparedError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrStateError`

When trying to access execution data of a NodeRun, the NodeRun must be prepare. The NodeRun has not been prepared by the execution, so the data is not available!

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrNodeNotValidError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrStateError`

A NodeRun is not in a valid state where it should be, typically an invalid NodeRun is passed to the executor causing trouble.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrNotExecutableError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrExecutionError`

The command invoked by subprocess is not executable on the system

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrNotImplementedError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError, exceptions.NotImplementedError`

This function/method has not been implemented on purpose (e.g. should be overwritten in a sub-class)

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrOSError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError, exceptions.OSError`

OSError in the fastr system

`__module__ = 'fastr.exceptions'`

`__weakref__`

list of weak references to the object (if defined)

exception `fastr.exceptions.FastrObjectUnknownError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrKeyError`

Reference to a Tool that is not recognised by the fastr system. This typically means the specific id/version combination of the requested tool has not been loaded by the ToolManager.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrOptionalModuleNotAvailableError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrNotImplementedError`

A optional modules for Fastr is needed for this function, but is not available on the current python installation.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrOutputValidationrror(*args, **kwargs)`

Bases: `fastr.exceptions.FastrExecutionError`

An output of a Job does not pass validation

```
__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrParentMismatchError (*args, **kwargs)
    Bases: fastr.exceptions.FastrError

    Two interactive objects have different parent where they should be the same

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrPluginCapabilityNotImplemented (*args, **kwargs)
    Bases: fastr.exceptions.FastrNotImplementedError

    A plugin did not implement a capability that it advertised.

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrPluginNotAvailable (*args, **kwargs)
    Bases: fastr.exceptions.FastrKeyError

    Indicates that a requested Plugin was not found on the system.

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrPluginNotLoaded (*args, **kwargs)
    Bases: fastr.exceptions.FastrStateError

    The plugin was not successfully loaded. This means the plugin class cannot be instantiated.

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrResultFileNotFoundException (*args, **kwargs)
    Bases: fastr.exceptions.FastrExecutionError

    Could not find the result file of job that finished. This means the execution script process was killed during interruption. Generally this means a scheduler killed it because of resource shortage.

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrSerializationError (message,           serializer,           ori-
                                                       nal_exception=None)
    Bases: fastr.exceptions.FastrError

    The serialization encountered a serious problem

__init__ (message, serializer, original_exception=None)

__module__ = 'fastr.exceptions'

__repr__ ()
    Simple string representation of the exception

__str__ ()
    Advanced string representation of the exception including the data about where in the schema things went wrong.

exception fastr.exceptions.FastrSerializationIgnoreDefaultError (message,           seri-
                                                               alizer,           origi-
                                                               nal_exception=None)
    Bases: fastr.exceptions.FastrSerializationError

    The value and default are both None, so the value should not be serialized.

__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrSerializationInvalidDataError(*args, **kwargs)
    bases: fastr.exceptions.FastrSerializationError
    series: serializer, original_exception=None
    doc: Encountered data to serialize that is invalid given the serialization schema.

    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrSerializationMethodError(*args, **kwargs)
    bases: fastr.exceptions.FastrKeyError
    doc: The desired serialization method does not exist.

    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrSinkDataUnavailableError(*args, **kwargs)
    bases: fastr.exceptions.FastrKeyError
    doc: Could not find the Sink data for the desire sink.

    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrSizeInvalidError(*args, **kwargs)
    bases: fastr.exceptions.FastrError
    doc: The given size cannot be valid.

    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrSizeMismatchError(*args, **kwargs)
    bases: fastr.exceptions.FastrError
    doc: The size of two object in fastr is not matching where it should.

    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrSizeUnknownError(*args, **kwargs)
    bases: fastr.exceptions.FastrError
    doc: The size of object is not (yet) known and only a theoretical estimate is available at the moment.

    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrSourceDataUnavailableError(*args, **kwargs)
    bases: fastr.exceptions.FastrKeyError
    doc: Could not find the Source data for the desire source.

    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrStateError(*args, **kwargs)
    bases: fastr.exceptions.FastrError
    doc: An object is in an invalid/unexpected state.

    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrSubprocessNotFinished(*args, **kwargs)
    bases: fastr.exceptions.FastrExecutionError
    doc: Encountered an error before the subprocess call by the execution script was properly finished.

    __module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrToolNotAvailableError(*args, **kwargs)
    bases: fastr.exceptions.FastrError
```

The tool used is not available on the current platform (OS and architecture combination) and cannot be used.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrToolTargetNotFound(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

Could not determine the location of the tools target binary/script. The tool cannot be used.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrToolUnknownError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrKeyError`

Reference to a Tool that is not recognised by the fastr system. This typically means the specific id/version combination of the requested tool has not been loaded by the ToolManager.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrTypeError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError, exceptions.TypeError`

TypeError in the fastr system

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrUnknownURLSchemeError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrKeyError`

Fastr encountered a data URL with a scheme that was not recognised by the IOPlugin manager.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrValueError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError, exceptions.ValueError`

ValueError in the fastr system

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrVersionInvalidError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrValueError`

The string representation of the version is malformed.

`__module__ = 'fastr.exceptions'`

exception `fastr.exceptions.FastrVersionMismatchError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrValueError`

There is a mismatch between different parts of the Fastr environment and integrity is compromised.

`__module__ = 'fastr.exceptions'`

plugins Module

The plugins module holds all plugins loaded by Fastr. It is empty on start and gets filled by the BasePluginManager

`class fastr.plugins.BlockingExecution(finished_callback=None, cancelled_callback=None, status_callback=None)`

Bases: `fastr.execution.executionpluginmanager.ExecutionPlugin`

The blocking execution plugin is a special plugin which is meant for debug purposes. It will not queue jobs but immediately execute them inline, effectively blocking fastr until the Job is finished. It is the simplest execution plugin and can be used as a template for new plugins or for testing purposes.

```
__abstractmethods__ = frozenset([])
__init__(finished_callback=None, cancelled_callback=None, status_callback=None)
__module__ = 'fastr.plugins'
cleanup()

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'blockingexecution' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/pyth

class fastr.plugins.CommaSepreatedValueFile
    Bases: fastr.core.ioplugin.IOPPlugin
```

The CommaSepreatedValueFile is an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs.

The csv:// URL is a vfs:// URL with a number of query variables available. The URL mount and path should point to a valid CSV file. The query variable then specify what column(s) of the file should be used.

The following variable can be set in the query:

variable	usage
value	the column containing the value of interest, can be int for index or string for key
id	the column containing the sample id (optional)
header	indicates if the first row is considered the header, can be true or false (optional)
delimiter	the delimiter used in the csv file (optional)
quote	the quote character used in the csv file (optional)
reformat	a reformatting string so that value = reformat.format(value) (used before relative_path)
relative_path	indicates the entries are relative paths (for files), can be true or false (optional)

The header is by default false if the neither the value and id are set as a string. If either of these are a string, the header is required to define the column names and it automatically is assumed true

The delimiter and quota characters of the file should be detected automatically using the Sniffer, but can be forced by setting them in the URL.

Example of valid csv URLs:

```
# Use the first column in the file (no header row assumed)
csv://mount/some/dir/file.csv?value=0

# Use the images column in the file (first row is assumed header row)
csv://mount/some/dir/file.csv?value=images

# Use the segmentations column in the file (first row is assumed header row)
# and use the id column as the sample id
csv://mount/some/dir/file.csv?value=segmentations&id=id

# Use the first column as the id and the second column as the value
# and skip the first row (considered the header)
csv://mount/some/dir/file.csv?value=1&id=0&header=true

# Use the first column and force the delimiter to be a comma
csv://mount/some/dir/file.csv?value=0&delimiter=,
```

```

__abstractmethods__ = frozenset([])

__init__()

__module__ = 'fastr.plugins'

expand_url(url)

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'commaseparatedvaluefile' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/p
scheme = 'csv'

class fastr.plugins.CrossValidation
Bases: flowinterface.FlowPlugin

Advanced flow plugin that generated a cross-validation data flow. The node need an input with data and an input
number of folds. Based on that the outputs test and train will be supplied with a number of data sets.

__abstractmethods__ = frozenset([])

__module__ = 'fastr.plugins'

static execute(payload)

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'crossvalidation' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python

class fastr.plugins.DRMAAExecution(finished_callback=None, cancelled_callback=None, status_callback=None)
Bases: fastr.execution.executionpluginmanager.ExecutionPlugin

A DRMAA execution plugin to execute Jobs on a Grid Engine cluster. It uses a configuration option for selecting
the queue to submit to. It uses the python drmaa package.

```

Note: To use this plugin, make sure the drmaa package is installed and that the execution is started on an SGE submit host with DRMAA libraries installed.

Note: This plugin is at the moment tailored to SGE, but it should be fairly easy to make different subclasses for different DRMAA supporting systems.

```

CANCELS_DEPENDENCIES = False

GE_NATIVE_SPEC = {'QUEUE': '-q {queue}', 'DEPENDS': '-hold_jid {hold_list}', 'HOLD': '-h', 'MEMORY': '-l h_vm
NATIVE_SPEC = {'grid_engine': {'QUEUE': '-q {queue}', 'DEPENDS': '-hold_jid {hold_list}', 'HOLD': '-h', 'MEMORY': '-l h_vm
SUPPORTS_CANCEL = True

SUPPORTS_DEPENDENCY = True

SUPPORTS_HOLD_RELEASE = True

TORQUE_NATIVE_SPEC = {'QUEUE': '-q {queue}', 'DEPENDS': '-W depend=afterok:{hold_list}', 'HOLD': '-h', 'MEMORY': '-l h_vm
__abstractmethods__ = frozenset([])

__init__(finished_callback=None, cancelled_callback=None, status_callback=None)

__module__ = 'fastr.plugins'

cleanup()

```

```
collect_jobs()
configuration_fields = {'drmaa_engine': (<type 'str'>, 'grid_engine', 'The engine to use (options: grid_engine, to
create_native_spec(queue, walltime, memory, ncores, outputLog, errorLog, hold_job, hold)
Create the native spec for the DRMAA scheduler. Needs to be implemented in the subclasses
```

Parameters

- **queue** (*str*) – the queue to submit to
- **walltime** (*str*) – walltime specified
- **memory** (*str*) – memory requested
- **ncores** (*int*) – number of cores requested
- **outputLog** (*str*) – the location of the stdout log
- **errorLog** (*str*) – the location of stderr log
- **hold_job** (*list*) – list of jobs to depend on
- **hold** (*bool*) – flag if job should be submitted in hold mode

Returns

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'drmaaexecution' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python
send_job(command, arguments, queue=None, walltime=None, job_name=None, memory=None,
          ncores=None, joinLogFile=False, outputLog=None, errorLog=None, hold_job=None,
          hold=False)
spec_fields
submit_jobs()
classmethod test()
```

class fastr.plugins.DockerTarget (*binary, docker_image*)
Bases: *fastr.core.target.Target*

A tool target that is located in a Docker images. Can be run using docker-py. A docker target only need two variables: the binary to call within the docker container, and the docker container to use.

```
{
    "arch": "*",
    "os": "*",
    "binary": "bin/test.py",
    "docker_image": "fastr/test"
}
```

```
<target os="*" arch="*" binary="bin/test.py" docker_image="fastr/test">
```

```
__abstractmethods__ = frozenset(())
__enter__()
__exit__(exc_type, exc_value, traceback)
__init__(binary, docker_image)
Define a new docker target.
```

Parameters **docker_image** (*str*) – Docker image to use

```
__module__ = 'fastr.plugins'
container
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'dockertarget' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-p
monitor_docker(container, resources)
Monitor a docker container and profile the cpu, memory and io use. Register the resource use every
_MONITOR_INTERVAL seconds.
```

Parameters

- **container** (*ContainerCollection*) – process to monitor
- **resources** (*ProcessUsageCollection*) – list to append measurements to

run_command(command)

class fastr.plugins.FastrInterface(id_, document)
Bases: *fastr.core.interface.Interface*

The default Interface for fastr. For the command-line Tools as used by fastr. It build a commandline call based on the input/output specification.

The fields that can be set in the interface:

Attribute	Description
<code>id</code>	The id of this Tool (used internally in fastr)
<code>inputs[]</code>	List of Inputs that can are accepted by the Tool
	<code>id</code> ID of the Input
	<code>name</code> Longer name of the Input (more human readable)
	<code>datatype</code> The ID of the DataType of the Input ¹
	<code>enum[]</code> List of possible values for an EnumType (created on the fly by fastr) ¹
	<code>prefix</code> Commandline prefix of the Input (e.g. <code>-in</code> , <code>-i</code>)
	<code>cardinality</code> Cardinality of the Input
	<code>repeat_prefix</code> Flag indicating if for every value of the Input the prefix is repeated
	<code>required</code> Flag indicating if the input is required
	<code>nospace</code> Flag indicating if there is no space between prefix and value (e.g. <code>-in=val</code>)
	<code>format</code> For DataTypes that have multiple representations, indicate which one to use
	<code>default</code> Default value for the Input
<code>description</code>	Long description for an input
<code>outputs[]</code>	List of Outputs that are generated by the Tool (and accessible to fastr)
	<code>id</code> ID of the Output
	<code>name</code> Longer name of the Output (more human readable)
	<code>datatype</code> The ID of the DataType of the Output ¹
	<code>enum[]</code> List of possible values for an EnumType (created on the fly by fastr) ¹
	<code>prefix</code> Commandline prefix of the Output (e.g. <code>-out</code> , <code>-o</code>)
	<code>cardinality</code> Cardinality of the Output
	<code>repeat_prefix</code> Flag indicating if for every value of the Output the prefix is repeated
	<code>required</code> Flag indicating if the output is required
	<code>nospace</code> Flag indicating if there is no space between prefix and value (e.g. <code>-out=val</code>)
	<code>format</code> For DataTypes that have multiple representations, indicate which one to use
	<code>description</code> Long description for an output
	<code>action</code> Special action (defined per DataType) that needs to be performed before creating output value
<code>automatic</code>	Indicate that output doesn't require commandline argument, but is created automatically by a T
<code>method</code>	The collector plugin to use for the gathering automatic output, see the <i>Collector plugins</i>

Table 3.1 – continued from previous page

Attribute	Description
	location

`__abstractmethods__ = frozenset([])`

`__dataschemafile__ = 'FastrInterface.schema.json'`

`__eq__(other)`

`__getstate__()`
Get the state of the FastrInterface object.

Returns state of interface

Return type dict

`__init__(id_, document)`

`__module__ = 'fastr.plugins'`

`__setstate__(state)`
Set the state of the Interface

`check_input_id(id_)`
Check if an id for an object is valid and unused in the Tool. The method will always returns True if it does not raise an exception.

Parameters `id (str)` – the id to check

Returns True

Raises

- `FastrValueError` – if the id is not correctly formatted
- `FastrValueError` – if the id is already in use

`check_output_id(id_)`
Check if an id for an object is valid and unused in the Tool. The method will always returns True if it does not raise an exception.

Parameters `id (str)` – the id to check

Returns True

Raises

- `FastrValueError` – if the id is not correctly formatted
- `FastrValueError` – if the id is already in use

`static collect_errors(result)`
Special error collection for fastr interfaces

`collect_results(result)`
Collect all results of the interface

`collector_plugin_type`
alias of CollectorPlugin

`collectors = CollectorPluginManager [37m[42m[1mLoaded[0m json : <CollectorPlugin: JsonCollector> [37m[42m[1mLoaded[0m]`

¹ datatype and enum are conflicting entries, if both specified datatype has precedence² More details on defining automatica output are given in [TODO]

execute (*target, payload*)

Execute the interface using a specific target and payload (containing a set of values for the arguments)

Parameters

- **target** (*SampleId*) – the target to use
- **payload** (*dict*) – the values for the arguments

Returns result of the execution

Return type *InterfaceResult*

expanding

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
```

get_arguments (*values*)

Get the argument list for this interface

Returns return list of arguments

get_command (*target, payload*)**get_specials** (*payload, output, cardinality_nr*)

Get special attributes. Returns tuples for specials, inputs and outputs that are used for formatting substitutions.

Parameters

- **output** – Output for which to get the specials
- **cardinality_nr** (*int*) – the cardinality number

inputs

```
module = <module 'fastrinterface' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
```

outputs**class** fastr.plugins.FileSystem

Bases: *fastr.core.iplugin.IOPlugin*

The FileSystem plugin is created to handle `file://` type or URLs. This is generally not a good practice, as this is not portable over between machines. However, for test purposes it might be useful.

The URL scheme is rather simple: `file://host/path` (see [wikipedia](#) for details)

We do not make use of the `host` part and at the moment only support localhost (just leave the host empty) leading to `file:///` URLs.

Warning: This plugin ignores the hostname in the URL and does only accept driver letters on Windows in the form `c:/`

```
__abstractmethods__ = frozenset([])
```

```
__init__()
```

```
__module__ = 'fastr.plugins'
```

```
fetch_url (inurl, outpath)
```

Fetch the files from the file.

Parameters

- **inurl** – url to the item in the data store, starts with `file://`

- **outpath** – path where to store the fetch data locally

fetch_value (*inurl*)

Fetch a value from an external file file.

Parameters *inurl* – url of the value to read

Returns the fetched value

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

module = <module ‘filesystem’ from ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/sit

path_to_url (*path, mountpoint=None*)

Construct an url from a given mount point and a relative path to the mount point.

put_url (*inpath, outurl*)

Put the files to the external data store.

Parameters

- **inpath** – path of the local data
- **outurl** – url to where to store the data, starts with `file://`

put_value (*value, outurl*)

Put the value in the external data store.

Parameters

- **value** – value to store
- **outurl** – url to where to store the data, starts with `file://`

scheme = ‘file’

url_to_path (*url*)

Get the path to a file from a url. Currently supports the `file://` scheme

Examples:

```
>>> 'file:///d:/data/project/file.ext'  
'd:\data\project\file.ext'
```

Warning: `file://` will not function cross platform and is mainly for testing

class *fastr.plugins.FlowInterface* (*id_, document*)

Bases: *fastr.core.interface.Interface*

The Interface use for AdvancedFlowNodes to create the advanced data flows that are not implemented in the fastr. This allows nodes to implement new data flows using the plugin system.

The definition of FlowInterfaces are very similar to the default FastrInterfaces.

Note: A flow interface should be using a specific FlowPlugin

```
__abstractmethods__ = frozenset([])  
__dataschemafile__ = ‘FastrInterface.schema.json’  
__eq__ (other)
```

```

__getstate__()
    Get the state of the FastrInterface object.

    Returns state of interface

    Return type dict

__init__(id_, document)
__module__ = 'fastr.plugins'

__setstate__(state)
    Set the state of the Interface

execute(target, payload)

expanding

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
flow_plugin_type
    alias of FlowPlugin

flow_plugins = FlowPluginManager [37m[42m[1mLoaded[0m CrossValidation : <FlowPlugin: CrossValidation>

inputs

module = <module 'flowinterface' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-p
outputs

class fastr.plugins.LinearExecution(finished_callback=None, cancelled_callback=None, status_callback=None)
Bases: fastr.execution.executionpluginmanager.ExecutionPlugin

An execution engine that has a background thread that executes the jobs in order. The queue is a simple FIFO
queue and there is one worker thread that operates in the background. This plugin is meant as a fallback when
other plugins do not function properly. It does not multi-processing so it is safe to use in environments that do
not support that.

__abstractmethods__ = frozenset([])

__init__(finished_callback=None, cancelled_callback=None, status_callback=None)

__module__ = 'fastr.plugins'

cleanup()

exec_worker()

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'linearexecution' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-p

class fastr.plugins.LocalBinaryTarget(binary, paths=None, environment_variables=None,
                                         initscripts=None, modules=None, interpreter=None,
                                         **kwargs)
Bases: fastr.core.target.Target

```

A tool target that is a local binary on the system. Can be found using environmentmodules or a path on the executing machine. A local binary target has a number of fields that can be supplied:

- **binary** (required): the name of the binary/script to call, can also be called `bin` for backwards compatibility.
- **modules**: list of modules to load, this can be environmentmodules or lmod modules. If modules are given, the `paths`, `environment_variables` and `initscripts` are ignored.

- **paths:** a list of paths to add following the structure `{"value": "/path/to/dir", "type": "bin"}`. The types can be `bin` if it should be added to `$PATH` or `lib` if it should be added to the library path (e.g. `$LD_LIBRARY_PATH` for linux).
- **environment_variables:** a dictionary of environment variables to set.
- **initscript:** a list of script to run before running the main tool
- **interpreter:** the interpreter to use to call the binary e.g. `python`

The LocalBinaryTarget will first check if there are modules given and the module subsystem is loaded. If that is the case it will simply unload all current modules and load the given modules. If not it will try to set up the environment itself by using the following steps:

1. Prepend the bin paths to `$PATH`
2. Prepend the lib paths to the correct environment variable
3. Setting the other environment variables given (`$PATH` and the system library path are ignored and cannot be set that way)
4. Call the initscripts one by one

The definition of the target in JSON is very straightforward:

```
{
  "binary": "bin/test.py",
  "interpreter": "python",
  "paths": [
    {
      "type": "bin",
      "value": "vfs://apps/test/bin"
    },
    {
      "type": "lib",
      "value": "./lib"
    }
  ],
  "environment_variables": {
    "othervar": 42,
    "short_var": 1,
    "testvar": "value1"
  },
  "initscripts": [
    "bin/init.sh"
  ],
  "modules": ["elastix/4.8"]
}
```

In XML the definition would be in the form of:

```
<target os="linux" arch="*" modules="elastix/4.8" bin="bin/test.py" interpreter="python">
  <paths>
    <path type="bin" value="vfs://apps/test/bin" />
    <path type="lib" value="./lib" />
  </paths>
  <environment_variables short_var="1">
    <testvar>value1</testvar>
    <othervar>42</othervar>
  </environment_variables>
```

```
<initscripts>
  <initscript>bin/init.sh</initscript>
</initscripts>
</target>
```

```
DYNAMIC_LIBRARY_PATH_DICT = {'windows': 'PATH', 'darwin': 'DYLD_LIBRARY_PATH', 'linux': 'LD_LIBRARY_PATH'}
```

__abstractmethods__ = frozenset([])

__enter__()
Set the environment in such a way that the target will be on the path.

__exit__(exc_type, exc_value, traceback)
Cleanup the environment

__init__(binary, paths=None, environment_variables=None, initscripts=None, modules=None, interpreter=None, **kwargs)
Define a new local binary target. Must be defined either using paths and optionally environment_variables and initscripts, or environment modules.

__module__ = 'fastr.plugins'

call_subprocess(command)
Call a subprocess with logging/timing/profiling

Parameters `command` (`list`) – the command to execute

Returns execution info

Return type `dict`

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg/

module = <module 'localbinarytarget' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg/>

monitor_process(process, resources)
Monitor a process and profile the cpu, memory and io use. Register the resource use every _MONITOR_INTERVAL seconds.

Parameters

- **process** (`subprocess.Popen`) – process to monitor
- **resources** (`ProcessUsageCollection`) – list to append measurements to

run_command(command)

class fastr.plugins.NipypeInterface(id_, nipype_cls=None, document=None)
Bases: `fastr.core.interface.Interface`

Experimental interfaces to using nipype interfaces directly in fastr tools, only using a simple reference.

To create a tool using a nipype interface just create an interface with the correct type and set the nipype argument to the correct class. For example in an xml tool this would become:

```
<interface class="NipypeInterface">
  <nipype_class>nipype.interfaces.elastix.Registration</nipype_class>
</interface>
```

Note: To use these interfaces nipype should be installed on the system.

Warning: This interface plugin is basically functional, but highly experimental!

```
__abstractmethods__ = frozenset([])

__eq__(other)

__getstate__()

__init__(id_, nipyper_cls=None, document=None)

__module__ = 'fastr.plugins'

__setstate__(state)

execute(target, payload)
```

Execute the interface using a specific target and payload (containing a set of values for the arguments)

Parameters

- **target** (*SampleId*) – the target to use
- **payload** (*dict*) – the values for the arguments

Returns result of the execution

Return type *InterfaceResult*

expanding

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
```

get_type (*trait*)

inputs

```
module = <module 'nipyperinterface' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python
```

outputs

classmethod test()

class fastr.plugins.**Null**

Bases: *fastr.core.ioplugin.IOPPlugin*

The Null plugin is created to handle null:// type or URLs. These URLs are indicating the sink should not do anything. The data is not written to anywhere. Besides the scheme, the rest of the URL is ignored.

```
__abstractmethods__ = frozenset([])
```

```
__init__()
```

```
__module__ = 'fastr.plugins'
```

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
```

```
module = <module 'null' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-pac
```

put_url (*inpath, outurl*)

Put the files to the external data store.

Parameters

- **inpath** – path of the local data
- **outurl** – url to where to store the data, starts with file://

put_value (*value, outurl*)

Put the value in the external data store.

Parameters

- **value** – value to store
- **outurl** – url to where to store the data, starts with `file://`

scheme = ‘null’

```
class fastr.plugins.ProcessPoolExecution(finished_callback=None, cancelled_callback=None,
                                         status_callback=None, nr_of_workers=None)
Bases: fastr.execution.executionpluginmanager.ExecutionPlugin
```

A local execution plugin that uses multiprocessing to create a pool of worker processes. This allows fastr to execute jobs in parallel with true concurrency. The number of workers can be specified in the fastr configuration, but the default amount is the number of cores - 1 with a minimum of 1.

Warning: The ProcessPoolExecution does not check memory requirements of jobs and running many workers might lead to memory starvation and thus an unresponsive system.

```
__abstractmethods__ = frozenset([])
__init__(finished_callback=None, cancelled_callback=None, status_callback=None,
         nr_of_workers=None)
__module__ = 'fastr.plugins'
cleanup()
configuration_fields = {'process_pool_worker_number': (<type 'int'>, 3, 'Number of workers to use in a process pool')}
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg/execution_plugins/processpoolexecution.py'
module = <module 'processpoolexecution' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg/execution_plugins/processpoolexecution.py'>
classmethod test()

class fastr.plugins.RQExecution(finished_callback=None, cancelled_callback=None, status_callback=None)
Bases: fastr.execution.executionpluginmanager.ExecutionPlugin
```

A execution plugin based on Redis Queue. Fastr will submit jobs to the redis queue and workers will peel the jobs from the queue and process them.

This system requires a running redis database and the database url has to be set in the fastr configuration.

Note: This execution plugin required the `redis` and `rq` packages to be installed before it can be loaded properly.

```
__abstractmethods__ = frozenset([])
__init__(finished_callback=None, cancelled_callback=None, status_callback=None)
__module__ = 'fastr.plugins'
check_finished()
cleanup()
configuration_fields = {'rq_queue': (<type 'str'>, 'default', 'The redis queue to use'), 'rq_host': (<type 'str'>, 'redis://localhost:6379/0', 'The redis host to use')}
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg/execution_plugins/rqexecution.py'
module = <module 'rqexecution' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg/execution_plugins/rqexecution.py'>
```

```
classmethod run_job(job_id, job_command, job_stdout, job_stderr)
```

```
class fastr.plugins.Reference
```

```
Bases: fastr.core.ioplugin.IOPlugin
```

The Reference plugin is created to handle `ref://` type or URLs. These URLs are to make the sink just write a simple reference file to the data. The reference file contains the DataType and the value so the result can be reconstructed. It for files just leaves the data on disk by reference. This plugin is not useful for production, but is used for testing purposes.

```
__abstractmethods__ = frozenset([])
```

```
__init__()
```

```
__module__ = 'fastr.plugins'
```

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
```

```
module = <module 'reference' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-
```

```
push_sink_data(value, outurl, datatype=None)
```

Write out the sink data from the inpath to the outurl.

Parameters

- **value** (`str`) – the path of the data to be pushed
- **outurl** (`str`) – the url to write the data to
- **datatype** (`DataType`) – the datatype of the data, used for determining the total contents of the transfer

Returns

None

```
scheme = 'ref'
```

```
class fastr.plugins.S3Filesystem
```

```
Bases: fastr.core.ioplugin.IOPlugin
```

Warning: As this IOPlugin is under development, it has not been thoroughly tested.

example url: `s3://bucket.server/path/to/resource`

```
__abstractmethods__ = frozenset([])
```

```
__init__()
```

```
__module__ = 'fastr.plugins'
```

```
cleanup()
```

```
expand_url(url)
```

Expand an S3 URL. This allows a source to collect multiple samples from a single url.

Parameters `url` (`str`) – url to expand

Returns the resulting url(s), a tuple if multiple, otherwise a str

Return type str or tuple of str

```
fetch_url(inurl, outpath)
```

Get the file(s) or values from s3.

Parameters

- **inurl** – url to the item in the data store

- **outpath** – path where to store the fetch data locally

fetch_value (*inurl*)
Fetch a value from S3

Parameters *inurl* – url of the value to read

Returns the fetched value

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

module = <module ‘s3filesystem’ from ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/

put_url (*inpath*, *outurl*)

Upload the files to the S3 storage

Parameters

- **inpath** – path to the local data
- **outurl** – url to where to store the data in the external data store.

put_value (*value*, *outurl*)

Put the value in S3

Parameters

- **value** – value to store
- **outurl** – url to where to store the data, starts with `file://`

scheme = ('s3', 's3list')

class *fastr.plugins.StrongrExecution* (*finished_callback=None*, *cancelled_callback=None*, *status_callback=None*)
Bases: *fastr.execution.executionpluginmanager.ExecutionPlugin*

A execution plugin based on Redis Queue. Fastr will submit jobs to the redis queue and workers will peel the jobs from the queue and process them.

This system requires a running redis database and the database url has to be set in the fastr configuration.

Note: This execution plugin required the `redis` and `rq` packages to be installed before it can be loaded properly.

```
__abstractmethods__ = frozenset([])

__init__ (finished_callback=None, cancelled_callback=None, status_callback=None)
__module__ = 'fastr.plugins'

check_finished ()

cleanup ()

configuration_fields = {}

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p'
module = <module ‘strongrexecution’ from ‘/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/’>
classmethod test ()

class fastr.plugins.VirtualFileSystem
Bases: fastr.core.iopluging.IOPluging
```

The virtual file system class. This is an IOPlugin, but also heavily used internally in fastr for working with directories. The VirtualFileSystem uses the `vfs://` url scheme.

A typical virtual filesystem url is formatted as `vfs://mountpoint/relative/dir/from/mount.ext`

Where the `mountpoint` is defined in the [Config file](#). A list of the currently known mountpoints can be found in the `fastr.config` object

```
>>> fastr.config.mounts
{'example_data': '/home/username/fastr-feature-documentation/fastr/fastr/examples/
˓→data',
 'home': '/home/username/',
 'tmp': '/home/username/FastrTemp'}
```

This shows that a url with the mount `home` such as `vfs://home/tempdir/testfile.txt` would be translated into `/home/username/tempdir/testfile.txt`.

There are a few default mount points defined by Fastr (that can be changed via the config file).

mountpoint	default location
home	the users home directory (<code>expanduser('~/')</code>)
tmp	the fastr temporary dir, defaults to <code>tempfile.gettempdir()</code>
example_data	the fastr example data directory, defaults <code>\$FASTRDIR/example/data</code>

`__abstractmethods__ = frozenset([])`

`__init__()`

Instantiate the VFS plugin

Returns the VirtualFileSysten plugin

`__module__ = 'fastr.plugins'`

`abstract = False`

`static copy_file_dir(inpath, outpath)`

Helper function, copies a file or directory not caring what the inpath actually is

Parameters

- `inpath` – path of the things to be copied
- `outpath` – path of the destination

Returns the result of `shutil.copy2` or `shutil.copytree` (depending on inpath pointing to a file or directory)

`expand_url(url)`

Try to expand the url. For vfs with will return the original url.

Parameters `url` – url to expand

Returns the expanded url (same as url)

`fetch_url(inurl, outpath)`

Fetch the files from the vfs.

Parameters

- `inurl` – url to the item in the data store, starts with `vfs://`
- `outpath` – path where to store the fetch data locally

fetch_value (*inurl*)

Fetch a value from an external vfs file.

Parameters **inurl** – url of the value to read

Returns the fetched value

path_to_url (*path*, *mountpoint=None*, *scheme=None*)

Construct an url from a given mount point and a relative path to the mount point.

Parameters **path** (*str*) – the path to find the url for

Mountpoint **str** mountpoint the url should be under

Returns url of the

put_url (*inpath*, *outurl*)

Put the files to the external data store.

Parameters

- **inpath** – path of the local data
- **outurl** – url to where to store the data, starts with `vfs://`

put_value (*value*, *outurl*)

Put the value in the external data store.

Parameters

- **value** – value to store
- **outurl** – url to where to store the data, starts with `vfs://`

scheme**setup()**

The plugin setup, does nothing but needs to be implemented

url_to_path (*url*, *scheme=None*)

Get the path to a file from a vfs url

Parameters **url** (*str*) – url to get the path for

Returns the matching path

Return type *str*

Raises

- **FastrMountUnknownError** – if the mount in url is unknown
- **FastrUnknownURLSchemeError** – if the url scheme is not correct

Example (the mountpoint tmp points to /tmp):

```
>>> fastr.vfs.url_to_path('vfs://tmp/file.ext')
'/tmp/file.ext'
```

```
class fastr.plugins.VirtualFileSystemRegularExpression
Bases: fastr.core.ioplugin.IOPPlugin
```

The VirtualFileSystemValueList an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs.

A `vfsregex://` URL is a vfs URL that can contain regular expressions on every level of the path. The regular expressions follow the `re module` definitions.

An example of a valid URLs would be:

```
vfsregex://tmp/network_dir/.*/*/__fastr_result__.pickle.gz
vfsregex://tmp/network_dir/nodeX/(?P<id>.*)/__fastr_result__.pickle.gz
```

The first URL would result in all the `__fastr_result__.pickle.gz` in the working directory of a Network. The second URL would only result in the file for a specific node (`nodeX`), but by adding the named group `id` using `(?P<id>.*)` the sample id of the data is automatically set to that group (see [Regular Expression Syntax](#) under the special characters for more info on named groups in regular expression).

Concretely if we would have a directory `vfs://mount/somedir` containing:

```
image_1/Image.nii
image_2/image.nii
image_3/anotherimage.nii
image_5/inconsistentnamingftw.nii
```

we could match these files using `vfsregex://mount/somedir/(?P<id>image_\d+)/.*\.nii` which would result in the following source data after expanding the URL:

```
{'image_1': 'vfs://mount/somedir/image_1/Image.nii',
'image_2': 'vfs://mount/somedir/image_2/image.nii',
'image_3': 'vfs://mount/somedir/image_3/anotherimage.nii',
'image_5': 'vfs://mount/somedir/image_5/inconsistentnamingftw.nii'}
```

Showing the power of this regular expression filtering. Also it shows how the ID group from the URL can be used to have sensible sample ids.

Warning: due to the nature of regexp on multiple levels, this method can be slow when having many matches on the lower level of the path (because the tree of potential matches grows) or when directories that are parts of the path are very large.

```
__abstractmethods__ = frozenset([])
__init__()
__module__ = 'fastr.plugins'
expand_url(url)
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'virtualfilesystemregularexpression' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/
scheme = 'vfsregex'

class fastr.plugins.VirtualFileSystemValueList
Bases: fastr.core.ioplugin.IOPlugin
```

The `VirtualFileSystemValueList` an expand-only type of `IOPlugin`. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs. A `vfslist://` URL basically is a url that points to a file using `vfs`. This file then contains a number lines each containing another URL.

If the contents of a file `vfs://mount/some/path/contents` would be:

```
vfs://mount/some/path/file1.txt
vfs://mount/some/path/file2.txt
vfs://mount/some/path/file3.txt
vfs://mount/some/path/file4.txt
```

Then using the URL `vfslist://mount/some/path/contents` as source data would result in the four files being pulled.

Note: The URLs in a `vfslis`t file do not have to use the `vfs` scheme, but can use any scheme known to the Fastr system.

```
__abstractmethods__ = frozenset([])

__init__()

__module__ = 'fastr.plugins'

expand_url(url)

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p
module = <module 'virtualfilesystemvaluelist' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/p
scheme = 'vfslis

class fastr.plugins.XNATStorage
Bases: fastr.core.ioplugin.IOP plugin
```

Warning: As this IOPlugin is under development, it has not been thoroughly tested.

The XNATStorage plugin is an IOPlugin that can download data from and upload data to an XNAT server. It uses its own `xnat://` URL scheme. This is a scheme specific for this plugin and though it looks somewhat like the XNAT rest interface, a different type of URL.

Data resources can be accessed directly by a data url:

```
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/
↳experiments/experiment001/scans/T1/resources/DICOM
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/
↳experiments/*_BRAIN/scans/T1/resources/DICOM
```

In the second URL you can see a wildcard being used. This is possible at long as it resolves to exactly one item.

The `id` query element will change the field from the default experiment to subject and the `label` query element sets the use of the label as the fastr id (instead of the XNAT id) to True (the default is False)

To disable https transport and use http instead the query string can be modified to add `insecure=true`. This will make the plugin send requests over http:

```
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/
↳experiments/*_BRAIN/scans/T1/resources/DICOM?insecure=true
```

For sinks it is important to know where to save the data. Sometimes you want to save data in a new assessor/resource and it needs to be created. To allow the Fastr sink to create an object in XNAT, you have to supply the type as a query parameter:

```
xnat://xnat.bmia.nl/data/archive/projects/sandbox/subjects/S01/experiments/_BRAIN/
↳assessors/test_assessor/resources/IMAGE/files/image.nii.gz?resource_
↳type=xnat:resourceCatalog&assessor_type=xnat:qcAssessmentData
```

Valid options are: `subject_type`, `experiment_type`, `assessor_type`, `scan_type`, and `resource_type`.

If you want to do a search where multiple resources are returned, it is possible to use a search url:

```
xnat://xnat.example.com/search?projects=sandbox&subjects=subject[0-9][0-9][0-9]&  
- experiments=_BRAIN&scans=T1&resources=DICOM
```

This will return all DICOMs for the T1 scans for experiments that end with _BRAIN that belong to a subjectXXX where XXX is a 3 digit number. By default the ID for the samples will be the experiment XNAT ID (e.g. XNAT_E00123). The wildcards that can be used are the same UNIX shell-style wildcards as provided by the module `fnmatch`.

It is possible to change the id to a different fields id or label. Valid fields are project, subject, experiment, scan, and resource:

```
xnat://xnat.example.com/search?projects=sandbox&subjects=subject[0-9][0-9][0-9]&  
- experiments=_BRAIN&scans=T1&resources=DICOM&id=subject&label=true
```

The following variables can be set in the search query:

variable	default	usage
projects	*	The project(s) to select, can contain wildcards (see <code>fnmatch</code>)
subjects	*	The subject(s) to select, can contain wildcards (see <code>fnmatch</code>)
experiments	*	The experiment(s) to select, can contain wildcards (see <code>fnmatch</code>)
scans	*	The scan(s) to select, can contain wildcards (see <code>fnmatch</code>)
resources	*	The resource(s) to select, can contain wildcards (see <code>fnmatch</code>)
id	experiment	What field to use as the id, can be: project, subject, experiment, scan, or resource
label	false	Indicate the XNAT label should be used as fastr id, options true or false
insecure	false	Change the url scheme to be used to http instead of https
verify	true	(Dis)able the verification of SSL certificates
regex	false	Change search to use regex <code>re.match()</code> instead of fnmatch for matching
overwrite	false	Tell XNAT to overwrite existing files if a file with the name is already present

For storing credentials the `.netrc` file can be used. This is a common way to store credentials on UNIX systems. It is required that the file is only accessible by the owner only or a `NetrcParseError` will be raised. A netrc file is really easy to create, as its entries look like:

```
machine xnat.example.com  
login username  
password secret123
```

See the `netrc` module or the [GNU inet utils website](#) for more information about the `.netrc` file.

Note: On windows the location of the netrc file is assumed to be `os.path.expanduser('~/_.netrc')`. The leading underscore is because windows does not like filename starting with a dot.

Note: For scan the label will be the scan type (this is initially the same as the series description, but can be updated manually or the XNAT scan type cleanup).

Warning: labels in XNAT are not guaranteed to be unique, so be careful when using them as the sample ID.

For background on XNAT, see the [XNAT API DIRECTORY](#) for the REST API of XNAT.

```
__abstractmethods__ = frozenset([])

__init__()

__module__ = 'fastr.plugins'

cleanup()

connect(server, path='', insecure=False, verify=True)

expand_url(url)

fetch_url(inurl, outpath)
```

Get the file(s) or values from XNAT.

Parameters

- **inurl** – url to the item in the data store
- **outpath** – path where to store the fetch data locally

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-p

module = <module 'xnatstorage' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/

put_url (inpath, outurl)

Upload the files to the XNAT storage

Parameters

- **inpath** – path to the local data
- **outurl** – url to where to store the data in the external data store.

scheme = 'xnat'

server

static upload (resource, in_path, location, retries=3, overwrite=False)

xnat

fastr.plugins.json
alias of JsonCollector

fastr.plugins.path
alias of PathCollector

fastr.plugins.stdout
alias of StdoutCollector

version Module

This module keeps track of the version of the currently used Fastr framework. It can check its version from mercurial or a saved file

fastr.version.clear_version()

Remove the cached version info

fastr.version.get_base_version()

Get the version from the top-level version file

Returns the version

Rtype str

`fastr.version.get_hg_info()`

Read information about the current mercurial branch and revision

Returns tuple containing head revision and branch

`fastr.version.get_saved_version()`

Get cached version from file

Returns tuple with version, head revision and branch

`fastr.version.save_version(current_version, current_hg_head, current_hg_branch)`

Cache the version information (useful for when installing)

Parameters

- `current_version (str)` – version
- `current_hg_head (str)` – mercurial head revision
- `current_hg_branch (str)` – mercurial branch

Returns

Subpackages

`core Package`

`core Package`

This module contains all of the core components of fastr. It has the classes to create networks and work with them.

basemanager Module

This module contains the core class for all managers

`class fastr.core.basemanager.BaseManager(path=None, recursive=False)`

Bases: `_abcoll.MutableMapping`

Baseclass for a Manager, subclasses needs to override the following methods:

`BaseManager._item_extension, BaseManager._load_item()`

`_item_extension()`

Abstract property that sets the extension of the files to be loaded by the BaseManager. When scanning for items, only files with this extension will be loaded.

Returns desired extension

Return type `str`

Raises `FastrNotImplementedError` – if property not reimplemented in subclass

`_load_item(filepath, namespace)`

Abstract method to load an item of the BaseManager. This function is not implemented and needs to be reimplemented by a subclass.

Parameters

- `filepath (str)` – path of the item to load
- `namespace (str)` – the namespace of the item to be loaded

Returns the loaded item

Raises `FastrNotImplementedError` – if called without being reimplemented by a subclass

`__abstractmethods__ = frozenset(['_load_item', '_item_extension'])`

`__delitem__(key)`
Remove item from the BaseManager

Parameters `key` – key of the item to remove

Returns None

Raises `FastrKeyError` – if the key is not found in the BaseManager

`__getitem__(key)`
Retrieve item from BaseManager

Parameters `key` – the key of the item to retrieve

Returns the value indicated by the key

Raises `FastrKeyError` – if the key is not found in the BaseManager

`__init__(path=None, recursive=False)`
The BaseManager constructor

Parameters

- `path (str or None)` – path to scan for items, or None for no path
- `recursive (bool)` – Flag to indicate a recursive search is desired

Returns the newly created BaseManager

Return type `BaseManager`

`__iter__()`
Get an iterator from the BaseManager. The iterator will iterate over the keys of the BaseManager.

Returns the iterator

Return type dictionary-keyiterator

`__keytransform__(key)`
Identity transform for the keys. This function can be reimplemented by a subclass to implement a different key transform.

Parameters `key` – key to transform

Returns the transformed key (in this case the same key as inputted)

`__len__()`
Return the number of items in the BaseManager

Returns number of items in the BaseManager

Return type `int`

`__metaclass__`
alias of ABCMeta

`__module__ = 'fastr.core.basemanager'`

`__repr__()`
Convert the BaseManager to a representation string.

Returns Representation string

Return type `str`

`__setitem__(key, value)`
Set item in the BaseManager

Parameters

- **key** – the key of the item to store
- **value** – the value of the item to store

Returns None

`data`

The actual data dict underlying this Manager

`match_filename(filename)`

Check if the filename matches the pattern the manager expects.

Parameters `filename` – filename to match

Returns flag indicating that the filename matches

`populate()`

Populate the manager with the data. This is a method that will be called when the Managers data is first accessed. This way we avoid doing expensive directory scans when the data is never requested.

`reload()`

Reload entire contents of this manager.

baseplugin Module

The base class for all Plugins in the fastr system

`class fastr.core.baseplugin.BasePlugin`

Bases: `object`

Base class for Plugins in the fastr system.

`__abstractmethods__ = frozenset([])`

`__dict__ = dict_proxy({'status': <fastr.utils.classproperty.ClassPropertyDescriptor object>, '__module__': 'fastr.core.baseplugin'})`

`__init__()`

The BasePlugin constructor.

Returns the created plugin

Return type `BasePlugin`

Raises `FastrPluginNotLoaded` – if the plugin did not load correctly

`__metaclass__`

alias of `PluginMeta`

`__module__ = 'fastr.core.baseplugin'`

`__repr__()`

`__str__()`

Create string representation of the plugin.

Returns string representation

Return type `str`

`__weakref__`
list of weak references to the object (if defined)

`cleanup()`
Perform any cleanup action needed when the plugin use ended. This can be closing filesstreams etc.

`configuration_fields = {}`

`fullid = 'fastr://plugins/BasePlugin'`

`id = 'BasePlugin'`

`instantiate = False`

`module = None`

`classmethod register_configuration()`
Register and test the configuration fields of the plugin

`classmethod set_code(source_code)`
Set the filename and source code of the plugin

Parameters `source_code (str)` – the source code of the plugin

`classmethod set_status(status, message, exception=None)`
Update the status of the plugin

Parameters

- `status (str)` – the new status
- `message (str)` – message explaining the status change
- `exception (str)` – stacktrace of the exception causing the failed load

`source_code`
A descriptor that can act like a property for a class.

`status = '\x1b[46mUnInitialized\x1b[0m'`

`status_message = 'Plugin object created'`

`classmethod test()`
Test the plugin, default behaviour is just to instantiate the plugin

`class fastr.core.baseplugin.Plugin`
Bases: `fastr.core.baseplugin.BasePlugin`

`__abstractmethods__ = frozenset([])`

`__module__ = 'fastr.core.baseplugin'`

`class fastr.core.baseplugin.PluginMeta`
Bases: `abc.ABCMeta`

Meta class for the BasePlugin.

`__module__ = 'fastr.core.baseplugin'`

`__repr__()`

`class fastr.core.baseplugin.PluginState`
Bases: `enum.Enum`

Plugin status Enum.

`__format__(format_spec)`

```
__module__ = 'fastr.core.baseplugin'
static __new__(value)
__reduce_ex__(proto)
__repr__()
__str__()

failed = 'x1b[37m\x1b[41m\x1b[1mFailed\x1b[0m'
loaded = 'x1b[37m\x1b[42m\x1b[1mLoaded\x1b[0m'
preload = 'x1b[102mPreLoad\x1b[0m'
uninitialized = 'x1b[46mUnInitialized\x1b[0m'
unloaded = 'x1b[46mUnLoaded\x1b[0m'
```

datatypemanager Module

This module manages datatypes. These datatypes are python classes generated from the XML/JSON datatype files.

```
class fastr.core.datatypemanager.DataTypeManager
    Bases: fastr.core.pluginmanager.BasePluginManager
```

The DataTypeManager hold a mapping of all DataTypes in the fast system and can create new DataTypes from files/data structures.

```
__abstractmethods__ = frozenset([])
```

```
__init__()
```

The DataTypeManager constructor will create a new DataTypeManager and populate it with all DataTypes it can find in the paths set in `fastr.config.types_path`.

Returns the created DataTypeManager

```
__keytransform__(key)
```

Key transformation for this mapping. The key transformation allows indexing by both the DataType name as well as the DataType it self.

Parameters `key` (`fastr.datatypes.BaseDataType` or `str`) – The name of the requested datatype or the datatype itself

Returns The requested datatype

```
__module__ = 'fastr.core.datatypemanager'
```

```
create_enumtype(type_id, options, name=None)
```

Create a python class based on an XML file. This function return a completely functional python class based on the contents of a DataType XML file.

Such a class will be of type `EnumType`.

Parameters

- `type_id` (`str`) – the id of the new class
- `options` (`iterable`) – an iterable of options, each option should be str

Returns the newly created subclass of `EnumType`

Raises `FastrTypeError` – if the options is not an iterable of str

fullid

The fullid of the datatype manager

get_type (name)

Read a type given a typename. This will scan all directories in types_path and attempt to load the newest version of the DataType.

Parameters `name (str)` – Name of the datatype that should be imported in the system

Returns the datatype with the requested name, or None if datatype is not found

Note: If type is already in TypeManager it will not load anything and return the already loaded version.

guess_type (value, exists=True, options=None, preferred=None)

Guess the DataType based on a value str.

Parameters

- `value (str)` – the value to guess the type for
- `options (TypeGroup, DataType or tuple of DataTypes)` – The options that are allowed to be guessed from
- `exists (bool)` – Indicate the value exists (if file) and can be checked for validity, if false skip validity check
- `preferred (iterable)` – An iterable of preferred types in case multiple types match.

Returns The resulting DataType or None if no match was found

Raises `FastrTypeError` – if the options argument is of the wrong type

The function will first create a list of all candidate DataTypes. Subsequently, it will check for each candidate if the value would valid. If there are multiple matches, the config value for preferred types is consulted to break the ties. If non of the DataTypes are in the preferred types list, a somewhat random DataType will be picked as the most optimal result.

has_type (name)

Check if the datatype with requested name exists

Parameters `name (str)` – the name of the requested datatype

Returns flag indicating if the datatype exists

Return type `bool`

static isdatatype (item)

Check if item is a valid datatype for the fastr system.

Parameters `item` – item to check

Returns flag indicating if the item is a fastr datatype

Return type `bool`

match_types (*args, **kwargs)

Find the match between a list of DataTypes/TypeGroups, see resolve-datatype for details

Parameters

- `args` – A list of DataType/TypeGroup objects to match
- `kwargs` – A ‘preferred’ keyword argument can be used to indicate a list of DataTypes to prefer in case of ties (first has precedence over later in list)

Returns The best DataType match, or None if no match is possible.

Raises *FastrTypeError* – if not all args are subclasses of BaseDataType

match_types_any(*args)

Find the match between a list of DataTypes/TypeGroups, see resolve-datatype for details

Parameters **args** – A list of DataType/TypeGroup objects to match

Returns A set with all DataTypes that match.

Return type `set`

Raises *FastrTypeError* – if not all args are subclasses of BaseDataType

plugin_class

The PluginClass of the items of the BasePluginManager

poll_datatype(filename)

Poll an xml file to see if there is a definition of a datatype in it.

Parameters **filename** (`str`) – path of the file to poll

Returns tuple with (id, version, basetype) if a datatype is found or (None, None, None) if no datatype is found

populate()

Populate Manager. After scanning for DataTypes, create the AnyType and set the preferred types

preferred_types

dimension Module

`class fastr.core.dimension.Dimension(name, size)`

Bases: `object`

A class representing a dimension. It contains the name and size of the dimension.

`__dict__ = dict_proxy({‘__ne__’: <function __ne__>, ‘__module__’: ‘fastr.core.dimension’, ‘name’: <property object>})`

`__eq__(other)`

Dimension is the same if the name and size are the same

`__init__(name, size)`

The constructor for the dimension.

Parameters

- **name** (`str`) – Name of the dimension
- **size** (`int` or `sympy.Symbol`) – Size fo the dimension

`__module__ = ‘fastr.core.dimension’`

`__ne__(other)`

The not equal test is simply the inverse of the equal test

`__repr__()`

String representation of a Dimension

`__weakref__`

list of weak references to the object (if defined)

`name`

```

size
update_size(value)

```

class `fastr.core.dimension.ForwardsDimensions`
Bases: `fastr.core.dimension.HasDimensions`

Class of objects that have dimensions not because they contain data with dimensions but forward them (optionally with changes via `combine_dimensions`)

```

__abstractmethods__ = frozenset(['source', 'combine_dimensions'])
__module__ = 'fastr.core.dimension'

```

combine_dimensions(*dimensions*)
Method to combine/manipulate the dimensions

Parameters `dimensions` – the input dimensions from the source

Returns dimensions manipulated for this object

Return type tuple of dimensions

dimensions
The dimensions of the object based on the forwarding

source
The source object from which the dimensions are forwarded

Returns the object from which the dimensions are forwarded

Return type `HasDimensions`

```

class fastr.core.dimension.HasDimensions
Bases: object

```

A Mixin class for any object that has a notion of dimensions and size. It uses the dimension property to expose the dimension name and size.

```

__abstractmethods__ = frozenset(['dimensions'])
__dict__ = dict_proxy({'__module__': 'fastr.core.dimension', '__metaclass__': <class 'abc.ABCMeta'>, '_abc_negative_size': 0})
__metaclass__
    alias of ABCMeta
__module__ = 'fastr.core.dimension'
__weakref__
    list of weak references to the object (if defined)

```

dimensions
The dimensions has to be implemented by any subclass. It has to provide a tuple of Dimensions.

Returns dimensions

Return type tuple

dimnames
A tuple containing the dimension names of this object. All items of the tuple are of type str.

ndims
The number of dimensions in this object

size
A tuple containing the size of this object. All items of the tuple are of type int or sympy.Symbol.

inputgroup Module

```
class fastr.core.inputgroup.InputGroup(*args, **kwargs)
    Bases: collections.OrderedDict, fastr.core.dimension.HasDimensions
```

A class representing a group of inputs. Input groups allow the

```
__abstractmethods__ = frozenset([])
```

```
__delitem__(*args, **kwargs)
```

od.__delitem__(y) <==> del od[y]

Note: This is a wrapped version of collections.__delitem__ which triggers an update of the object after being called

```
__getitem__(key)
```

```
__init__(*args, **kwargs)
```

Create a new InputGroup representation

Parameters

- **parent** (NodeRun) – the parent node
- **id** (*str*) – the id of the input group

Raises *FastrTypeError* – if parent is not a NodeRun

Note: This is a wrapped version of fastr.core.inputgroup.__init__ which triggers an update of the object after being called

```
__metaclass__
```

alias of UpdateableMeta

```
__module__ = 'fastr.core.inputgroup'
```

```
__setitem__(*args, **kwargs)
```

Assign an input to this input group.

Parameters

- **key** (*str*) – id of the input
- **value** (*Input*) – the input to assign

Raises *FastrTypeError* – if value of valid type

Note: This is a wrapped version of fastr.core.inputgroup.__setitem__ which triggers an update of the object after being called

```
__updatefunc__()
```

Update the InputGroup. Triggers when a change is made to the content of the InputGroup. Automatically recalculates the size, primary Input etc.

```
__updatetriggers__ = ['__init__', '__setitem__', '__delitem__', 'clear', 'pop', 'popitem', 'setdefault', 'update']
```

clear () → None. Remove all items from od.

Note: This is a wrapped version of `collections.clear` which triggers an update of the object after being called

dimensions

The dimensions of this InputGroup

empty

Bool indicating that this InputGroup is empty (has no data connected)

find_source_index (`target_size, target_dimnames, source_size, source_dimnames, target_index`)

fullid**iterinputvalues**

Iterate over the item in this InputGroup

Returns iterator yielding `SampleItems`

parent

The parent node of this InputGroup

pop (`k[, d]`) → v, remove specified key and return the corresponding

value. If key is not found, d is returned if given, otherwise KeyError is raised.

Note: This is a wrapped version of `collections.pop` which triggers an update of the object after being called

popitem () → (k, v), return and remove a (key, value) pair.

Pairs are returned in LIFO order if last is true or FIFO order if false.

Note: This is a wrapped version of `collections.popitem` which triggers an update of the object after being called

primary

The primary Input in this InputGroup. The primary Input is the Input that defines the size of this InputGroup. In case of ties it will be the first in the tool definition.

setdefault (`k[, d]`) → od.get(k,d), also set od[k]=d if k not in od

Note: This is a wrapped version of `collections.setdefault` which triggers an update of the object after being called

classmethod solve_broadcast (`target_size, target_dimnames, source_size, source_dimnames, target_index, nodegroups=None`)

update (`[E], **F`) → None. Update D from mapping/iterable E and F.

If E present and has a .keys() method, does: for k in E: D[k] = E[k] If E present and lacks .keys() method, does: for (k, v) in E: D[k] = v In either case, this is followed by: for k, v in F.items(): D[k] = v

Note: This is a wrapped version of `_abcoll.update` which triggers an update of the object after being called

inputgroupcombiner Module

class `fastr.core.inputgroupcombiner.BaseInputGroupCombiner` (`parent`)
Bases: `fastr.core.dimension.HasDimensions`

An object that takes the different input groups and combines them in the correct way.

`__abstractmethods__ = frozenset(['merge', 'unmerge', 'iter_input_groups'])`

`__init__` (`parent`)

`__iter__` ()

`__metaclass__`

alias of ABCMeta

`__module__ = 'fastr.core.inputgroupcombiner'`

`dimensions`

`fullid`

The full id of the InputGroupCombiner

`input_groups`

`iter_input_groups()`

Iterate over all the merged samples :return:

`merge` (`list_of_items`)

Given a list of items for each input group, it returns the combined list of items.

Parameters `list_of_items` (`list`) – items to combine

Returns combined list

`merge_failed_annotations` (`list_of_failed_annotations`)

`merge_payloads` (`sample_payloads`)

`merge_sample_data` (`list_of_sample_data`)

`merge_sample_id` (`list_of_sample_ids`)

`merge_sample_index` (`list_of_sample_indexes`)

`merge_sample_jobs` (`list_of_sample_jobs`)

`unmerge` (`item`)

Given a item it will recreate the seperate items, basically this is the inverse operation of merge. However, this create an OrderedDict so that specific input groups can be easily retrieved. To get a round trip, the values of the OrderedDict should be taken:

```
>>> odict_of_items = combiner.unmerge(item)
>>> item = combiner.merge(odict_of_items.values())
```

Parameters `item` (`list`) – the item to unmerge

Returns items

Return type OrderedDict

```
update()
class fastr.core.inputgroupcombiner.DefaultInputGroupCombiner (parent)
Bases: fastr.core.inputgroupcombiner.BaseInputGroupCombiner
```

The default input group combiner combines the input group in a cross product version, taking each combinations of samples between the input groups. So if there are two input groups with one with size N and the other with size M x P the result would be N x M x P samples, with all possible combinations of the samples in each input group.

```
__abstractmethods__ = frozenset(())
__module__ = 'fastr.core.inputgroupcombiner'
iter_input_groups()
merge (list_of_items)
```

Given a list of items for each input group, it returns the combined list of items.

Parameters **list_of_items** (*list*) – items to combine

Returns combined list

unmerge (*item*)

Given a item it will recreate the separate items, basically this is the inverse operation of merge. However, this creates an OrderedDict so that specific input groups can be easily retrieved. To get a round trip, the values of the OrderedDict should be taken:

```
>>> odict_of_items = combiner.unmerge(item)
>>> item = combiner.merge(odict_of_items.values())
```

Parameters **item** (*list*) – the item to unmerge

Returns items

Return type OrderedDict

```
class fastr.core.inputgroupcombiner.MergingInputGroupCombiner (input_groups,
                                                               merge_dimension)
Bases: fastr.core.inputgroupcombiner.BaseInputGroupCombiner
```

The merging input group combiner takes a similar approach as the default combiner but merges dimensions that are the same. If input group A has N(3) x M(2) samples and B has M(2) x P(4) it will not result in N(3) x M(2) x M(2) x P(4), but merge the dimensions M leading to N(3) x M(2) x P(4) in resulting size.

```
__abstractmethods__ = frozenset(())
__init__ (input_groups, merge_dimension)
__module__ = 'fastr.core.inputgroupcombiner'
iter_input_groups()
merge (list_of_items)
unmerge (item)
update()
```

inputoutput Module

Classes for arranging the input and output for nodes.

Exported classes:

Input – An input for a node (holding datatype). Output – The output of a node (holding datatype and value). ConstantOutput – The output of a node (holding datatype and value).

Warning: Don't mess with the Link, Input and Output internals from other places. There will be a huge chances of breaking the network functionality!

```
class fastr.core.inputoutput.AdvancedFlowOutput (node, description)
    Bases: fastr.core.inputoutput.Output
```

Output for nodes that have an advanced flow. This means that the output sample id and index is not the same as the input sample id and index. The AdvancedFlowOutput has one extra dimensions that is created by the Node.

```
__abstractmethods__ = frozenset([])
```

```
__module__ = 'fastr.core.inputoutput'
```

```
dimensions
```

```
class fastr.core.inputoutput.BaseInput (node, description)
```

```
    Bases: fastr.core.inputoutput.BaseInputOutput
```

Base class for all inputs.

```
__abstractmethods__ = frozenset(['itersubinputs', '_update', 'dimensions', 'fullid'])
```

```
__init__ (node, description)
```

Instantiate a BaseInput

Parameters

- **node** – the parent node the input/output belongs to.
- **description** – the ParameterDescription describing the input/output.

Returns the created BaseInput

Raises

- **FastrTypeError** – if description is not of class ParameterDescription
- **FastrDataTypeNotAvailableError** – if the DataType requested cannot be found in the `fastr.typeplist`

```
__lshift__ (other)
```

```
__module__ = 'fastr.core.inputoutput'
```

```
__rrshift__ (other)
```

```
create_link_from (value)
```

```
itersubinputs ()
```

Iterator over the SubInputs

Returns iterator

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

class fastr.core.inputoutput.**BaseInputOutput** (*node, description*)

Bases: *fastr.core.dimension.HasDimensions*, *fastr.core.updateable.Updateable*, *fastr.core.serializable.Serializable*

Base class for Input and Output classes. It mainly implements the properties to access the data from the underlying ParameterDescription.

__abstractmethods__ = frozenset(['*_update*', '*dimensions*', '*fullid*'])

__getstate__ ()

Retrieve the state of the BaseInputOutput

Returns the state of the object

Rtype dict

__init__ (*node, description*)

Instantiate a BaseInputOutput

Parameters

- **node** – the parent node the input/output belongs to.
- **description** – the ParameterDescription describing the input/output.

Returns created BaseInputOutput

Raises

- **FastrTypeError** – if description is not of class ParameterDescription
- **FastrDataTypeNotAvailableError** – if the DataType requested cannot be found in the fastr.typeplist

__iter__ ()

This function is blocked to avoid support for iteration using a legacy __getitem__ method.

Returns None

Raises **FastrNotImplementedError** – always

__module__ = 'fastr.core.inputoutput'

__repr__ ()

Get a string representation for the Input/Output

Returns the string representation

Return type str

__setstate__ (*state*)

Set the state of the BaseInputOutput by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

cardinality (*key=None, job_data=None*)

Determine the cardinality of this Input/Output. Optionally a key can be given to determine for a sample.

Parameters **key** – key for a specific sample

Returns the cardinality

Return type `int`, `sympy.Symbol`, or `None`

check_cardinality (`key=None`)

Check if the actual cardinality matches the cardinality specified in the ParameterDescription. Optionally you can use a key to test for a specific sample.

Parameters `key` – sample_index (tuple of int) or SampleId for desired sample

Returns flag indicating that the cardinality is correct

Return type `bool`

Raises `FastrCardinalityError` – if the Input/Output has an incorrect cardinality description.

datatype

The datatype of this Input/Output

description

The description object of this input/output

fullid

The fullid of the Input/Output, the fullid should be unique and makes the object retrievable by the network.

id

Id of the Input/Output

node

The NodeRun to which this Input/Output belongs

required

Flag indicating that the Input/Output is required

class `fastr.core.inputoutput.BaseOutput` (`node, description`)

Bases: `fastr.core.inputoutput.BaseInputOutput`

Base class for all outputs.

__abstractmethods__ = frozenset(['_update', 'dimensions', 'fullid'])

__init__ (`node, description`)

Instantiate a BaseOutput

Parameters

- **node** – the parent node the output belongs to.
- **description** – the ParameterDescription describing the output.

Returns created BaseOutput

Raises

- `FastrTypeError` – if description is not of class ParameterDescription
- `FastrDataTypeNotFoundError` – if the DataType requested cannot be found in the `fastr.typeplist`

__module__ = 'fastr.core.inputoutput'

automatic

Flag indicating that the Output is generated automatically without being specified on the command line

```
class fastr.core.inputoutput.Input (node, description)
Bases: fastr.core.inputoutput.BaseInput
```

Class representing an input of a node. Such an input will be connected to the output of another node or the output of a constant node to provide the input value.

`__abstractmethods__ = frozenset([])`

`__eq__ (other)`

Compare two Input instances with each other. This function ignores the parent node and update status, but tests rest of the dict for equality.

Parameters `other` (`Input`) – the other instances to compare to

Returns True if equal, False otherwise

Return type `bool`

`__getitem__ (key)`

Retrieve an item from this Input.

Parameters `key` (str, SampleId or tuple) – the key of the requested item, can be a key str, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int the corresponding `SubInput` will be returned. If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned.

Return type `SampleItem` or `SubInput`

Raises

- `FastrTypeError` – if key is not of a valid type
- `FastrKeyError` – if the key is not found

`__getstate__ ()`

Retrieve the state of the Input

Returns the state of the object

Rtype dict

`__init__ (node, description)`

Instantiate an input.

Parameters

- `node` (`NodeRun`) – the parent node of this input.
- `description` (`ParameterDescription`) – the ParameterDescription of the input.

Returns the created Input

`__module__ = 'fastr.core.inputoutput'`

`__setitem__ (key, value)`

Create a link between a SubInput of this Inputs and an Output/Constant

Parameters

- `key` (`int`, `str`) – the key of the SubInput
- `value` (`BaseOutput`, `list`, `tuple`, `dict`, `OrderedDict`) – the target to link, can be an output or a value to create a constant for

Raises `FastrTypeError` – if key is not of a valid type

__setstate__(state)

Set the state of the Input by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

__str__()

Get a string version for the Input

Returns the string version

Return type *str*

append(value)

When you want to append a link to an Input, you can use the append property. This will automatically create a new SubInput to link to.

example:

```
>>> link = node2['input'].append(node1['output'])
```

will create a new SubInput in node2['input'] and link to that.

cardinality(key=None, job_data=None)

Cardinality for an Input is the sum the cardinalities of the SubInputs, unless defined otherwise.

Parameters **key** (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type *int*, *sympy.Symbol*, or *None*

clear()**datatype**

The datatype of this Input

dimensions

The list names of the dimensions in this Input. This will be a list of str.

fullid

The full defining ID for the Input

get_sourced_nodes()

Get a list of all *Nodes* connected as sources to this Input

Returns list of all connected *Nodes*

Return type list

get_sourced_outputs()

Get a list of all *Outputs* connected as sources to this Input

Returns tuple of all connected *Outputs*

Return type tuple

index(value)

Find index of a SubInput

Parameters **value** (*SubInput*) – the *SubInput* to find the index of

Returns key

Return type *int*, *str*

input_group

The id of the InputGroup this Input belongs to.

insert (index)

Insert a new SubInput at index in the sources list

Parameters **key** (*int*) – positive integer for position in `_source` list to insert to

Returns newly inserted `SubInput`

Return type `SubInput`

itersubinputs ()

Iterate over the `SubInputs` in this Input.

Returns iterator yielding `SubInput`

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

remove (value)

Remove a SubInput from the SubInputs list based on the connected Link.

Parameters **value** (`SubInput`, `<fastr.core.inputoutput.SubInput>`) – the `SubInput` or `SubLink` to removed from this Input

source

The mapping of `SubInputs` that are connected and have more than 0 elements.

class fastr.core.inputoutput.MacroOutput (node, description)

Bases: `fastr.core.inputoutput.Output`

`__abstractmethods__ = frozenset([])`

`__module__ = 'fastr.core.inputoutput'`

dimensions**class fastr.core.inputoutput.Output (node, description)**

Bases: `fastr.core.inputoutput.BaseOutput`

Class representing an output of a node. It holds the output values of the tool ran. Output fields can be connected to inputs of other nodes.

`__abstractmethods__ = frozenset([])`

`__eq__ (other)`

Compare two Output instances with each other. This function ignores the parent node, listeners and update status, but tests rest of the dict for equality.

Parameters **other** (`Output`) – the other instances to compare to

Returns True if equal, False otherwise

Return type `bool`

`__getitem__ (key)`

Retrieve an item from this Output. The returned value depends on what type of key used:

- Retrieving data using index tuple: [index_tuple]
- Retrieving data sample_id str: [SampleId]
- Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]

- Retrieving a *SubOutput* using an int or slice: [n] or [n:m]

Parameters key (int, slice, SampleId or tuple) – the key of the requested item, can be a number, slice, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int or slice the corresponding *SubOutput* will be returned (and created if needed). If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned. If the key was a list of SampleId a tuple of SampleItem will be returned.

Return type *SubInput* or SampleItem or list of SampleItem

Raises

- *FastrTypeError* – if key is not of a valid type
- *FastrKeyError* – if the parent Node has not been executed

__getstate__()

Retrieve the state of the Output

Returns the state of the object

Rtype dict

__init__(node, description)

Instantiate an Output

Parameters

- **node** – the parent node the output belongs to.
- **description** – the ParameterDescription describing the output.

Returns created Output

Raises

- *FastrTypeError* – if description is not of class ParameterDescription
- *FastrDataTypeNotFoundError* – if the DataType requested cannot be found in the fastr.typeplist

__module__ = 'fastr.core.inputoutput'

__setstate__(state)

Set the state of the Output by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

__str__()

Get a string version for the Output

Returns the string version

Return type str

blocking

Flag indicating that this Output will cause blocking in the execution

cardinality()

Cardinality of this Output, may depend on the inputs of the parent Node.

Returns the cardinality

Return type `int`, `sympy.Symbol`, or `None`

Raises

- `FastrCardinalityError` – if cardinality references an invalid `Input`
- `FastrTypeError` – if the referenced cardinality values type cannot be cast to int
- `FastrValueError` – if the referenced cardinality value cannot be cast to int

static `create_output_cardinality(desc)`

Create a lambda function that returns an integer value of the cardinality.

param `str desc` The cardinality description string

return output cardinality description

rtype `tuple`

The description string can be one of the following forms:

- N: N number of values needed.
- as:input_name: the same number of values as attached to input_name are needed.
- val:input_name: the number of values needed is the value of input_name.
- unknown: the output cardinality cannot be estimated a priori

datatype

The datatype of this Output

dimensions

The list of the dimensions in this Output. This will be a tuple of Dimension.

fullid

The full defining ID for the Output

listeners

The list of `Links` connected to this Output.

preferred_types

The list of preferred DataTypes for this Output.

resulting_datatype

The DataType that will the results of this Output will have.

valid

Check if the output is valid, i.e. has a valid cardinality

class `fastr.core.inputoutput.SourceOutput(node, description)`

Bases: `fastr.core.inputoutput.Output`

Output for a SourceNodeRun, this type of Output determines the cardinality in a different way than a normal NodeRun.

__abstractmethods__ = frozenset([])

__getitem__(item)

Retrieve an item from this Output. The returned value depends on what type of key used:

- Retrieving data using index tuple: [index_tuple]
- Retrieving data sample_id str: [SampleId]
- Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]
- Retrieving a `SubOutput` using an int or slice: [n] or [n:m]

Parameters `key` (int, slice, SampleId or tuple) – the key of the requested item, can be a number, slice, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int or slice the corresponding `SubOutput` will be returned (and created if needed). If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned. If the key was a list of SampleId a tuple of SampleItem will be returned.

Return type `SubInput` or SampleItem or list of SampleItem

Raises

- `FastrTypeError` – if key is not of a valid type
- `FastrKeyError` – if the parent NodeRun has not been executed

`__init__(node, description)`

Instantiate a FlowOutput

Parameters

- `node` – the parent node the output belongs to.
- `description` – the ParameterDescription describing the output.

Returns created FlowOutput

Raises

- `FastrTypeError` – if description is not of class ParameterDescription
- `FastrDataTypeNotFoundError` – if the DataType requested cannot be found in the fastr.typeplist

`__module__ = 'fastr.core.inputoutput'`

`cardinality()`

Cardinality of this SourceOutput, may depend on the inputs of the parent NodeRun.

Parameters `key` (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type int, sympy.Symbol, or None

`linearized`

A linearized version of the sample data, this is lazily cached linearized version of the underlying SampleCollection.

`class fastr.core.inputoutput.SubInput(input_)`
Bases: `fastr.core.inputoutput.BaseInput`

This class is used by `Input` to allow for multiple links to an `Input`. The SubInput class can hold only a single Link to a (Sub)Output, but behaves very similar to an `Input` otherwise.

`__abstractmethods__ = frozenset([])`

`__eq__(other)`

Compare two SubInput instances with each other. This function ignores the parent, node, source and update status, but tests rest of the dict for equality.

Parameters `other` (`SubInput`) – the other instances to compare to

Returns True if equal, False otherwise

__getitem__(key)

Retrieve an item from this SubInput.

Parameters `key` (`int`) – the index of the requested item

Returns the corresponding `SubInput`

Return type `SubInput`

Raises `FastrTypeError` – if key is not of a valid type

Note: As a SubInput has only one SubInput, only requesting int key 0 or -1 is allowed, and it will return self

__getstate__()

Retrieve the state of the SubInput

Returns the state of the object

Rtype dict

__init__(input_)

Instantiate an SubInput.

Parameters `input` (`Input`) – the parent of this SubInput.

Returns the created SubInput

__module__ = ‘fastr.core.inputoutput’**__setstate__**(state)

Set the state of the SubInput by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

__str__()

Get a string version for the SubInput

Returns the string version

Return type str

cardinality(key=None, job_data=None)

Get the cardinality for this SubInput. The cardinality for a SubInputs is defined by the incoming link.

Parameters `key` (SampleIndex or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type int, sympy.Symbol, or None

description**dimensions**

List of dimension for this SubInput

fullid

The full defining ID for the SubInput

get_sourced_nodes()

Get a list of all `Nodes` connected as sources to this SubInput

Returns list of all connected *Nodes*

Return type list

get_sourced_outputs()

Get a list of all *Outputs* connected as sources to this SubInput

Returns list of all connected *Outputs*

Return type list

input_group

The id of the InputGroup this SubInputs parent belongs to.

iteritems()

Iterate over the SampleItems that are in the SubInput.

Returns iterator yielding SampleItem objects

itersubinputs()

Iterate over SubInputs (for a SubInput it will yield self and stop iterating after that)

Returns iterator yielding *SubInput*

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

node

The Node to which this SubInputs parent belongs

remove(value)

Remove a SubInput from parent Input.

Parameters **value** (*SubInput*) – the *SubInput* to removed from this Input

source

A list with the source *Link*. The list is to be compatible with *Input*

source_output

The *Output* linked to this SubInput

class fastr.core.inputoutput.SubOutput(output, index)

Bases: *fastr.core.inputoutput.Output*

The SubOutput is an Output that represents a slice of another Output.

__abstractmethods__ = frozenset([])

__eq__(other)

Compare two SubOutput instances with each other. This function ignores the parent, node and update status, but tests rest of the dict for equality. equality

Parameters **other** (*SubOutput*) – the other instances to compare to

Returns True if equal, False otherwise

Return type bool

__getitem__(key)

Retrieve an item from this SubOutput. The returned value depends on what type of key used:

- Retrieving data using index tuple: [index_tuple]

- Retrieving data sample_id str: [SampleId]

- Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]
- Retrieving a *SubOutput* using an int or slice: [n] or [n:m]

Parameters **key** (int, slice, SampleId or tuple) – the key of the requested item, can be a number, slice, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int or slice the corresponding *SubOutput* will be returned (and created if needed). If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned. If the key was a list of SampleId a tuple of SampleItem will be returned.

Return type *SubInput* or SampleItem or list of SampleItem

Raises *FastrTypeError* – if key is not of a valid type

`__getstate__()`

Retrieve the state of the SubOutput

Returns the state of the object

Rtype dict

`__init__(output, index)`

Instantiate a SubOutput

Parameters

- **output** – the parent output the suboutput slices.
- **index** (*int* or *slice*) – the way to slice the parent output

Returns created SubOutput

Raises

- *FastrTypeError* – if the output argument is not an instance of *Output*
- *FastrTypeError* – if the index argument is not an *int* or *slice*

`__len__()`

Return the length of the Output.

Note: In a SubOutput this is always 1.

`__module__ = 'fastr.core.inputoutput'`

`__setstate__(state)`

Set the state of the SubOutput by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

`__str__()`

Get a string version for the SubOutput

Returns the string version

Return type str

`cardinality()`

Cardinality of this SubOutput depends on the parent Output and `self.index`

Parameters `key` (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type `int`, `sympy.Symbol`, or `None`

Raises

- `FastrCardinalityError` – if cardinality references an invalid `Input`
- `FastrTypeError` – if the referenced cardinality values type cannot be cast to int
- `FastrValueError` – if the referenced cardinality value cannot be cast to int

datatype

The datatype of this SubOutput

fullid

The full defining ID for the SubOutput

indexrep

Simple representation of the index.

listeners

The list of `Links` connected to this Output.

node

The NodeRun to which this SubOutput belongs

preferred_types

The list of preferred DataTypes for this SubOutput.

resulting_datatype

The DataType that will the results of this SubOutput will have.

samples

The SampleCollection for this SubOutput

interface Module

A module that describes the interface of a Tool. It specifies how a set of input values will be translated to commands to be executed. This creates a generic interface to different ways of executing underlying software.

class `fastr.core.interface.InputSpec`

Bases: `fastr.core.interface.InputSpec`

```
__dict__ = dict_proxy({'__dict__': <attribute '__dict__' of 'InputSpec' objects>, '__module__': 'fastr.core.interface', '__weakref__': <attribute '__weakref__' of 'InputSpec' objects>})
__module__ = 'fastr.core.interface'

static __new__(id_, cardinality, datatype, required=False, description='', default=None, hidden=False)
```

fastr.core.interface.InputSpecBase

alias of `InputSpec`

class `fastr.core.interface.Interface`

Bases: `fastr.core.baseplugin.Plugin`, `fastr.core.serializable.Serializable`

Abstract base class of all Interfaces. Defines the minimal requirements for all Interface implementations.

```
__abstractmethods__ = frozenset(['inputs', 'execute', '__setstate__', 'expanding', '__getstate__', 'outputs'])
```

`__getstate__()`
Retrieve the state of the Interface

Returns the state of the object

Rtype dict

`__metaclass__`
alias of ABCMeta

`__module__ = 'fastr.core.interface'`

`__setstate__(state)`
Set the state of the Interface

`execute(target, payload)`
Execute the interface given the target and payload. The payload should have the form {‘input’: {‘input_id_a’: (value, value), ‘input_id_b’: (value, value)}, ‘output’: {‘output_id_a’: (value, value), ‘output_id_b’: (value, value)}}}

Parameters

- **target** – the target to call
- **payload** – the payload to use

Returns the result of the execution

Return type (tuple of) *InterfaceResult*

expanding
Indicates whether or not this Interface will result in multiple samples per run. If the flow is unaffected, this will be zero, if it is nonzero it means that number of dimension will be added to the sample array.

inputs
OrderedDict of Inputs connected to the Interface. The format should be {input_id: InputSpec}.

outputs
OrderedDict of Output connected to the Interface. The format should be {output_id: OutputSpec}.

classmethod test()
Test the plugin, interfaces do not need to be tested on import

class fastr.core.interface.InterfacePluginManager
Bases: *fastr.core.pluginmanager.PluginSubManager*

Container holding all the CollectorPlugins

`__abstractmethods__ = frozenset([])`

`__init__()`
Create the Coll :param path: :param recursive: :return:

`__module__ = 'fastr.core.interface'`

class fastr.core.interface.InterfaceResult (*result_data*, *log_data*, *payload*, *sample_index=None*, *sample_id=None*, *errors=None*)
Bases: *object*

The class in which Interfaces should wrap their results to be picked up by fastr

`__dict__ = dict_proxy({‘__dict__’: <attribute ‘__dict__’ of ‘InterfaceResult’ objects>, ‘__module__’: ‘fastr.core.interface’})`

`__init__(result_data, log_data, payload, sample_index=None, sample_id=None, errors=None)`

`__module__ = 'fastr.core.interface'`

__weakref__
list of weak references to the object (if defined)

class fastr.core.interface.OutputSpec
Bases: *fastr.core.interface.OutputSpec*

__dict__ = dict_proxy({‘__dict__’: <attribute ‘__dict__’ of ‘OutputSpec’ objects>, ‘__module__’: ‘fastr.core.interface’},)
__module__ = ‘fastr.core.interface’

static __new__(id_, cardinality, datatype, automatic=True, required=False, description=‘’, hid-den=False)

fastr.core.interface.OutputSpecBase
alias of *OutputSpec*

ioplugin Module

This module contains the manager class for IOPlugins and the base class for all IOPlugins

class fastr.core.ioplugin.IOPlugin
Bases: *fastr.core.baseplugin.Plugin*

IOPlugins are used for data import and export for the sources and sinks. The main use of the *IOPlugins* is during execution (see *Execution*). The *IOPlugins* can be accessed via *fastr.ioplugins*, but generally there should be no need for direct interaction with these objects. The use of is mainly via the URL used to specify source and sink data.

__abstractmethods__ = frozenset(['scheme'])

__init__()
Initialization for the IOPlugin

Returns newly created IOPlugin

__metaclass__
alias of ABCMeta

__module__ = ‘fastr.core.ioplugin’

cleanup()
(abstract) Clean up the IOPlugin. This is to do things like closing files or connections. Will be called when the plugin is no longer required.

expand_url(url)

(abstract) Expand an URL. This allows a source to collect multiple samples from a single url. The URL will have a wildcard or point to something with info and multiple urls will be returned.

Parameters **url** (*str*) – url to expand

Returns the resulting url(s), a tuple if multiple, otherwise a str

Return type *str* or tuple of *str*

fetch_url(inurl, outfile)

(abstract) Fetch a file from an external data source.

Parameters

- **inurl** – url to the item in the data store
- **outpath** – path where to store the fetch data locally

fetch_value (inurl)
 (abstract) Fetch a value from an external data source.

Parameters `inurl` – the url of the value to retrieve

Returns the fetched value

static isurl (string)
 Test if given string is an url.

Parameters `string (str)` – string to test

Returns True if the string is an url, False otherwise

Return type `bool`

path_to_url (path, mountpoint=None)
 (abstract) Construct an url from a given mount point and a relative path to the mount point.

Parameters

- `path (str)` – the path to determine the url for
- `mountpoint (str or None)` – the mount point to use, will be automatically detected if None is given

Returns url matching the path

Return type `str`

static print_result (result)
 Print the result of the IOPlugin to stdout to be picked up by the tool

Parameters `result` – value to print as a result

Returns None

pull_source_data (inurl, outdir, sample_id, datatype=None)
 Transfer the source data from inurl to be available in outdir.

Parameters

- `inurl (str)` – the input url to fetch data from
- `outdir (str)` – the directory to write the data to
- `datatype (DataType)` – the datatype of the data, used for determining the total contents of the transfer

Returns None

push_sink_data (inpath, outurl, datatype=None)
 Write out the sink data from the inpath to the outurl.

Parameters

- `inpath (str)` – the path of the data to be pushed
- `outurl (str)` – the url to write the data to
- `datatype (DataType)` – the datatype of the data, used for determining the total contents of the transfer

Returns None

put_url (inpath, outurl)
 (abstract) Put the files to the external data store.

Parameters

- **inpath** – path to the local data
- **outurl** – url to where to store the data in the external data store.

put_value (*value, outurl*)

(abstract) Put the files to the external data store.

Parameters

- **value** – the value to store
- **outurl** – url to where to store the data in the external data store.

scheme

(abstract) This abstract property is to be overwritten by a subclass to indicate the url scheme associated with the IOPlugin.

setup (**args*, ***kwargs*)

(abstract) Setup before data transfer. This can be any function that needs to be used to prepare the plugin for data transfer.

url_to_path (*url*)

(abstract) Get the path to a file from a url.

Parameters **url** (*str*) – the url to retrieve the path for**Returns** the corresponding path**Return type** *str***class** *fastr.core.ioplugin.IOPluginManager*Bases: *fastr.core.pluginmanager.PluginSubManager*

A mapping containing the IOPlugins known to this system

__abstractmethods__ = frozenset([])**__init__** ()

Create the IOPluginManager and populate it.

Returns newly created IOPluginManager**__iter__** ()**__keytransform__** (*key*)**__module__** = 'fastr.core.ioplugin'**cleanup** ()

Cleanup all plugins, this closes files, connections and other things that could be left dangling otherwise.

static create_ioplugin_tool ()

Create the tools which handles sinks and sources. The command of this tool is the main of core.ioplugin.

expand_url (*url*)

Expand the url by filling the wildcards. This function checks the url scheme and uses the expand function of the correct IOPlugin.

Parameters **url** (*str*) – url to expand**Returns** list of urls**Return type** list of str

`populate()`

Populate the IOPlugins manager. After the default directory scan, add the vfs IOPlugin and create the Tools for the IOPlugins

`pull_source_data(url, outdir, sample_id, datatype=None)`

Retrieve data from an external source. This function checks the url scheme and selects the correct IOPlugin to retrieve the data.

Parameters

- **url** – url to pull
- **outdir** (`str`) – the directory to write the data to
- **datatype** (`DataType`) – the datatype of the data, used for determining the total contents of the transfer

Returns None**`push_sink_data(inpath, outurl, datatype=None)`**

Send data to an external source. This function checks the url scheme and selects the correct IOPlugin to retrieve the data.

Parameters

- **inpath** (`str`) – the path of the data to be pushed
- **outurl** (`str`) – the url to write the data to
- **datatype** (`DataType`) – the datatype of the data, used for determining the total contents of the transfer

`put_url(inpath, outurl)`

Put the files to the external data store.

Parameters

- **inpath** – path to the local data
- **outurl** – url to where to store the data in the external data store.

`static register_url_scheme(scheme)`

Register a custom scheme to behave http like. This is needed to parse all things properly with urlparse.

Parameters `scheme` – the scheme to register

`url_to_path(url)`

Retrieve the path for a given url

Parameters `url` (`str`) – the url to parse

Returns the path corresponding to the input url

Return type `str`

`fastr.core.ioplugin.main()`

The main entry point for command line access to the IOPlugin

link Module

The link module contain the Link class. This class represents the links in a network. These links lead from an output (BaseOutput) to an input (BaseInput) and indicate the desired data flow. Links are smart objects, in the sense that when you set their start or end point, they register themselves with the Input and Output. They do all the book keeping, so as long as you only set the source and target of the Link, the link should be valid.

Warning: Don't mess with the Link, Input and Output internals from other places. There will be a huge chances of breaking the network functionality!

```
class fastr.core.link.Link(source, target, parent, id_=None, collapse=None, expand=None)
Bases: fastr.core.dimension.HasDimensions, fastr.core.updateable.Updateable,
fastr.core.serializable.Serializable
```

Class for linking outputs ([BaseOutput](#)) to inputs ([BaseInput](#))

Examples:

```
>>> import fastr
>>> network = fastr.Network()
>>> link1 = network.create_link( n1.ouputs['out1'], n2.inputs['in2'] )

link2 = Link()
link2.source = n1.ouputs['out1']
link2.target = n2.inputs['in2']
```

__abstractmethods__ = frozenset([])

__dataschemafile__ = 'Link.schema.json'

__eq__ (other)

Test for equality between two Links

Parameters **other** ([Link](#)) – object to test against

Returns True for equality, False otherwise

Return type [bool](#)

__getstate__ ()

Retrieve the state of the Link

Returns the state of the object

Rtype [dict](#)

__init__ (source, target, parent, id_=None, collapse=None, expand=None)

Create a new Link in a Network.

Parameters

- **source** ([BaseOutput](#)) – the source output
- **target** ([BaseInput](#)) – the target input
- **parent** ([Network](#) or None) – the parent network
- **id** ([str](#) or [None](#)) – the id of the link, if no **id**_ is given, the id will be in the form of "link_{:d}"
- **collapse** ([int](#), [str](#), or tuple of [int](#)/[str](#)) – the dimensions that the link has to collapse on
- **expand** ([bool](#)) – Does this link need to expand the cardinality into a new sample dimension

Returns newly created Link

Raises

- **FastrValueError** – if parent is not given

- **FastrValueError** – if the source output is not in the same network as the Link
- **FastrValueError** – if the target input is not in the same network as the Link

__module__ = ‘fastr.core.link’

__repr__()
Get a string representation for the Link

Returns the string representation

Return type str

__setstate__(state)
Set the state of the Link by the given state.

Parameters state (dict) – The state to populate the object with

Returns None

Raises FastrValueError – if the parent network is not set

cardinality(index=None)
Cardinality for a Link is given by source Output and the collapse/expand settings

Parameters key (SampleIndex) – key for a specific sample (can be only a sample index!)

Returns the cardinality

Return type int, sympy.Symbol

Raises FastrIndexError – if the index length does not match the number of dimension in the data

collapse
The converging dimensions of this link. Collapsing changes some dimensions of sample lists into cardinality, reshaping the data.

Collapse can be set to a tuple or an int/str, in which case it will be automatically wrapped in a tuple. The int will be seen as indices of the dimensions to collapse. The str will be seen as the name of the dimensions over which to collapse.

Raises FastrTypeError – if assigning a collapse value of a wrong type

collapse_indexes
The converging dimensions of this link as integers. Dimension names are replaced with the corresponding int.

Collapsing changes some dimensions of sample lists into cardinality, reshaping the data

classmethod createobj(state, network=None)
Create object function for Link

Parameters

- **cls** – The class to create
- **state** – The state to use to create the Link
- **network** – the parent Network

Returns newly created Link

destroy()
The destroy function of a link removes all default references to a link. This means the references in the network, input and output connected to this link. If there is no references in other places in the code, it will destroy the link (reference count dropping to zero).

This function is called when a source for an input is set to another value and the links becomes disconnected. This makes sure there is no dangling links.

dimensions

The dimensions of the data delivered by the link. This can be different from the source dimensions because the link can make data collapse or expand.

draw (*context, graph*)**expand**

Flag indicating that the link will expand the cardinality into a new sample dimension to be created.

fullid

The full defining ID for the Input

parent

The Network to which this Link belongs.

source

The source *BaseOutput* of the Link. Setting the source will automatically register the Link with the source BaseOutput. Updating source will also make sure the Link is unregistered with the previous source.

Raises *FastrTypeError* – if assigning a non *BaseOutput*

status**target**

The target *BaseInput* of the Link. Setting the target will automatically register the Link with the target BaseInput. Updating target will also make sure the Link is unregistered with the previous target.

Raises *FastrTypeError* – if assigning a non *BaseInput*

network Module

Network module containing Network facilitators and analysers.

```
class fastr.core.network.Network(id_='unnamed_network', version=None, filename=None)
Bases: fastr.core.serializable.Serializable
```

The NetworkRun contains the entire Run state for a Network execution. It has a working copy of the network, but also includes all temporary data required for the execution. These objects are meant to be single use.

```
NETWORK_DUMP_FILE_NAME = '__fastr_network__.json'
SINK_DUMP_FILE_NAME = '__sink_data__.json'
SOURCE_DUMP_FILE_NAME = '__source_data__.pickle.gz'
__dataschemafile__ = 'Network.schema.json'
```

__eq__ (*other*)

Compare two Networks and see if they are equal.

Parameters *other* (*Network*) –

Returns flag indicating that the Networks are the same

Return type *bool*

__getitem__ (*item*)

Get an item by its fullid. The fullid can point to a link, node, input, output or even subinput/suboutput.

Parameters *item* (*str, unicode*) – fullid of the item to retrieve

Returns the requested item

__getstate__()
Retrieve the state of the Network

Returns the state of the object

Rtype dict

__init__(id_=‘unnamed_network’, version=None, filename=None)
Create a new, empty Network

Parameters **name** (*str*) – name of the Network

Returns newly created Network

Raises **OSError** – if the tmp mount in the config is not a writable directory

__module__ = ‘fastr.core.network’

__ne__(other)
Tests for non-equality, this is the negated version **__eq__**

__repr__()

__setstate__(state)
Set the state of the Network by the given state. This completely overwrites the old state!

Parameters **state** (*dict*) – The state to populate the object with

Returns None

add_link(link)
Add a Link to the Network. Make sure the link is in the link list and the link parent is set to this Network

Parameters **link** (*Link*) – link to add

Raises

- **FastrTypeError** – if link is incorrectly typed
- **FastrNetworkMismatchError** – if the link already belongs to another Network

add_node(node)
Add a Node to the Network. Make sure the node is in the node list and the node parent is set to this Network

Parameters **node** (*Node*) – node to add

Raises **FastrTypeError** – if node is incorrectly typed

add_stepid(stepid, node)
Add a Node to a specific step id

Parameters

- **stepid** (*str*) – the stepid that the node will be added to
- **node** (*Node*) – the node to add to the stepid

check_id(id_)
Check if an id for an object is valid and unused in the Network. The method will always returns True if it does not raise an exception.

Parameters **id** (*str*) – the id to check

Returns True

Raises

- *FastrValueError* – if the id is not correctly formatted
- *FastrValueError* – if the id is already in use

create_constant (*datatype*, *data*, *id_=None*, *stepid=None*, *nodegroup=None*, *sourcegroup=None*)

Create a ConstantNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (*BaseDataType*) – The DataType of the constant node
- **data** (*datatype or list of datatype*) – The data to hold in the constant node
- **id** (*str*) – The id of the constant node to be created
- **stepid** (*str*) – The stepid to add the created constant node to
- **nodegroup** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Returns the newly created constant node

Return type *ConstantNode*

create_link (*source*, *target*, *id_=None*, *collapse=None*, *expand=None*)

Create a link between two Nodes and add it to the current Network.

Parameters

- **source** (*BaseOutput*) – the output that is the source of the link
- **target** (*BaseInput*) – the input that is the target of the link
- **id** (*str*) – the id of the link

Returns the created link

Type *Link*

create_macro (*network*, *id_=None*)

create_node (*tool*, *id_=None*, *stepid=None*, *cores=None*, *memory=None*, *walltime=None*, *nodegroup=None*)

Create a Node in this Network. The Node will be automatically added to the Network.

Parameters

- **tool** (*Tool*) – The Tool to base the Node on
- **id** (*str*) – The id of the node to be created
- **stepid** (*str*) – The stepid to add the created node to
- **nodegroup** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Returns the newly created node

Return type *Node*

create_reference (*source_data*, *output_directory*)

create_sink (*datatype*, *id_=None*, *stepid=None*)

Create a SinkNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (*BaseDataType*) – The DataType of the sink node

- **id** (*str*) – The id of the sink node to be created
- **stepid** (*str*) – The stepid to add the created sink node to

Returns the newly created sink node

Return type *SinkNode*

create_source (*datatype*, *id*=*None*, *stepid*=*None*, *nodegroup*=*None*, *sourcegroup*=*None*)

Create a SourceNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (*BaseDataType*) – The DataType of the source *source_node*
- **id** (*str*) – The id of the source *source_node* to be created
- **stepid** (*str*) – The stepid to add the created source *source_node* to
- **nodegroup** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.
- **sourcegroup** (*str*) – *DEPRECATED!* The nodegroup this SourceNode will be added to

Returns the newly created source *source_node*

Return type *SourceNode*

draw (*name*=*None*, *image_format*=*None*, *draw_dimensions*=*False*, *context*=*None*, *graph*=*None*, *expand_macro*=*False*)

draw_network (*name*=’network_layout’, *img_format*=’svg’, *draw_dimension*=*False*, *expand_macro*=*False*)

Output a dot file and try to convert it to an image file.

Parameters **img_format** (*str*) – extension of the image format to convert to

Returns path of the image created or *None* if failed

Return type *str* or *None*

execute (*sourcedata*, *sinkdata*, *blocking*=*True*, ***kwargs*)

fullid

The fullid of the Network, within the network scope

global_id

The global id of the Network, this is different for networks used in macronodes, as they still have parents.

id

The id of the Network. This is a read only property.

is_valid()

namespace = *None*

The namespace this network lives in, this will be set by the NetworkManager on load

nodegroups

Give an overview of the nodegroups in the network

remove (*value*)

Remove an item from the Network.

Parameters **value** (*Node* or *Link*) – the item to remove

```
classmethod test(reference_data_dir, network=None, source_data=None,
                 force_remove_temp=False)
```

Execute the network with the source data specified and test the results against the reference data. This effectively tests the network execution.

Parameters

- **reference_data_dir** (*str*) – The path or vfs url of reference data to compare with
- **source_data** (*dict*) – The source data to use

networkmanager Module

This module contains the tool manager class

```
class fastr.core.networkmanager.NetworkManager(path)
```

Bases: *fastr.core.objectmanager.ObjectManager*

```
__abstractmethods__ = frozenset([])
```

```
__module__ = 'fastr.core.networkmanager'
```

```
get_object_version(obj)
```

```
object_class
```

```
fastr.core.networkmanager.networklist = NetworkManager add_ints v0.0 : /home/docs/checkouts/readthedocs.org
```

The fastr networklist

node Module

A module to maintain a network node.

Exported classes:

Node – A class encapsulating a tool. ConstantNode – A node encapsulating an Output to set scalar values. SourceNode – A class providing a handle to a file.

```
class fastr.core.node.AdvancedFlowNode(tool, id=None, parent=None, cores=None, memory=None, walltime=None, nodegroup=None)
```

Bases: *fastr.core.node.FlowNode*

```
__abstractmethods__ = frozenset([])
```

```
__module__ = 'fastr.core.node'
```

```
class fastr.core.node.ConstantNode(datatype, data, id=None, parent=None, nodegroup=None)
```

Bases: *fastr.core.node.SourceNode*

Class encapsulating one output for which a value can be set. For example used to set a scalar value to the input of a node.

```
__abstractmethods__ = frozenset([])
```

```
__dataschemafile__ = 'ConstantNode.schema.json'
```

```
__getstate__()
```

Retrieve the state of the ConstantNode

Returns the state of the object

Rtype dict

`__init__(datatype, data, id_=None, parent=None, nodegroup=None)`

Instantiation of the ConstantNode.

Parameters

- **datatype** – The datatype of the output.
- **data** – the prefilled data to use.
- **id** – The url pattern.

This class should never be instantiated directly (unless you know what you are doing). Instead create a constant using the network class like shown in the usage example below.

usage example:

```
>>> import fastr
>>> network = fastr.Network()
>>> source = network.create_source(datatype=fastr.typelist['ITKImageFile'], ↴
-> id_='sourceN')
```

or alternatively create a constant node by assigning data to an item in an InputDict:

```
>>> node_a.inputs['in'] = ['some', 'data']
```

which automatically creates and links a ConstantNode to the specified Input

`__module__ = 'fastr.core.node'`**`__setstate__(state)`**

Set the state of the ConstantNode by the given state.

Parameters `state (dict)` – The state to populate the object with

Returns None

`data`

The data stored in this constant node

`draw(context, graph, color=None)`**`set_data(data=None, ids=None)`**

Set the data of this constant node in the correct way. This is mainly for compatibility with the parent class SourceNode

Parameters

- **data (dict or list of urls)** – the data to use
- **ids** – if data is a list, a list of accompanying ids

```
class fastr.core.node.FlowNode(tool, id_=None, parent=None, cores=None, memory=None, wall-time=None, nodegroup=None)
```

Bases: `fastr.core.node.Node`

A Flow Node is a special subclass of Nodes in which the amount of samples can vary per Output. This allows non-default data flows.

`__abstractmethods__ = frozenset([])`**`__init__(tool, id_=None, parent=None, cores=None, memory=None, walltime=None, node-group=None)`**

Instantiate a flow node.

Parameters

- **tool** ([Tool](#)) – The tool to base the node on
- **id** ([str](#)) – the id of the node
- **parent** ([Network](#)) – the parent network of the node

Returns the newly created FlowNode

__module__ = ‘fastr.core.node’

blocking

A FlowNode is (for the moment) always considered blocking.

Returns True

dimensions

Names of the dimensions in the Node output. These will be reflected in the SampleIdList of this Node.

outputszie

Size of the outputs in this Node

class fastr.core.node.**InputDict** (*args, **kwds)
Bases: [collections.OrderedDict](#)

The container containing the Inputs of Node. Implements helper functions for the easy linking syntax.

__module__ = ‘fastr.core.node’

__setitem__ (key, value, dict_setitem=<slot wrapper ‘__setitem__’ of ‘dict’ objects>)

Set an item in the input dictionary. The behaviour depends on the type of the value. For a [BaseInput](#), the input will simply be added to the list of inputs. For a [BaseOutput](#), a link between the output and input will be created.

Parameters

- **key** ([str](#)) – id of the input to assign/link
- **value** ([BaseInput](#) or [BaseOutput](#)) – either the input to add or the output to link
- **dict_setitem** – the setitem function to use for the underlying OrderedDict insert

class fastr.core.node.**MacroNode** (network, id_=None, parent=None, cores=None, memory=None, walltime=None, nodegroup=None)
Bases: [fastr.core.node.Node](#)

MacroNode encapsulates an entire network in a single node.

__abstractmethods__ = frozenset([])

__getstate__()

Retrieve the state of the MacroNode

Returns the state of the object

Rtype dict

__init__ (network, id_=None, parent=None, cores=None, memory=None, walltime=None, nodegroup=None)

Parameters **network** ([Network](#)) – network to create macronode for

__module__ = ‘fastr.core.node’

__setstate__ (state)

draw (context, graph, color=None)

draw_link_target (context, port_name, input=True)

get_output_info (*output*)

This functions maps the output dimensions based on the input dimensions of the macro. This is cached for speed as this can become rather costly otherwise

Parameters **output** – output to get info for

Returns tuple of Dimensions

network

```
class fastr.core.node.Node(tool, id=None, node_class=None, parent=None, cores=None, memory=None, walltime=None, nodegroup=None)
Bases: fastr.core.dimension.HasDimensions, fastr.core.updateable.Updateable, fastr.core.serializable.Serializable
```

The class encapsulating a node in the network. The node is responsible for setting and checking inputs and outputs based on the description provided by a tool instance.

__abstractmethods__ = frozenset([])**__dataschemafile__** = ‘Node.schema.json’**__eq__** (*other*)

Compare two Node instances with each other. This function ignores the parent and update status, but tests rest of the dict for equality. equality

Parameters **other** (Node) – the other instances to compare to

Returns True if equal, False otherwise

__getstate__ ()

Retrieve the state of the Node

Returns the state of the object

Rtype dict**__init__** (*tool*, *id*=None, *node_class*=None, *parent*=None, *cores*=None, *memory*=None, *walltime*=None, *nodegroup*=None)

Instantiate a node.

Parameters

- **tool** (*Tool*) – The tool to base the node on
- **id** (*str*) – the id of the node
- **node_class** (*str*) – The class of the NodeRun to create (e.g. SourceNodeRun, NodeRun)
- **parent** (*Network*) – the parent network of the node
- **cores** (*int*) – number of cores required for executing this Node
- **memory** (*str*) – amount of memory required in the form d+[mGgG] where M is for megabyte and G for gigabyte
- **walltime** (*str*) – amount of time required in second or in the form HOURS:MINUTES:SECOND

Returns the newly created Node

__metaclass__

alias of ABCMeta

__module__ = ‘fastr.core.node’

__repr__()

Get a string representation for the Node

Returns the string representation

Return type str

__setstate__(state)

Set the state of the Node by the given state.

Parameters state (dict) – The state to populate the object with

Returns None

__str__()

Get a string version for the Node

Returns the string version

Return type str

blocking

Indicate that the results of this Node cannot be determined without first executing the Node, causing a blockage in the creation of jobs. A blocking Nodes causes the Chunk borders.

classmethod createobj(state, network=None)

dimensions

dimnames

Names of the dimensions in the Node output. These will be reflected in the SampleIdList of this Node.

draw(context, graph, color=None)

draw_id(context)

draw_link_target(context, port_name, input=True)

find_source_index(target_index, target, source)

fullid

The full defining ID for the Node inside the network

get_sourced_nodes()

A list of all Nodes connected as sources to this Node

Returns list of all nodes that are connected to an input of this node

global_id

The global defining ID for the Node from the main network (goes out of macro nodes to root network)

id

The id of the Node

id_=None

The Node id is a unique string identifying the Node

input_groups

A list of input groups for this Node. An input group is InputGroup object filled according to the Node

inputs =None

A list of inputs of this Node

listeners

All the listeners requesting output of this node, this means the listeners of all Outputs and SubOutputs

merge_dimensions

name
Name of the Tool the Node was based on. In case a Toolless Node was used the class name is given.

nodegroup

outputs = None
A list of outputs of this Node

outputszie
The size of output of this SourceNode

parent
The parent is the Network this Node is part of

required_cores
Number of cores required for the execution of this Node

required_memory
Amount of memory required for the execution of this Node. Follows the format d+[mMgG] so 500M or 4g would be valid ways to specify 500 megabytes or 4 gigabyte of memory.

required_time
Amount of time required for the execution of this Node. Follows the format of a number of second or H:M:S, with H the number of hours, M the number of minutes and S the number of seconds.

status

tool

update_input_groups()
Update all input groups in this node

class fastr.core.node.OutputDict(*args, **kwds)
Bases: `collections.OrderedDict`

The container containing the Inputs of Node. Only checks if the inserted values are actually outputs.

__module__ = 'fastr.core.node'

__setitem__(key, value, dict_setitem=<slot wrapper '__setitem__' of 'dict' objects>)
Set an output.

Parameters

- **key** (`str`) – the of the item to set
- **value** (`BaseOutput`) – the output to set
- **dict_setitem** – the setitem function to use for the underlying OrderedDict insert

class fastr.core.node.SinkNode(datatype, id_=None, parent=None, nodegroup=None)
Bases: `fastr.core.node.Node`

Class which handles where the output goes. This can be any kind of file, e.g. image files, textfiles, config files, etc.

__abstractmethods__ = frozenset([])

__dataschemafile__ = 'SinkNode.schema.json'

__getstate__()

__init__(datatype, id_=None, parent=None, nodegroup=None)
Instantiation of the SourceNode.

Parameters

- **datatype** – The datatype of the output.
- **id** – the id of the node to create

Returns newly created sink node

usage example:

```
>>> import fastr
>>> network = fastr.Network()
>>> sink = network.create_sink(datatype=fastr.typelist['ITKImageFile'], id_=  
↳'SinkN')
```

__module__ = 'fastr.core.node'**__setstate__**(state)**datatype**

The datatype of the data this sink can store.

draw(context, graph, color=None)**input**

The default input of the sink Node

class fastr.core.node.**SourceNode**(datatype, id_=None, parent=None, nodegroup=None)Bases: *fastr.core.node.FlowNode*

Class providing a connection to data resources. This can be any kind of file, stream, database, etc from which data can be received.

__abstractmethods__ = frozenset([])**__dataschemafile__** = 'SourceNode.schema.json'**__eq__**(other)

Compare two Node instances with each other. This function ignores the parent and update status, but tests rest of the dict for equality. equality

Parameters **other** (*Node*) – the other instances to compare to**Returns** True if equal, False otherwise**__getstate__**()

Retrieve the state of the SourceNode

Returns the state of the object**Rtype** dict**__init__**(datatype, id_=None, parent=None, nodegroup=None)

Instantiation of the SourceNode.

Parameters

- **datatype** – The (id of) the datatype of the output.
- **id** – The url pattern.

This class should never be instantiated directly (unless you know what you are doing). Instead create a source using the network class like shown in the usage example below.

usage example:

```
>>> import fastr
>>> network = fastr.Network()
>>> source = network.create_source(datatype=fastr.typeList['ITKImageFile'],
    ↪id_='sourceN')
```

__module__ = 'fastr.core.node'**__setstate__(state)**

Set the state of the SourceNode by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

datatype

The datatype of the data this source supplies.

dimensions

The dimensions in the SourceNode output. These will be reflected in the SampleIdLists.

draw(context, graph, color=None)**nodegroup****output**

Shorthand for `self.outputs['output']`

set_data(data, ids=None)

Set the data of this source node.

Parameters

- **data** (*dict*, *OrderedDict* or *list of urls*) – the data to use
- **ids** – if data is a list, a list of accompanying ids

sourcegroup**valid**

This does nothing. It only overloads the valid method of Node(). The original is intended to check if the inputs are connected to some output. Since this class does not implement inputs, it is skipped.

objectmanager Module

This module contains the object manager class

class fastr.core.objectmanager.ObjectManager(path)

Bases: `fastr.core.basemanager.BaseManager`

Class for managing all the objects loaded in the fastr system

__abstractmethods__ = frozenset(['object_class', 'get_object_version'])**__contains__(key)**

Check if an item is in the ObjectManager

Parameters **key** (*str* or *tuple*) – object id or tuple (Objectid, version)

Returns flag indicating the item is in the manager

__getitem__(key)

Retrieve a Object from the ObjectManager. You can request by only an id, which results in the newest version of the Object being returned, or request using both an id and a version.

Parameters `key` (`str` or `tuple`) – object id or tuple (Objectid, version)

Returns the requested Object

Raises `FastrObjectUnknownError` – if a non-existing Object was requested

__init__(path)
Create a ObjectManager and scan path to search for Objects

Parameters `path` (`str` or `iterable of str`) – the path(s) to scan for Objects

Returns newly created ObjectManager

__keytransform__(key)
Key transform, used for allowing indexing both by id-only and by (id, version)

Parameters `key` – key to transform

Returns key in form (id, version)

__module__ = 'fastr.core.objectmanager'

get_object_version(obj)
Get the version of a given object

Parameters `object` – the object to use

Returns the version of the object

object_class
The class of the objects to populate the manager with

objectversions(obj)
Return a list of available versions for the object

Parameters `object` – The object to check the versions for. Can be either a *Object* or a *str*.

Returns List of version objects. Returns *None* when the given object is not known.

todict()
Return a dictionary version of the Manager

Returns manager as a dict

pluginmanager Module

This module contains the Manager class for Plugins in the fastr system

class `fastr.core.pluginmanager.BasePluginManager(path=None, recursive=False)`
Bases: `fastr.core.basemanager.BaseManager`

Baseclass for PluginManagers, need to override the self._plugin_class

__abstractmethods__ = frozenset(['plugin_class'])

__getitem__(key)
Retrieve item from BaseManager

Parameters `key` – the key of the item to retrieve

Returns the value indicated by the key

Raises `FastrKeyError` – if the key is not found in the BaseManager

__init__(path=None, recursive=False)
Create a BasePluginManager and scan the give path for matching plugins

Parameters

- **path** (*str*) – path to scan
- **recursive** (*bool*) – flag to indicate a recursive search

Returns newly created plugin manager**Raises** *FastrTypeError* – if self._plugin_class is set to a class not subclassing BasePlugin**__module__** = ‘fastr.core.pluginmanager’**load_plugin** (*plugin_key*)**plugin_class**

The class from which the plugins must be subclassed

populate ()

Populate the manager with the data. This is a method that will be called when the Managers data is first accessed. This way we avoid doing expensive directory scans when the data is never requested.

test_plugin (*plugin*)**class** fastr.core.pluginmanager.**LazyModule** (*name, parent, plugin_manager*)

Bases: module

A module that allows content to be loaded lazily from plugins. It generally is (almost) empty and gets (partially) populated when an attribute cannot be found. This allows lazy loading and plugins depending on other plugins.

__getattr__ (*item*)

The getattr is called when getattribute does not return a value and is used as a fallback. In this case we try to find the value normally and will trigger the plugin manager if it cannot be found.

Parameters **item** (*str*) – attribute to retrieve**Returns** the requested attribute**__init__** (*name, parent, plugin_manager*)**__module__** = ‘fastr.core.pluginmanager’**__repr__** ()**__weakref__**

list of weak references to the object (if defined)

class fastr.core.pluginmanager.**PluginManager** (*path=None*)Bases: *fastr.core.pluginmanager.BasePluginManager***__abstractmethods__** = frozenset([])**__init__** (*path=None*)**__module__** = ‘fastr.core.pluginmanager’**__setitem__** (*key, value*)

Store an item in the BaseManager, will ignore the item if the key is already present in the BaseManager.

Parameters

- **name** – the key of the item to save
- **value** – the value of the item to save

Returns None**plugin_class**

The plugin manager contains any Plugin subclass

```
class fastr.core.pluginmanager.PluginSubManager(parent, plugin_class)
Bases: fastr.core.pluginmanager.BasePluginManager
```

A PluginManager that is a selection of a parent plugin manager. It uses the PluginsView to only expose part of the parent PluginManager. This is used to create plugin managers for only certain types of plugins (e.g. IOPlugins) without loading them multiple times.

```
__abstractmethods__ = frozenset([])
```

```
__init__(parent, plugin_class)
```

```
__module__ = 'fastr.core.pluginmanager'
```

```
data
```

```
plugin_class
```

PluginSubManagers only expose the plugins of a certain class

```
class fastr.core.pluginmanager.PluginsView(parent, plugin_class)
```

Bases: _abcoll.MutableMapping

A collection that acts like view of the plugins of another plugin manager. This is a proxy object that only gives access the plugins of a certain plugin class. It behaves like a mapping and is used as the data object for a PluginSubManager.

```
__abstractmethods__ = frozenset([])
```

```
__delitem__(key)
```

```
__getitem__(item)
```

```
__init__(parent, plugin_class)
```

Constructor for the plugins view

Parameters

- **parent** ([BasePluginManager](#)) – the parent plugin manager

- **plugin_class** (*class*) – the class of the plugins to expose

```
__iter__()
```

```
__len__()
```

```
__module__ = 'fastr.core.pluginmanager'
```

```
__setitem__(key, value)
```

```
filter_plugin(plugin)
```

```
class fastr.core.pluginmanager.plugin_option_type(filename, name, namespace, id)
```

Bases: tuple

```
__dict__ = dict_proxy({'__module__': 'fastr.core.pluginmanager', '_make': <classmethod object>, '_replace': <function
```

```
__getnewargs__()
```

Return self as a plain tuple. Used by copy and pickle.

```
__getstate__()
```

Exclude the OrderedDict from pickling

```
__module__ = 'fastr.core.pluginmanager'
```

```
static __new__(_cls, filename, name, namespace, id)
```

Create new instance of plugin_option_type(filename, name, namespace, id)

```

__repr__()
    Return a nicely formatted representation string

__slots__ = ()

filename
    Alias for field number 0

id
    Alias for field number 3

name
    Alias for field number 1

namespace
    Alias for field number 2

```

provenance Module

class `fastr.core.provenance.Provenance(host=None)`

Bases: `object`

The Provenance object keeps track of everything that happens to a data object.

```

__dict__ = dict_proxy({'__module__': 'fastr.core.provenance', 'init_provenance': <function init_provenance>, 'collect_'
__init__(host=None)
__module__ = 'fastr.core.provenance'
__weakref__
    list of weak references to the object (if defined)

activity(identifier, start_time=None, end_time=None, other_attributes=None)
agent(identifier, other_attributes=None)
collect_input_argument_provenance(input_argument)
collect_provenance(job, advanced_flow=False)
    Collect the provenance for this job

static data_uri(value, job)
entity(identifier, other_attributes=None)
static get_parent_provenance(value)
    Find the provenance of the parent job

    Parameters value (str) – url for the value for which to find the job
    Returns the provenance of the job that created the value
    Raises
        • FastrKeyError – if the deferred is not available (yet)
        • FastrValueError – if the value is not a valid deferred url

init_provenance(job)
    Create initial provenance document

serialize(filename, format)

```

samples Module

This package holds the classes for working with samples.

class `fastr.core.samples.ContainsSamples`

Bases: `fastr.core.samples.HasSamples`

`__abstractmethods__ = frozenset(['samples'])`

`__getitem__(item)`

`__module__ = 'fastr.core.samples'`

`__setitem__(key, value)`

`dimensions`

`samples`

class `fastr.core.samples.HasSamples`

Bases: `fastr.core.dimension.HasDimensions`

Base class for all classes that supply samples. This base class allows to only define `__getitem__` and size and get all other basic functions mixed in so that the object behaves similar to a Mapping.

`__abstractmethods__ = frozenset(['dimensions', '__getitem__'])`

`__contains__(item)`

`__getitem__(item)`

`__iter__()`

`__metaclass__`

alias of ABCMeta

`__module__ = 'fastr.core.samples'`

`ids()`

`indexes()`

`items()`

`iteritems()`

class `fastr.core.samples.SampleBaseId`

Bases: tuple

This class represents a sample id. A sample id is a multi-dimensional id that has a simple, consistent string representation.

`__add__(other)`

Add another SampleId, this allows to add parts to the SampleId in a convenient way.

`__dict__ = dict_proxy({ '__module__': 'fastr.core.samples', '__new__': <staticmethod object>, '__str__': <function __str__ at 0x7f3e00000000> })`

`__module__ = 'fastr.core.samples'`

`static __new__(*args)`

Create a new SampleId

Parameters `args` (iterator/iterable of element type or element type)

– the strings to make sample id for

`__radd__(other)`

Add another SampleId, this allows to add parts to the SampleId in a convenient way. This is the right-hand version of the operator.

`__repr__()`

Get a string representation for the SampleBaseId

Returns the string representation

Return type `str`

`__str__()`

Get a string version for the SampleId, joins the SampleId with `_` to create a single string version.

Returns the string version

Return type `str`

class `fastr.core.samples.SampleCollection(dimnames, parent)`

Bases: `_abcoll.MutableMapping, fastr.core.dimension.HasDimensions`

The SampleCollections is a class that contains the data including a form of ordering. Each sample is reachable both by its SampleId and a SampleIndex. The object is sparse, so not all SampleId have to be defined allowing for non-rectangular data shapes.

Note: This object is meant to replace both the SampleIdList and the ValueStorage.

`__abstractmethods__ = frozenset([])`**`__contains__(item)`**

Check if an item is in the SampleCollection. The item can be a SampleId or SampleIndex. If the item is a slicing SampleIndex, then check if it would return any data (True) or no data (False)

Parameters `item` (`SampleId`, `SampleIndex`) – the item to check for

Returns flag indicating item is in the collections

Return type `bool`

`__delitem__(key)`

Remove an item from the SampleCollection

Parameters `key` (`SampleId`, `SampleIndex`, tuple of both, or `SampleItem`) – the key of the item to remove

`__getitem__(item)`

Retrieve (a) SampleItem(s) from the SampleCollection using the SampleId or SampleIndex. If the item is a tuple, it should be valid tuple for constructing either a SampleId or SampleIndex.

Parameters `item` (`SampleId`, `SampleIndex`, or `tuple`) – the identifier of the item to retrieve

Returns the requested item

Return type `SampleItem`

Raises

- `FastrTypeError` – if the item parameter is of incorrect type
- `KeyError` – if the item is not found

`__init__(dimnames, parent)`

Create a new SampleCollection

__iter__()

Iterate over the indices

__len__()

Get the number of samples in the SampleCollections.

__module__ = 'fastr.core.samples'**__repr__()****__setitem__(key, value)**

Set an item to the SampleCollection. The key can be a SampleId, SampleIndex or a tuple containing a SampleId and SampleIndex. The value can be a SampleItem (with the SampleId and SampleIndex matching), a tuple with values (assuming no depending jobs), or a with a list of values and a set of depending jobs.

Parameters

- **key** (`SampleId`, `SampleIndex`, `tuple of both`, or `SampleItem`) – the key of the item to store
- **value** (`SampleItem`, `tuple of values`, or `tuple of tuple of values and set of depending jobs`) – the value of the SampleItem to store

Raises

- **FastrTypeError** – if the key or value types are incorrect
- **FastrValueError** – if the id or values are incorrectly formed

dimensions**fullId**

The full defining ID for the SampleIdList

ndims

The number of dimensions in this SampleCollection

parent

The parent object holding the SampleCollection

class fastr.core.samples.SampleId

Bases: `fastr.core.samples.SampleBaseId`

SampleId is an identifier for data using human readable strings

__module__ = 'fastr.core.samples'**class fastr.core.samples.SampleIndex**

Bases: `fastr.core.samples.SampleBaseId`

SampleId is an identifier for data using the location in the N-d data structure.

__module__ = 'fastr.core.samples'**__repr__()**

Get a string representation for the SampleIndex

Returns the string representation

Return type `str`

__str__()

Get a string version for the SampleId, joins the SampleId with `__` to create a single string version.

Returns the string version

Return type `str`

expand(`size`)

Function expanding a slice SampleIndex into a list of non-slice SampleIndex objects

Parameters `size` – the size of the collection to slice

isslice

Flag indicating that the SampleIndex is a slice (as opposed to a simple single index).

class `fastr.core.samples.SampleItem`

Bases: `fastr.core.samples.SampleItemBase`

__module__ = ‘fastr.core.samples’

static __new__(`index, id_, data, jobs=None, failed_annotations=None`)

Create a SampleItem. Data should be an OrderedDict of tuples.

Parameters

- **index**(`tuple, slice`) – the sample index
- **id**(`SampleId`) – the sample id
- **data**(`SampleValue, Mapping`) – the data values
- **jobs**(`set`) – set of jobs on which this SampleItems data depends.
- **failed_annotations**(`set`) – set of tuples. The tuple is contructed like follows: (job_id, reason).

class `fastr.core.samples.SampleItemBase`

Bases: `tuple`

This class represents a sample item, a combination of a SampleIndex, SampleID, value and required jobs. The SampleItem based on a named tuple and has some extra methods to combine SampleItems easily.

__add__(`other`)

The addition operator combines two SampleItems into a single SampleItems. It merges the data and jobs and takes the index and id of the left-hand item.

Parameters `other`(`SampleItem`) – The other item to add to this one

Returns the combined SampleItem

Return type `SampleItem`

__dict__ = dict_proxy({‘index’: <property object>, ‘__module__’: ‘fastr.core.samples’, ‘dimensionality’: <property object>})

__getnewargs__()

Get new args gives the arguments to use to re-create this object, This is used for serialization.

__module__ = ‘fastr.core.samples’

static __new__(`index, id_, data, jobs=None, failed_annotations=None`)

Create a SampleItem. Data should be an OrderedDict of tuples.

Parameters

- **index**(`tuple, slice`) – the sample index
- **id**(`SampleId`) – the sample id
- **data**(`SampleValue, Mapping`) – the data values
- **jobs**(`set`) – set, tuple or list of jobs on which this SampleItems data depends.

- **failed_annotations** (`set`) – set of tuples. The tuple is contructed like follows: (job_id, reason).

__repr__()

Get a string representation for the SampleItem

Returns the string representation

Return type `str`

cardinality

The cardinality of this Sample

static combine (*args)

Combine a number of SampleItems into a new one.

Parameters `*args` – the SampleItems to combine

Returns the combined SampleItem

Return type `SampleItem`

It is possible to both give multiple arguments, where each argument is a SampleItem, or a single argument which is an iterable yielding SampleItems.

```
# variables a, b, c, d are SampleItems to combine
# These are all valid ways of combining the SampleItems
comb1 = SampleItem.combine(a, b, c, d)    # Using multiple arguments
l = [a, b, c, d]
comb2 = SampleItem.combine(l)    # Using a list of arguments
comb3 = SampleItem.combine(l.__iter__())    # Using an iterator
```

data

The data SampleValue of the SampleItem

Returns The value of this SampleItem

Return type `SampleValue`

dimensionality

The dimensionality of this Sample

failed_annotations**id**

The sample id of the SampleItem

Returns The id of this SampleItem

Return type `SampleId`

index

The index of the SampleItem

Returns The index of this SampleItem

Return type `SampleIndex`

jobs

The set of the jobs on which this SampleItem depends

Returns The jobs that generated the data for this SampleItem

Return type `set`

```

class fastr.core.samples.SamplePayload
Bases: fastr.core.samples.SampleItemBase

__add__(other)
    The addition operator combines two SampleItems into a single SampleItems. It merges the data and jobs and takes the index and id of the left-hand item.

        Parameters other (SampleItem) – The other item to add to this one

        Returns the combined SamplePayload

        Return type SamplePayload

__module__ = ‘fastr.core.samples’

static __new__(index, id_, data, jobs=None, failed_annotations=None)
    Create a SampleItem. Data should be an OrderedDict of tuples.

        Parameters

            • index (tuple, slice) – the sample index

            • id (SampleId) – the sample id

            • data (SampleValue, Mapping) – the data values

            • jobs (set) – set of jobs on which this SampleItems data depends.

            • failed_annotations (set) – set of tuples. The tuple is contructed like follows: (job_id, reason).

class fastr.core.samples.SampleValue(*args, **kwargs)
Bases: _abcoll.MutableMapping

A collection containing the content of a sample

__abstractmethods__ = frozenset([])

__add__(other)
__delitem__(key)
__getitem__(item)
__getstate__()
__init__(*args, **kwargs)
__iter__()
__len__()
__module__ = ‘fastr.core.samples’

__radd__(other)
__repr__()
__setitem__(key, value)
__setstate__(state)
cast(datatype)
is_mapping
is_sequence
iteelements()

```

```
mapping_part()  
sequence_part()
```

serializable Module

This package contains the base class and meta class for all serializable objects in the Fastr system.

```
class fastr.core.serializable.PassThroughSerializer
```

Bases: `object`

```
__dict__ = dict_proxy({'__module__': 'fastr.core.serializable', 'dumps': <staticmethod object>, '__dict__': <attribute
```

```
__module__ = 'fastr.core.serializable'
```

```
__weakref__
```

list of weak references to the object (if defined)

```
static dumps (data)
```

```
static loads (data)
```

```
class fastr.core.serializable.Serializable
```

Bases: `object`

Superclass for all classes that can be serialized.

```
SERIALIZERS = {'/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg-info':
```

```
__dict__ = dict_proxy({'load': <classmethod object>, '__module__': 'fastr.core.serializable', 'SERIALIZERS': {'/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/2.0.0/lib/python2.7/site-packages/fastr-2.0.0-py2.7.egg-info':
```

```
__getstate__ ()
```

```
__module__ = 'fastr.core.serializable'
```

```
__weakref__
```

list of weak references to the object (if defined)

```
classmethod createobj (state, _=None)
```

Create object function for generic objects

Parameters

- **cls** – The class to create
- **state** – The state to use to create the Link
- **network** – the parent Network

Returns

newly created Link

```
dump (file_handle, method='json', **kwargs)
```

Dump the object to a file like object.

Parameters

- **file_handle** – file descriptor to write the data to
- **method** (`str`) – method of final serialization to use (e.g. json, xml, pickle)
- **kwargs** – extra arguments passed to the final serializer

```
dumpf (path, method=None, **kwargs)
```

Dump the object to a file

Parameters

- **path** – path where to write the file
 - **method** (`str`) – method of final serialization to use (e.g. json, xml, pickle)
 - **kwargs** – extra arguments passed to the final serializer

Note: The dumpf function can determine the method based on the desired output filename. Also, if the filename ends with .gz it will continue search for another extension (so .json.gz could be found) and will then compress the result with gzip.

```
dumps(method='json', **kwargs)
    Dump the object to a string
```

Parameters

- **method** (*str*) – method of final serialization to use (e.g. json, xml, pickle)
 - **kwarg**s – extra arguments passed to the final serializer

Returns serialization string

Return type str

classmethod **get_serializer** (*filename=None*)

classmethod **load** (*file_handle*, *method=None*, *network=None*, ****kwargs**)

Load the object from a file-like object

Parameters

- **cls** – class of the object
 - **file_handle** – file descriptor to write the data to
 - **method** (*str*) – method of final serialization to use (e.g. json, xml, pickle)
 - **network** – network in which to place the loaded object
 - **kwarqs** – extra arguments passed to the final serializer

Returns newly created object

Warning: Unlike the loadf functions, this function does not automatically detect gzip compression. You read a gzip using the gzip.open method, but not but simply opening a stream and hopeing this function will function.

classmethod **loaddf** (*path*, *method=None*, *network=None*, ***kwargs*)

Load the object from a file

Parameters

- **cls** – class of the object
 - **path** – path where to write the file
 - **method** (*str*) – method of final serialization to use (e.g. json, xml, pickle)
 - **network** – network in which to place the loaded object
 - **kwargs** – extra arguments passed to the final serializer

Returns newly created object

Note: The loadf function can determine the method of loading based on the filename. Also it can automatically determine whether a file is gzipped.

classmethod loads (string, method=None, network=None, **kwargs)

Load the object from a string

Parameters

- **cls** – class of the object
- **string** (*str*) – the string containing the serialized data
- **method** (*str*) – method of final serialization to use (e.g. json, xml, pickle)
- **network** – network in which to place the loaded object
- **kwargs** – extra arguments passed to the final serializer

Returns newly created object

target Module

The module containing the classes describing the targets.

class fastr.core.target.ProcessUsageCollection

Bases: `_abcoll.Sequence`

`__abstractmethods__ = frozenset([])`

`__getitem__(item)`

`__init__()`

`__len__()`

`__module__ = 'fastr.core.target'`

`aggregate(number_of_points)`

`append(value)`

`usage_type`

alias of `SystemUsageInfo`

class fastr.core.target.SystemUsageInfo (timestamp, cpu_percent, vmem, rmem, read_bytes, write_bytes)

Bases: `tuple`

`__dict__ = dict_proxy({'__module__': 'fastr.core.target', '_make': <classmethod object>, 'timestamp': <property object>})`

`__getnewargs__()`

Return self as a plain tuple. Used by copy and pickle.

`__getstate__()`

Exclude the OrderedDict from pickling

`__module__ = 'fastr.core.target'`

`static __new__ (_cls, timestamp, cpu_percent, vmem, rmem, read_bytes, write_bytes)`

Create new instance of SystemUsageInfo(timestamp, cpu_percent, vmem, rmem, read_bytes, write_bytes)

`__repr__()`

Return a nicely formatted representation string

```

__slots__ = ()

cpu_percent
    Alias for field number 1

read_bytes
    Alias for field number 4

rmem
    Alias for field number 3

timestamp
    Alias for field number 0

vmem
    Alias for field number 2

write_bytes
    Alias for field number 5

class fastr.core.target.Target
    Bases: fastr.core.baseplugin.Plugin

```

The abstract base class for all targets. Execution with a target should follow the following pattern:

```

>>> with Target() as target:
...     target.run_command(['sleep', '10'])
...     target.run_command(['sleep', '10'])
...     target.run_command(['sleep', '10'])

```

The Target context operator will set the correct paths/initialization. Within the context command can be ran and when leaving the context the target reverts the state before.

```

__abstractmethods__ = frozenset(['run_command'])

__enter__()
    Set the environment in such a way that the target will be on the path.

__exit__(exc_type, exc_value, traceback)
    Cleanup the environment where needed

__metaclass__
    alias of ABCMeta

__module__ = 'fastr.core.target'

run_command(command)

classmethod test()
    Test the plugin, interfaces do not need to be tested on import

class fastr.core.target.TargetManager
    Bases: fastr.core.pluginmanager.PluginSubManager

Container holding all the ExecutionPlugins known to the Fastr system

__abstractmethods__ = frozenset([])

__init__()
    Initialize a ExecutionPluginManager and load plugins.

```

Parameters

- **path** – path to search for plugins

- **recursive** – flag for searching recursively

Returns newly created ExecutionPluginManager

__module__ = ‘fastr.core.target’

tool Module

A module to maintain a tool.

Exported classes:

- Tool – A class encapsulating a tool.
- ParameterDescription – The base class containing the shared description of a parameter (both input and output).
- InputParameterDescription – A class containing the description of an input parameter.
- Output ParameterDescription – A class containing the description of an output parameter.

class fastr.core.tool.**Tool** (*doc=None*)
Bases: *fastr.core.serializable.Serializable*

The class encapsulating a tool.

TOOL_REFERENCE_FILE_NAME = ‘__fastr_tool_ref__.json’

TOOL_RESULT_FILE_NAME = ‘__fastr_tool_result.pickle.gz’

__dataschemafile__ = ‘Tool.schema.json’

__eq__ (*other*)

Compare two Tool instances with each other.

Parameters *other* ([Tool](#)) – the other instances to compare to

Returns True if equal, False otherwise

__getstate__ ()

Retrieve the state of the Tool

Returns the state of the object

Rtype dict

__init__ (*doc=None*)

Create a new Tool :param doc: path of toolfile or a dict containing the tool data :type doc: str or dict

__module__ = ‘fastr.core.tool’

__repr__ ()

Get a string representation for the Tool. This will show the inputs and output defined in a table-like structure.

Returns the string representation

Return type str

__setstate__ (*state*)

Set the state of the Tool by the given state.

Parameters *state* ([dict](#)) – The state to populate the object with

__str__ ()

Get a string version for the Tool

Returns the string version
Return type str

authors = None
List of authors of the tool. These people wrapped the executable but are not responsible for executable itself.

cite = None
This holds the citation you should use when publishing something based on this Tool

command = None
Command is a dictionary contain information about the command which is called by this Tool: command['interpreter'] holds the (possible) interpreter to use command['targets'] holds a per os/arch dictionary of files that should be executed command['url'] is the webpage of the command to be called command['version'] is the version of the command used command['description'] can help a description of the command command['authors'] lists the original authors of the command

command_version

static compare_output_data (*current_output_data*, *reference_output_data*, *validation_result*, *output*)

create_reference (*input_data*, *output_directory*, *mount_name*='ref_tmp', *copy_input*=True)

description = None
Description of the tool and it's functionality

execute (*payload*=None, ***kwargs*)
Execute a Tool given the payload for a single run

Parameters **payload** – the data to execute the Tool with

Returns The result of the execution

Return type InterFaceResult

fullid
The full id of this tool

hash

help = None
Man page for the Tool. Here usage and examples can be described in detail

inputs

interface_class = None
Create the Interface based on the class specified in the tool file

name = None
Name of the tool, this should be a descriptive, human readable name.

namespace = None
The namespace this tools lives in, this will be set by the ToolManager on load

node_class = None
Class for of the Node to use

ns_id
The namespace and id of the Tool

outputs

path
The path of the directory in which the tool definition file was located.

references = None

A list of documents and in depth reading about the methods used in this tool

regex = None

Identifier for the tool

requirements = None

Requirements for this Tool

Warning: Not yet implemented

tags = None

List of tags for this tool

target

The OS and arch matched target definition.

test (reference=None)

Run the tests for this tool

test_spec

alias of TestSpecification

classmethod test_tool (reference_data_dir, tool=None, input_data=None)

Execute the tool with the input data specified and test the results against the reference data. This effectively tests the tool execution.

Parameters

- **reference_data_dir (str)** – The path or vfs url of reference data to compare with
- **source_data (dict)** – The source data to use

tests = None

Test for this tool. A test should be a collection of inputs, parameters and outputs to verify the proper functioning of the Tool.

The format of the tests is a list of namedtuples, that have 3 fields: - input: a dict of the input data - command: a list given the expected command-line arguments - output: a dict of the output data to validate

Warning: Not yet implemented

url = None

URL to website where this tool can be downloaded from

version = None

Version of the tool, not of the underlying software

toolmanager Module

This module contains the tool manager class

```
class fastr.core.toolmanager.ToolManager(path)
    Bases: fastr.core.objectmanager.ObjectManager

    __abstractmethods__ = frozenset(())
    __module__ = 'fastr.core.toolmanager'
```

```
get_object_version(obj)
object_class
populate()
toolversions(tool)
```

Return a list of available versions for the tool

Parameters `tool` – The tool to check the versions for. Can be either a *Tool* or a *str*.

Returns List of version objects. Returns *None* when the given tool is not known.

```
fastr.core.toolmanager.toollist = ToolManager fastr.Sink v1.0 : /home/docs/checkouts/readthedocs.org/user_builds
```

The fastr toollist

updateable Module

This module contains both the `Updateable` class and `UpdateableMeta` meta-class for objects which support updates within the fastr system

```
class fastr.core.updateable.Updateable
```

Bases: `object`

Super class for all classes that can be updated and have a status. These objects can be valid/invalid state. These states are set by the function `update`. This allows for interactively checking the network.

```
__abstractmethods__ = frozenset(['update'])
```

```
__dict__ = dict_proxy({'_abc_cache': <_weakrefset.WeakSet object>, '__module__': 'fastr.core.updateable', '__update'})
```

```
__getstate__()
```

Retrieve the state of the object, make sure the status is not part of the description as it will not be valid after re-creating the object.

Returns the state of the object

Rtype dict

```
__init__()
```

Constructor, creates the status field

Returns newly created object

```
__metaclass__
```

alias of `UpdateableMeta`

```
__module__ = 'fastr.core.updateable'
```

```
__setstate__(state)
```

Set the state of the object by the given state. This adds a clean status field, making sure it is not unintended, outdated information from before serialization.

Parameters `state` (`dict`) – The state to populate the object with

```
__updatefunc__(key=None, forward=True, backward=False)
```

Default function for updating, it can be called without key to have a new update started with a new key.

Parameters

- `key` (`int`) – a key for this update, should be different than the last update key
- `forward` (`bool`) – flag indicating to update forward in the network
- `backward` (`bool`) – flag indicating to update backward in the network

__updateinprogress__ = <thread.lock object>

Lock to avoid multiple updates happening at the same time

__updatetriggers__ = []

Which methods need to be wrapped to trigger an update. Override this value to have the functions automatically wrapped. E.g. `__update_triggers__` = ['append', 'insert', '__setitem__'] to have these functions wrapped.

__updating__ = True

Flag to indicate that this object is allowed to update

__weakref__

list of weak references to the object (if defined)

messages

The messages of the last update

update (*key=None, forward=True, backward=False*)

Default function for updating, it can be called without key to have a new update started with a new key.

Parameters

- **key** (*int*) – a key for this update, should be different than the last update key
- **forward** (*bool*) – flag indicating to update forward in the network
- **backward** (*bool*) – flag indicating to update backward in the network

valid

Flag indicating that the object is valid

class fastr.core.updateable.UpdateableMeta

Bases: `abc.ABCMeta`

A metaclass for objects which are updateable and need some methods/properties to trigger an update.

__module__ = 'fastr.core.updateable'**static __new__** (*mcs, name, parents, dct*)**classmethod calcmro** (*mcs, bases*)

Calculate the Method Resolution Order of bases using the C3 algorithm.

Suppose you intended creating a class K with the given base classes. This function returns the MRO which K would have, *excluding* K itself (since it doesn't yet exist), as if you had actually created the class.

Another way of looking at this, if you pass a single class K, this will return the linearization of K (the MRO of K, *including* itself).

Parameters **bases** – the list of bases for which create the MRO

Returns the list representing the entire MRO, except the (non-existing) class itself

Note: Taken from <http://code.activestate.com/recipes/577748-calculate-the-mro-of-a-class/> Created by Steven D'Aprano and licensed under the MIT license

classmethod find_member (*mcs, name, parents, dct*)

Find a member of the class in the same way as Python would if it had a given dict and set of bases

Parameters

- **mcs** – metaclass at work
- **name** – name of the class to be created

- **parents** – list of the bases for the new class
- **dct** – the dict of the class being created

Returns the firstly resolved member or None if nothing found

static **updatetrigger** (*fnc*)

Function decorator to make a function trigger an update after being called. This is a way to easily have function trigger an update after setting a value without writing tons of wrapper functions. The function keeps the original docstring and appends a note to it.

version Module

Module containing the class that represent versions

class fastr.core.version.Version
Bases: tuple

Class representing a software version definition. Allows for sorting and extraction of parts.

```
__dict__ = dict_proxy({'status': <property object>, '__module__': 'fastr.core.version', '__new__': <staticmethod object>})
```

```
__module__ = 'fastr.core.version'
```

```
static __new__ (*version)
```

Class containing a version

Can be constructed by:

```
Version( 'major.$minor.$extra[0].$extra[1]$seperator$status$build$suffix' )
Version( major, minor, extra, status, build, suffix, seperator )
Version( major, minor, extra, status, build, suffix, seperator )
Version( [major, minor, extra, status, build, suffix, seperator] )
```

Parameters

- **major** (*int*) – interger giving major version
- **minor** (*int*) – is an integer (required)
- **extra** (*list of int*) – is a list of integers
- **status** (*str*) – can be “a”, “alpha”, “b”, “beta”, “rc”, or “r”
- **build** (*int*) – is an integer
- **suffix** (*str*) – can contain any combination of alpha-numeric character and “._“
- **seperator** (*str*) – is any of “.”, “-”, or “_”, which is located between \$extra and \$build

Note: The method based on strings is the recommended method. For strings the major and minor version are required, where for tuple and list constructors all seven elements are optional.

Examples:

```
>>> a = Version('0.1')
>>> print(tuple(a))
(0, 1, None, None, None, '', None)
>>> b = Version('2.5.3-rc2')
>>> print(tuple(b))
```

```
(2, 5, [3], 'rc', 2, '', '-')
>>> c = Version('1.2.3.4.5.6.7-beta8_with_suffix')
>>> print(tuple(c))
(1, 2, [3, 4, 5, 6, 7], 'beta', 8, '_with_suffix', '-')
```

__repr__()

Return a in-editor representation of the version

__str__()

Return a string representation of the version

build

the build number, this is following the status (e.g. for 3.2-beta4, this would be 4)

date_version_matcher = <sre.SRE_Pattern object>**extra**

extra version extension as a list

extra_string

extra version extension as a string

major

major version

minor

minor version

status

the status of the version (a, alpha, b, beta, rc or r)

suffix

the remainder of the version which was not formatted in a known way

version_matcher = <sre.SRE_Pattern object at 0x250f040>

vfs Module

This module contains the virtual file system code. This is both an internally used object as well as an IOPlugin.

Subpackages

test Package

test Package

testdatatypemanager Module

testdimension Module

testnetwork Module

testnode Module

testsamples Module**testtool Module****testversion Module****testvfs Module****data Package****data Package**

Package containig data related modules

url Module

Module providing tools to parse and create valid urls and paths.

usage example:

When in fastr.config under the mounts section the data mount is set to /media/data, you will get the following. ..
code-block:: python

```
>>> import fastrdata.url import get_path_from_url
>>> get_path_from_url('vfs://data/temp/blaat1.png')
'/media/data/temp/blaat1.png'
```

`fastr.data.url.basename(url)`

Get basename of url

Parameters `url` (*str*) – the url

Returns the basename of the path in the url

`fastr.data.url.create_vfs_url(mountpoint, path)`

Construct an url from a given mount point and a relative path to the mount point.

Parameters

- `mountpoint` (*str*) – the name of the mountpoint

- `path` (*str*) – relative path from the mountpoint

Returns the created vfs url

`fastr.data.url.dirname(url)`

Get the dirname of the url

Parameters `url` (*str*) – the url

Returns the dirname of the path in the url

`fastr.data.url.dirurl(url)`

Get the a new url only having the dirname as the path

Parameters `url` (*str*) – the url

Returns the modified url with only dirname as path

`fastr.data.url.full_split(urlpath)`

Split the path in the url in a list of parts

Parameters `urlpath` – the url path

Returns a list of parts

`fastr.data.url.get_path_from_url(url)`

Get the path to a file from a url. Currently supports the file:// and vfs:// scheme's

Examples:

```
>>> url.get_path_from_url('vfs://neurodata/user/project/file.ext')
'Y:\neuro3\user\project\file.ext'
```

```
>>> 'file:///d:/data/project/file.ext'
'd:\data\project\file.ext'
```

Warning: file:// will not function cross platform and is mainly for testing

`fastr.data.url.get_url_scheme(url)`

Get the scheme of the url

Parameters `url` (`str`) – url to extract scheme from

Returns the url scheme

Return type `str`

`fastr.data.url.isurl(string)`

Check if string is a valid url

Parameters `string` (`str`) – potential url

Returns flag indicating if string is a valid url

`fastr.data.url.join(url, *p)`

Join the path in the url with p

Parameters

- `url` (`str`) – the base url to join with
- `p` – additional parts of the path

Returns the url with the parts added to the path

`fastr.data.url.normurl(url)`

Normalized the path of the url

Parameters `url` (`str`) – the url

Returns the normalized url

`fastr.data.url.register_url_scheme(scheme)`

Register a custom scheme to behave http like. This is needed to parse all things properly.

`fastr.data.url.split(url)`

Split a url in a url with the dirname and the basename part of the path of the url

Parameters `url` (`str`) – the url

Returns a tuple with (dirname_url, basename)

examples Package

examples Package

__generate_reference__ Module

```
fastr.examples.__generate_reference__.create_reference(example_path)
fastr.examples.__generate_reference__.generate_all_references()
```

add_ints Module

```
fastr.examples.add_ints.create_network()
fastr.examples.add_ints.main()
fastr.examples.add_ints.sink_data(network)
fastr.examples.add_ints.source_data(network)
```

add_ints_s3 Module

```
fastr.examples.add_ints_s3.create_network()
fastr.examples.add_ints_s3.main()
fastr.examples.add_ints_s3.sink_data(network)
fastr.examples.add_ints_s3.source_data(network)
```

auto_prefix Module

```
fastr.examples.auto_prefix.create_network()
fastr.examples.auto_prefix.main()
```

collapse Module

```
fastr.examples.collapse.create_network()
fastr.examples.collapse.main()
fastr.examples.collapse.sink_data(network)
fastr.examples.collapse.source_data(network)
```

collapse_expand Module

```
fastr.examples.collapse_expand.create_network()
fastr.examples.collapse_expand.main()
fastr.examples.collapse_expand.sink_data(network)
fastr.examples.collapse_expand.source_data(network)
```

cross_validation Module

```
fastr.examples.cross_validation.create_network()  
fastr.examples.cross_validation.main()  
fastr.examples.cross_validation.sink_data(network)  
fastr.examples.cross_validation.source_data(network)
```

elastix_nipype Module

```
fastr.examples.elastix_nipype.create_network()  
fastr.examples.elastix_nipype.main()  
fastr.examples.elastix_nipype.sink_data(network)  
fastr.examples.elastix_nipype.source_data(network)
```

expand Module

```
fastr.examples.expand.create_network()  
fastr.examples.expand.main()  
fastr.examples.expand.sink_data(network)  
fastr.examples.expand.source_data(network)
```

failing_network Module

```
fastr.examples.failing_network.create_network()  
fastr.examples.failing_network.main()  
fastr.examples.failing_network.sink_data(network)  
fastr.examples.failing_network.source_data(network)
```

filecopy Module

```
fastr.examples.filecopy.create_network()  
fastr.examples.filecopy.main()  
fastr.examples.filecopy.sink_data(network)  
fastr.examples.filecopy.source_data(network)
```

input_groups Module

```
fastr.examples.input_groups.create_network()  
fastr.examples.input_groups.main()  
fastr.examples.input_groups.sink_data(network)
```

```
fastr.examples.input_groups.source_data(network)
```

macro_node Module

```
fastr.examples.macro_node.create_macro_network()  
fastr.examples.macro_node.create_network()  
fastr.examples.macro_node.create_super_macro_node()  
fastr.examples.macro_node.main()  
fastr.examples.macro_node.sink_data(network)  
fastr.examples.macro_node.source_data(network)
```

macro_node2 Module

```
fastr.examples.macro_node2.create_macro_network()  
fastr.examples.macro_node2.create_network()  
fastr.examples.macro_node2.main()  
fastr.examples.macro_node2.sink_data(network)  
fastr.examples.macro_node2.source_data(network)
```

shift_links Module

```
fastr.examples.shift_links.create_network()  
fastr.examples.shift_links.main()  
fastr.examples.shift_links.sink_data(network)  
fastr.examples.shift_links.source_data(network)
```

source_sink Module

```
fastr.examples.source_sink.create_network()  
fastr.examples.source_sink.main()  
fastr.examples.source_sink.sink_data(network)  
fastr.examples.source_sink.source_data(network)
```

Subpackages

test Package

test_examples Module

execution Package

execution Package

This package contains all modules related directly to the execution

environmentmodules Module

This module contains a class to interact with EnvironmentModules

```
class fastr.execution.environmentmodules.EnvironmentModules (protected=None)  
    Bases: object
```

This class can control the module environments in python. It can list, load and unload environmentmodules. These modules are then used if subprocess is

called from python.

```
__dict__ = dict_proxy({'load': <function load>, '__module__': 'fastr.execution.environmentmodules', '__repr__': <fun
```

```
__init__ (protected=None)
```

Create the environmentmodules control object

Parameters **protected** (*list*) – list of modules that should never be unloaded

Returns newly created EnvironmentModules

```
__module__ = 'fastr.execution.environmentmodules'
```

```
__repr__ ()
```

```
__weakref__
```

list of weak references to the object (if defined)

```
avail (namestart=None)
```

Print available modules in same way as commandline version

Parameters **namestart** – filter on modules that start with namestart

```
avail_modules
```

List of avaible modules

```
clear ()
```

Unload all modules (except the protected modules as they cannot be unloaded). This should result in a clean environment.

```
exception = FastrImportError('Cannot find Environment Modules home directory (environment variables not setup p
```

```
isloaded (module)
```

Check if a specific module is loaded

Parameters **module** – module to check

Returns flag indicating the module is loaded

```
load (module)
```

Load specified module

Parameters **module** – module to load

```
loaded_modules
```

List of currently loaded modules

```
reload (module)
```

Reload specified module

Parameters `module` – module to reload

swap (`module1, module2`)
Swap one module for another one

Parameters

- `module1` – module to unload
- `module2` – module to load

sync ()
Sync the object with the underlying environment. Re-checks the available and loaded modules

static tostring_modvalue (`value`)
Turn a representation of a module into a string representation

Parameters `value` – module representation (either str or tuple)

Returns string representation

static totuple_modvalue (`value`)
Turn a representation of a module into a tuple representation

Parameters `value` – module representation (either str or tuple)

Returns tuple representation (name, version, default)

unload (`module`)
Unload specified module

Parameters `module` – module to unload

```
class fastr.execution.environmentmodules.ModuleSystem
    Bases: enum.Enum

    __format__(format_spec)
    __module__ = 'fastr.execution.environmentmodules'
    static __new__(value)
    __reduce_ex__(proto)
    __repr__()
    __str__()
    envmod = 'environmentmodules'
    lmod = 'Lmod'
```

executionpluginmanager Module

This module holds the ExecutionPluginManager as well as the base-class for all ExecutionPlugins.

```
class fastr.execution.executionpluginmanager.ExecutionPlugin(finished_callback=None,
    can-
    celled_callback=None,
    sta-
    tus_callback=None)
    Bases: fastr.core.baseplugin.Plugin
```

This class is the base for all Plugins to execute jobs somewhere. There are many methods already in place for taking care of stuff.

There are fall-backs for certain features, but if a system already implements those it is usually preferred to skip the fall-back and let the external system handle it. There are a few flags to enable disable these features:

- `cls.SUPPORTS_CANCEL` indicates that the plugin can cancel queued jobs
- `cls.SUPPORTS_HOLD_RELEASE` indicates that the plugin can queue jobs in a hold state and can release them again (if not, the base plugin will create a hidden queue for held jobs). The plugin should respect the `Job.status == JobState.hold` when queueing jobs.
- `cls.SUPPORTS_DEPENDENCY` indicate that the plugin can manage job dependencies, if not the base plugin job dependency system will be used and jobs with only be submitted when all dependencies are met.
- `cls.CANCELS_DEPENDENCIES` indicates that if a job is cancelled it will automatically cancel all jobs depending on that job. If not the plugin traverse the dependency graph and kill each job manual.

Note: If a plugin supports dependencies it is assumed that when a job gets cancelled, the depending job also get cancelled automatically!

Most plugins should only need to redefine a few abstract methods:

- `__init__` the constructor
- `cleanup` a clean up function that frees resources, closes connections, etc
- `_queue_job` the method that queues the job for execution

Optionally an extra job finished callback could be added:

- `_job_finished` extra callback for when a job finishes

If `SUPPORTS_CANCEL` is set to True, the plugin should also implement:

- `_cancel_job` cancels a previously queued job

If `SUPPORTS_HOLD_RELEASE` is set to True, the plugin should also implement:

- `_hold_job` hold_job a job that is currently held
- `_release_job` releases a job that is currently held

If `SUPPORTED_DEPENDENCY` is set to True, the plugin should:

- Make sure to use the `Job.hold_jobs` as a list of its dependencies

Not all of the functions need to actually do anything for a plugin. There are examples of plugins that do not really need a `cleanup`, but for safety you need to implement it. Just using a `pass` for the method could be fine in such a case.

Warning: When overwriting other functions, extreme care must be taken not to break the plugins working, as there is a lot of bookkeeping that can go wrong.

`CANCELS_DEPENDENCIES = False`

Indicates that when a job is cancelled the dependenceis

`SUPPORTS_CANCEL = False`

Indicates if the plugin can cancel queued jobs

`SUPPORTS_DEPENDENCY = False`

Indicate if the plugin can manage job dependencies, if not the base plugin job dependency system will be used and jobs with only be submitted when all dependencies are met.

SUPPORTS_HOLD_RELEASE = False

Indicates if the plugin can queue jobs in a hold state and can release them again (if not, the base plugin will create a hidden queue for held

jobs)

__abstractmethods__ = frozenset(['cleanup', '_queue_job', '__init__'])

__del__()

Cleanup if the variable was deleted on purpose

__enter__()

__exit__(type_, value, tb)

__init__(finished_callback=None, cancelled_callback=None, status_callback=None)

Setup the ExecutionPlugin

Parameters

- **finished_callback** – the callback to call after a job finished
- **cancelled_callback** – the callback to call after a job cancelled

Returns newly created ExecutionPlugin

__module__ = 'fastr.execution.executionpluginmanager'

cancel_job(job)

Cancel a job previously queued

Parameters **job** – job to cancel

check_job_requirements(job_id)

Check if the requirements for a job are fulfilled.

Parameters **job_id** – job to check

Returns directive what should happen with the job

Return type *JobAction*

check_job_status(job_id)

Get the status of a specified job

Parameters **job_id** – the target job

Returns the status of the job (or None if job not found)

cleanup()

Method to call to clean up the ExecutionPlugin. This can be to clear temporary data, close connections, etc.

Parameters **force** – force cleanup (e.g. kill instead of join a process)

get_job(job_id)

get_status(job)

hold_job(job)

job_finished(job, errors=None, blocking=False)

The default callback that is called when a Job finishes. This will create a new thread that handles the actual callback.

Parameters

- **job** (*Job*) – the job that finished

- **errors** – optional list of errors encountered
- **blocking** (`bool`) – if blocking, do not create threads

Returns

`process_callbacks()`

`queue_job(job)`

Add a job to the execution queue

Parameters `job` (`Job`) – job to add

`register_job(job)`

`release_job(job)`

Release a job that has been put on hold

Parameters `job` – job to release

`show_jobs(req_status=None)`

List the queued jobs, possible filtered by status

Parameters `req_status` – requested status to filter on

Returns list of jobs

class `fastr.execution.executionpluginmanager.ExecutionPluginManager`

Bases: `fastr.core.pluginmanager.PluginSubManager`

Container holding all the ExecutionPlugins known to the Fastr system

`__abstractmethods__ = frozenset([])`

`__init__()`

Initialize a ExecutionPluginManager and load plugins.

Parameters

- **path** – path to search for plugins
- **recursive** – flag for searching recursively

Returns newly created ExecutionPluginManager

`__module__ = 'fastr.execution.executionpluginmanager'`

class `fastr.execution.executionpluginmanager.JobAction`

Bases: `enum.Enum`

Job actions that can be performed. This is used for checking if held jobs should be queued, held longer or be cancelled.

`__format__(format_spec)`

`__module__ = 'fastr.execution.executionpluginmanager'`

`static __new__(value)`

`__reduce_ex__(proto)`

`__repr__()`

`__str__()`

`cancel = 'cancel'`

`hold = 'hold'`

```
queue = 'queue'
```

executionscript Module

The executionscript is the script that wraps around a tool executable. It takes a job, builds the command, executes the command (while profiling it) and collects the results.

```
fastr.execution.executionscript.execute_job(job)
```

Execute a Job and save the result to disk

Parameters `job` – the job to execute

```
fastr.execution.executionscript.main(joblist=None)
```

This is the main code. Wrapped inside a function to avoid the variables being seen as globals and to shut up pylint. Also if the joblist argument is given it can run any given job, otherwise it takes the first command line argument.

flownoderun Module

```
class fastr.execution.flownoderun.FlowNodeRun(node, parent)
```

Bases: `fastr.execution.noderun.NodeRun`

A Flow NodeRun is a special subclass of Nodes in which the amount of samples can vary per Output. This allows non-default data flows.

```
__abstractmethods__ = frozenset([])
```

```
__module__ = 'fastr.execution.flownoderun'
```

blocking

A FlowNodeRun is (for the moment) always considered blocking.

Returns True

dimnames

Names of the dimensions in the NodeRun output. These will be reflected in the SampleIdList of this NodeRun.

outputsizes

Size of the outputs in this NodeRun

```
set_result(job, failed_annotation)
```

Incorporate result of a job into the FlowNodeRun.

Parameters `job` (`Type`) – job of which the result to store

```
class fastr.execution.flownoderun.AdvancedFlowNodeRun(node, parent)
```

Bases: `fastr.execution.flownoderun.FlowNodeRun`

```
__abstractmethods__ = frozenset([])
```

```
__module__ = 'fastr.execution.flownoderun'
```

execute()

Execute the node and create the jobs that need to run

Returns list of jobs to run

Return type list of `Jobs`

```
set_result(job, failed_annotation)
```

inputoutputrun Module

Classes for arranging the input and output for nodes.

Exported classes:

Input – An input for a node (holding datatype). Output – The output of a node (holding datatype and value). ConstantOutput – The output of a node (holding datatype and value).

Warning: Don't mess with the Link, Input and Output internals from other places. There will be a huge chances of breaking the network functionality!

```
class fastr.execution.inputoutputrun.AdvancedFlowOutputRun (node_run, template)
    Bases: fastr.execution.inputoutputrun.OutputRun

    __abstractmethods__ = frozenset([])
    __module__ = 'fastr.execution.inputoutputrun'

class fastr.execution.inputoutputrun.BaseInputRun (node_run, template)
    Bases: fastr.core.samples.HasSamples, fastr.core.inputoutput.BaseInput

    Base class for all inputs runs.

    __abstractmethods__ = frozenset(['itersubinputs', '_update', '__getitem__', 'fullid', 'dimensions'])

    __init__(node_run, template)
        Instantiate a BaseInput
```

Parameters

- **node** – the parent node the input/output belongs to.
- **description** – the ParameterDescription describing the input/output.

Returns the created BaseInput

Raises

- **FastrTypeError** – if description is not of class ParameterDescription
- **FastrDataTypeNotFoundError** – if the DataType requested cannot be found in the `fastr.typeplist`

```
__module__ = 'fastr.execution.inputoutputrun'
```

```
itersubinputs()
    Iterator over the SubInputs
```

Returns iterator

example:

```
>>> for subinput in input_a.itersubinputs():
            print subinput
```

```
class fastr.execution.inputoutputrun.InputRun (node_run, template)
    Bases: fastr.execution.inputoutputrun.BaseInputRun
```

Class representing an input of a node. Such an input will be connected to the output of another node or the output of an constant node to provide the input value.

```
__abstractmethods__ = frozenset([])
```

`__getitem__(key)`

Retrieve an item from this Input.

Parameters `key` (str, SampleId or tuple) – the key of the requested item, can be a key str, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int the corresponding `SubInput` will be returned. If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned.

Return type SampleItem or `SubInput`

Raises

- `FastrTypeError` – if key is not of a valid type

- `FastrKeyError` – if the key is not found

`__getstate__()`

Retrieve the state of the Input

Returns the state of the object

Rtype dict

`__init__(node_run, template)`

Instantiate an input.

Parameters `template` – the Input that the InputRun is based on

`__module__ = 'fastr.execution.inputoutputrun'`**`__setstate__(state)`**

Set the state of the Input by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

`__str__()`

Get a string version for the Input

Returns the string version

Return type str

`cardinality(key=None, job_data=None)`

Cardinality for an Input is the sum the cardinalities of the SubInputs, unless defined otherwise.

Parameters `key` (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type int, sympy.Symbol, or None

`datatype`

The datatype of this Input

`dimensions`

The size of the sample collections that can accessed via this Input.

`fullid`

The full defining ID for the Input

`get_sourced_nodes()`

Get a list of all `Nodes` connected as sources to this Input

Returns list of all connected *Nodes*

Return type list

get_sourced_outputs()

Get a list of all *Outputs* connected as sources to this Input

Returns tuple of all connected *Outputs*

Return type tuple

index(value)

Find index of a SubInput

Parameters **value** (*SubInput*) – the *SubInput* to find the index of

Returns key

Return type int, str

input_group

The id of the InputGroup this Input belongs to.

insert(index)

Insert a new SubInput at index in the sources list

Parameters **key** (int) – positive integer for position in _source list to insert to

Returns newly inserted *SubInput*

Return type *SubInput*

itersubinputs()

Iterate over the *SubInputs* in this Input.

Returns iterator yielding *SubInput*

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

remove(value)

Remove a SubInput from the SubInputs list.

Parameters **value** (*SubInput*) – the *SubInput* to removed from this Input

source

The mapping of *SubInputs* that are connected and have more than 0 elements.

class *fastr.execution.inputoutputrun.MacroOutputRun* (*node_run, template*)

Bases: *fastr.execution.inputoutputrun.OutputRun*

__abstractmethods__ = frozenset([])

__module__ = 'fastr.execution.inputoutputrun'

dimensions

class *fastr.execution.inputoutputrun.OutputRun* (*node_run, template*)

Bases: *fastr.core.inputoutput.BaseOutput*, *fastr.core.samples.ContainsSamples*

Class representing an output of a node. It holds the output values of the tool ran. Output fields can be connected to inputs of other nodes.

__abstractmethods__ = frozenset([])

__getitem__(key)

Retrieve an item from this Output. The returned value depends on what type of key used:

- Retrieving data using index tuple: [index_tuple]
- Retrieving data sample_id str: [SampleId]
- Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]
- Retrieving a *SubOutput* using an int or slice: [n] or [n:m]

Parameters **key** (int, slice, SampleId or tuple) – the key of the requested item, can be a number, slice, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int or slice the corresponding *SubOutput* will be returned (and created if needed). If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned. If the key was a list of SampleId a tuple of SampleItem will be returned.

Return type *SubInput* or SampleItem or list of SampleItem

Raises

- *FastrTypeError* – if key is not of a valid type
- *FastrKeyError* – if the parent Node has not been executed

__getstate__()

Retrieve the state of the Output

Returns the state of the object

Rtype dict**__init__(node_run, template)**

Instantiate an Output

Parameters

- **node** – the parent node the output belongs to.
- **description** – the ParameterDescription describing the output.

Returns created Output

Raises

- *FastrTypeError* – if description is not of class ParameterDescription
- *FastrDataTypeNotAvailableError* – if the DataType requested cannot be found in the fastr.typeplist

__module__ = 'fastr.execution.inputoutputrun'**__setitem__(key, value)**

Store an item in the Output

Parameters

- **key** (tuple of int or SampleId) – key of the value to store
- **value** – the value to store

Returns None

Raises *FastrTypeError* – if key is not of correct type

__setstate__(state)

Set the state of the Output by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

__str__()

Get a string version for the Output

Returns the string version

Return type *str*

automatic

Flag indicating that the Output is generated automatically without being specified on the command line

blocking

Flag indicating that this Output will cause blocking in the execution

cardinality(key=None, job_data=None)

Cardinality of this Output, may depend on the inputs of the parent Node.

Parameters **key** (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type *int*, sympy.Symbol, or *None*

Raises

- *FastrCardinalityError* – if cardinality references an invalid *Input*
- *FastrTypeError* – if the referenced cardinality values type cannot be cast to int
- *FastrValueError* – if the referenced cardinality value cannot be cast to int

static create_output_cardinality(desc)

Create a lambda function that returns an integer value of the cardinality.

param **str** **desc** The cardinality description string

return output cardinality description

rtype tuple

The description string can be one of the following forms:

- N: N number of values needed.
- as:*input_name*: the same number of values as attached to *input_name* are needed.
- val:*input_name*: the number of values needed is the value of *input_name*.
- unknown: the output cardinality cannot be estimated a priori

datatype

The datatype of this Output

fullid

The full defining ID for the Output

iterconvergingindices(collapse_dims)

Iterate over all data, but collapse certain dimension to create lists of data.

Parameters **collapse_dims** (*iterable of int*) – dimension to collapse

Returns iterator SampleIndex (possibly containing slices)

listeners

The list of [Links](#) connected to this Output.

preferred_types

The list of preferred DataTypes for this Output.

resulting_datatype

The DataType that will the results of this Output will have.

samples

The SampleCollection of the samples in this Output. None if the NodeRun has not yet been executed. Otherwise a SampleCollection.

valid

Check if the output is valid, i.e. has a valid cardinality

class `fastr.execution.inputoutputrun.SourceOutputRun(node_run, template)`

Bases: [fastr.execution.inputoutputrun.OutputRun](#)

Output for a SourceNodeRun, this type of Output determines the cardinality in a different way than a normal NodeRun.

__abstractmethods__ = frozenset([])

__getitem__(item)

Retrieve an item from this Output. The returned value depends on what type of key used:

- Retrieving data using index tuple: [index_tuple]
- Retrieving data sample_id str: [SampleId]
- Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]
- Retrieving a [SubOutput](#) using an int or slice: [n] or [n:m]

Parameters **key** (int, slice, SampleId or tuple) – the key of the requested item, can be a number, slice, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int or slice the corresponding [SubOutput](#) will be returned (and created if needed). If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned. If the key was a list of SampleId a tuple of SampleItem will be returned.

Return type [SubInput](#) or SampleItem or list of SampleItem

Raises

- **FastrTypeError** – if key is not of a valid type
- **FastrKeyError** – if the parent NodeRun has not been executed

__init__(node_run, template)

Instantiate a FlowOutput

Parameters

- **node** – the parent node the output belongs to.
- **description** – the ParameterDescription describing the output.

Returns created FlowOutput

Raises

- **FastrTypeModelError** – if description is not of class ParameterDescription
- **FastrDataTypeNotAvailableError** – if the DataType requested cannot be found in the fastr.typeList

__module__ = 'fastr.execution.inputoutputrun'

__getitem__(key, value)

Store an item in the Output

Parameters

- **key** (tuple of int or SampleId) – key of the value to store
- **value** – the value to store

Returns

None

Raises **FastrTypeModelError** – if key is not of correct type

cardinality (key=None, job_data=None)

Cardinality of this SourceOutput, may depend on the inputs of the parent NodeRun.

Parameters **key** (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type `int`, `sympy.Symbol`, or `None`

dimensions

The dimensions of this SourceOutputRun

linearized

A linearized version of the sample data, this is lazily cached linearized version of the underlying SampleCollection.

ndims

The number of dimensions in this SourceOutput

size

The sample size of the SourceOutput

class `fastr.execution.inputoutputrun.SubInputRun` (`input_`)

Bases: `fastr.execution.inputoutputrun.BaseInputRun`

This class is used by `Input` to allow for multiple links to an `Input`. The SubInput class can hold only a single Link to a (Sub)Output, but behaves very similar to an `Input` otherwise.

__abstractmethods__ = frozenset([])

__getitem__(key)

Retrieve an item from this SubInput.

Parameters **key** (int, SampleId or SampleIndex) – the key of the requested item, can be a number, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int the corresponding `SubInput` will be returned. If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned.

Return type `SampleItem` or `SubInput`

Raises **FastrTypeModelError** – if key is not of a valid type

Note: As a SubInput has only one SubInput, only requesting int key 0 or -1 is allowed, and it will return self

`__getstate__()`

Retrieve the state of the SubInput

Returns the state of the object

Rtype dict

`__init__(input_)`

Instantiate an SubInput.

Parameters `input` (*Input*) – the parent of this SubInput.

Returns the created SubInput

`__module__ = 'fastr.execution.inputoutputrun'`**`__setstate__(state)`**

Set the state of the SubInput by the given state.

Parameters `state` (*dict*) – The state to populate the object with

Returns None

`__str__()`

Get a string version for the SubInput

Returns the string version

Return type str

`cardinality(key=None, job_data=None)`

Get the cardinality for this SubInput. The cardinality for a SubInputs is defined by the incoming link.

Parameters `key` (SampleIndex or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type int, sympy.Symbol, or None

`description`**`dimensions`**

The sample size of the SubInput

`fullid`

The full defining ID for the SubInput

`get_sourced_nodes()`

Get a list of all *Nodes* connected as sources to this SubInput

Returns list of all connected *Nodes*

Return type list

`get_sourced_outputs()`

Get a list of all *Outputs* connected as sources to this SubInput

Returns list of all connected *Outputs*

Return type list

input_group

The id of the InputGroup this SubInputs parent belongs to.

iteritems()

Iterate over the SampleItems that are in the SubInput.

Returns iterator yielding SampleItem objects

itersubinputs()

Iterate over SubInputs (for a SubInput it will yield self and stop iterating after that)

Returns iterator yielding *SubInput*

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

node

The Node to which this SubInputs parent belongs

source

A list with the source *Link*. The list is to be compatible with *Input*

source_output

The *Output* linked to this SubInput

class *fastr.execution.inputoutputrun.SubOutputRun* (*output, index*)

Bases: *fastr.execution.inputoutputrun.OutputRun*

The SubOutput is an Output that represents a slice of another Output.

__abstractmethods__ = frozenset([])

__getitem__(key)

Retrieve an item from this SubOutput. The returned value depends on what type of key used:

- Retrieving data using index tuple: [index_tuple]
- Retrieving data sample_id str: [SampleId]
- Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]
- Retrieving a *SubOutput* using an int or slice: [n] or [n:m]

Parameters key (int, slice, SampleId or tuple) – the key of the requested item, can be a number, slice, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int or slice the corresponding *SubOutput* will be returned (and created if needed). If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned. If the key was a list of SampleId a tuple of SampleItem will be returned.

Return type *SubInput* or SampleItem or list of SampleItem

Raises *FastrTypeError* – if key is not of a valid type

__getstate__()

Retrieve the state of the SubOutput

Returns the state of the object

Rtype dict

`__init__(output, index)`

Instantiate a SubOutput

Parameters

- **output** – the parent output the suboutput slices.
- **index** (`int` or `slice`) – the way to slice the parent output

Returns created SubOutput**Raises**

- **FastrTypeError** – if the output argument is not an instance of `Output`
- **FastrTypeError** – if the index argument is not an `int` or `slice`

`__len__()`

Return the length of the Output.

Note: In a SubOutput this is always 1.

`__module__ = 'fastr.execution.inputoutputrun'`**`__setitem__(key, value)`**

A function blocking the assignment operator. Values cannot be assigned to a SubOutput.

Raises `FastrNotImplementedError` – if called**`__setattr__(state)`**

Set the state of the SubOutput by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None**`__str__()`**

Get a string version for the SubOutput

Returns the string version**Return type** `str`**`cardinality(key=None, job_data=None)`**

Cardinality of this SubOutput depends on the parent Output and `self.index`

Parameters `key` (tuple of `int` or `SampleId`) – key for a specific sample, can be sample index or id

Returns the cardinality**Return type** `int`, `sympy.Symbol`, or `None`**Raises**

- **FastrCardinalityError** – if cardinality references an invalid `Input`
- **FastrTypeError** – if the referenced cardinality values type cannot be cast to int
- **FastrValueError** – if the referenced cardinality value cannot be cast to int

`datatype`

The datatype of this SubOutput

`fullid`

The full defining ID for the SubOutput

indexrep

Simple representation of the index.

listeners

The list of [Links](#) connected to this Output.

node

The NodeRun to which this SubOutput belongs

preferred_types

The list of preferred DataTypes for this SubOutput.

resulting_datatype

The DataType that will the results of this SubOutput will have.

samples

The SampleCollection for this SubOutput

job Module

This module contains the Job class and some related classes.

```
class fastr.execution.job.InlineJob(*args, **kwargs)
    Bases: fastr.execution.job.Job

    __init__(*args, **kwargs)
    __module__ = 'fastr.execution.job'
    get_result()

class fastr.execution.job.Job(node, sample_id, sample_index, input_arguments, output_arguments,
                                hold_jobs=None, status_callback=None, preferred_types=None)
    Bases: fastr.core.serializable.Serializable
```

Class describing a job.

Arguments: tool_name - the name of the tool (str) tool_version - the version of the tool (Version) argument - the arguments used when calling the tool (list) tmpdir - temporary directory to use to store output data hold_jobs - list of jobs that need to finished before this job can run (list)

COMMAND_DUMP = '__fastr_command__.pickle.gz'

INFO_DUMP = '__fastr_extra_job_info__.json'

PROV_DUMP = '__fastr_prov__.json'

RESULT_DUMP = '__fastr_result__.pickle.gz'

STDERR_DUMP = '__fastr_stderr__.txt'

STDOUT_DUMP = '__fastr_stdout__.txt'

__getstate__()

Get the state of the job

Returns job state

Return type dict

__init__(node, sample_id, sample_index, input_arguments, output_arguments, hold_jobs=None, status_callback=None, preferred_types=None)

Create a job

Parameters

- **node** (`Node`) – the node the job is based on
- **sample_id** (`fastr.core.samples.SampleID`) – the id of the sample
- **sample_index** (`fastr.core.samples.SampleIndex`) – the index of the sample
- **input_arguments** (`list[dict]`) – the argument list
- **output_arguments** (`list[dict]`) – the argument list
- **hold_jobs** (`list[str]`) – the jobs on which this jobs depend
- **status_callback** (`callable`) – The callback to call when the status changed
- **preferred_types** – The list of preferred types to use

Returns`__module__ = 'fastr.execution.job'``__repr__()`

String representation of the Job

`__setstate__(state)`

Set the state of the job

Parameters `state (dict)` –`static calc_cardinality(description, payload)``commandfile`

The path of the command pickle

`commandurl`

The url of the command pickle

`create_payload()`

Create the payload for this object based on all the input/output arguments

Returns the payload**Return type** `dict``ensure_tmp_dir()``execute()`

Execute this job

Returns The result of the execution**Return type** `InterFaceResult``extrainfofile`

The path where the extra job info document is saved

`extrainfourl`

The url where the extra job info document is saved

`classmethod fill_output_argument(output_spec, cardinality, desired_type, requested, tmpurl)`

This is an abstract class method. The method should take the argument_dict generated from calling self.get_argument_dict() and turn it into a list of commandline arguments that represent this Input/Output.

Parameters

- **cardinality** (`int`) – the cardinality for this output (can be non for automatic outputs)
- **desired_type** (`DataType`) – the desired datatype for this output

- **requested** (`bool`) – flag to indicate that the output is requested by Fastr

Returns the values for this output

Return type list

fullid

The full id of the job

get_deferred (`output_id, cardinality_nr, sample_id=None`)

Get a deferred pointing to a specific output value in the Job

Parameters

- **output_id** (`str`) – the output to select from
- **cardinality_nr** (`int`) – the index of the cardinality
- **sample_id** (`str`) – the sample id to select (optional)

Returns The deferred

get_output_datatype (`output_id`)

Get the datatype for a specific output

Parameters `output_id` (`str`) – the id of the output to get the datatype for

Returns the requested datatype

Return type `BaseDataType`

get_result ()

Get the result of the job if it is available. Load the output file if found and check if the job matches the current object. If so, load and return the result.

Returns Job after execution or None if not available

Return type Job | None

classmethod get_value (`value`)

Get a value

Parameters

- **value** – the url of the value
- **datatype** – datatype of the value

Returns the retrieved value

hash_inputs ()

Create hashes for all input values and store them in the info store

hash_results ()

Create hashes of all output values and store them in the info store

id

The id of this job

logfile

The path of the result pickle

logurl

The url of the result pickle

provfile

The path where the prov document is saved

provurl

The url where the prov document is saved

required_cores

Number of required cores

required_memory

Number of required memory

required_time

Number of required runtime

status

The status of the job

stderrfile

The path where the stderr text is saved

stderrurl

The url where the stderr text is saved

stdoutfile

The path where the stdout text is saved

stdouturl

The url where the stdout text is saved

tmpurl

The URL of the tmpdir to use

tool**classmethod translate_argument (value)**

Translate an argument from a URL to an actual path.

Parameters

- **value** – value to translate
- **datatype** – the datatype of the value

Returns the translated value

static translate_output_results (value, datatype, preferred_type, mountpoint=None)

Translate the results for on Output

Parameters

- **value** – the results value for the output
- **datatype** – the datatype of the output
- **preferred_type** – the preferred datatype of the output

Returns the update value for the result

translate_results (result)

Translate the results of an interface (using paths etc) to the proper form using URI's instead.

Parameters **result** (*dict*) – the result data of an interface

Returns the translated result

Return type *dict*

validate_results (payload)

Validate the results of the Job


Returns flag indicating the results are complete and valid

write()

class fastr.execution.job.**JobState** (*_*, *stage*, *error*)

Bases: enum.Enum

The possible states a Job can be in. An overview of the states and the advised transitions are depicted in the following figure:



`__format__(format_spec)`

```
__init__(_, stage, error)
__module__ = 'fastr.execution.job'

static __new__(value)

__reduce_ex__(proto)

__repr__()

__str__()

cancelled = ('cancelled', 'done', True)
created = ('created', 'idle', False)
done
execution_done = ('execution_done', 'in_progress', False)
execution_failed = ('execution_failed', 'in_progress', True)
failed = ('failed', 'done', True)
finished = ('finished', 'done', False)
hold = ('hold', 'idle', False)
idle
in_progress
nonexistent = ('nonexistent', 'idle', False)
processing_callback = ('processing_callback', 'in_progress', False)
queued = ('queued', 'idle', False)
running = ('running', 'in_progress', False)

class fastr.execution.job.SinkJob(node, sample_id, sample_index, input_arguments, output_arguments, hold_jobs=None, substitutions=None, status_callback=None, preferred_types=None)
Bases: fastr.execution.job.Job

Special SinkJob for the Sink

__init__(node, sample_id, sample_index, input_arguments, output_arguments, hold_jobs=None, substitutions=None, status_callback=None, preferred_types=None)
__module__ = 'fastr.execution.job'

__repr__()
String representation for the SinkJob

create_payload()
Create the payload for this object based on all the input/output arguments
    Returns the payload
    Return type dict

get_result()
Get the result of the job if it is available. Load the output file if found and check if the job matches the current object. If so, load and return the result.
    Returns Job after execution
```

hash_inputs()
Create hashes for all input values and store them in the info store

id
The id of this job

substitute (*value*, *datatype=None*)
Substitute the special fields that can be used in a SinkJob.

Parameters

- **value** (*str*) – the value to substitute fields in
- **datatype** (*BaseDataType*) – the datatype for the value

Returns string with substitutions performed

Return type *str*

tmpurl
The URL of the tmpdir to use

validate_results (*payload*)
Validate the results of the SinkJob

Returns flag indicating the results are complete and valid

class *fastr.execution.job.SourceJob* (*node*, *sample_id*, *sample_index*, *input_arguments*, *output_arguments*, *hold_jobs=None*, *status_callback=None*, *preferred_types=None*)

Bases: *fastr.execution.job.Job*

Special SourceJob for the Source

__module__ = 'fastr.execution.job'

__repr__()
String representation for the SourceJob

get_output_datatype (*output_id*)
Get the datatype for a specific output

Parameters **output_id** (*str*) – the id of the output to get the datatype for

Returns the requested datatype

Return type *BaseDataType*

hash_inputs()
Create hashes for all input values and store them in the info store

validate_results (*payload*)
Validate the results of the Job

Returns flag indicating the results are complete and valid

linkrun Module

The link module contain the Link class. This class represents the links in a network. These links lead from an output (BaseOutput) to an input (BaseInput) and indicate the desired data flow. Links are smart objects, in the sense that when you set their start or end point, they register themselves with the Input and Output. They do all the book keeping, so as long as you only set the source and target of the Link, the link should be valid.

Warning: Don't mess with the Link, Input and Output internals from other places. There will be a huge chances of breaking the network functionality!

class `fastr.execution.linkrun.LinkRun(link, parent=None)`

Bases: `fastr.core.updateable.Updateable, fastr.core.serializable.Serializable`

Class for linking outputs (`BaseOutput`) to inputs (`BaseInput`)

Examples:

```
>>> import fastr
>>> network = fastr.Network()
>>> link1 = network.create_link( n1.ouputs['out1'], n2.inputs['in2'] )

link2 = Link()
link2.source = n1.ouputs['out1']
link2.target = n2.inputs['in2']
```

`__abstractmethods__ = frozenset()`

`__dataschemafile__ = 'Link.schema.json'`

`__eq__(other)`

Test for equality between two Links

Parameters `other` (`LinkRun`) – object to test against

Returns True for equality, False otherwise

Return type `bool`

`__getitem__(index)`

Get a an item for this Link. The item will be retrieved from the connected output, but a diverging or converging flow can change the number of samples/cardinality.

Parameters `index` (`SampleIndex`) – index of the item to retrieve

Returns the requested item

Return type `SampleItem`

Raises `FastrIndexError` – if the index length does not match the number dimensions in the source data (after collapsing/expanding)

`__getstate__()`

Retrieve the state of the Link

Returns the state of the object

Rtype `dict`

`__init__(link, parent=None)`

Create a new Link in a Network.

Parameters

- `link` (`Link`) – the base link
- `parent` (`Network` or `None`) – the parent network, if `None` is given the `fastr.current_network` is assumed to be the parent

Returns newly created LinkRun

Raises

- **FastrValueError** – if parent is not given and *fastr.current_network* is not set
- **FastrValueError** – if the source output is not in the same network as the Link
- **FastrValueError** – if the target input is not in the same network as the Link

__module__ = ‘fastr.execution.linkrun’

__repr__()
Get a string representation for the Link
Returns the string representation
Return type str

__setstate__(state)
Set the state of the Link by the given state.
Parameters **state** (*dict*) – The state to populate the object with
Returns None
Raises **FastrValueError** – if the parent network and *fastr.current_network* are not set

cardinality(index=None)
Cardinality for a Link is given by source Output and the collapse/expand settings
Parameters **key** (*SampleIndex*) – key for a specific sample (can be only a sample index!)
Returns the cardinality
Return type int, sympy.Symbol
Raises **FastrIndexError** – if the index length does not match the number of dimension in the data

collapse
The converging dimensions of this link. Collapsing changes some dimensions of sample lists into cardinality, reshaping the data.
Collapse can be set to a tuple or an int/str, in which case it will be automatically wrapped in a tuple. The int will be seen as indices of the dimensions to collapse. The str will be seen as the name of the dimensions over which to collapse.
Raises **FastrTypeError** – if assigning a collapse value of a wrong type

collapse_indexes
The converging dimensions of this link as integers. Dimension names are replaced with the corresponding int.
Collapsing changes some dimensions of sample lists into cardinality, reshaping the data

classmethod createobj(state, network=None)
Create object function for Link
Parameters

- **cls** – The class to create
- **state** – The state to use to create the Link
- **network** – the parent Network

Returns newly created Link

destroy()

The destroy function of a link removes all default references to a link. This means the references in the network, input and output connected to this link. If there is no references in other places in the code, it will destroy the link (reference count dropping to zero).

This function is called when a source for an input is set to another value and the links becomes disconnected. This makes sure there is no dangling links.

dimensions

The dimensions of the data delivered by the link. This can be different from the source dimensions because the link can make data collapse or expand.

expand

Flag indicating that the link will expand the cardinality into a new sample dimension to be created.

fullid

The full defining ID for the Input

parent

The Network to which this Link belongs.

size

The size of the data delivered by the link. This can be different from the source size because the link can make data collapse or expand.

source

The source *BaseOutput* of the Link. Setting the source will automatically register the Link with the source BaseOutput. Updating source will also make sure the Link is unregistered with the previous source.

Raises *FastrTypeError* – if assigning a non *BaseOutput*

status**target**

The target *BaseInput* of the Link. Setting the target will automatically register the Link with the target BaseInput. Updating target will also make sure the Link is unregistered with the previous target.

Raises *FastrTypeError* – if assigning a non *BaseInput*

macronoderun Module

class *fastr.execution.macronoderun.MacroNodeRun* (*node, parent*)

Bases: *fastr.execution.noderun.NodeRun*

MacroNodeRun encapsulates an entire network in a single node.

__abstractmethods__ = frozenset([])

__getstate__ ()

Retrieve the state of the MacroNodeRun

Returns the state of the object

Rtype dict

__init__ (*node, parent*)

Parameters **network** (*Network*) – network to create macronode for

__module__ = ‘*fastr.execution.macronoderun*’

__setstate__ (*state*)

```
execute()
get_output_info(output)
network_run
```

networkanalyzer Module

Module that defines the NetworkAnalyzer and holds the reference implementation.

```
class fastr.execution.networkanalyzer.DefaultNetworkAnalyzer
    Bases: fastr.execution.networkanalyzer.NetworkAnalyzer
```

Default implementation of the NetworkAnalyzer.

```
__module__ = 'fastr.execution.networkanalyzer'
```

```
analyze_network(network, chunk)
```

Analyze a chunk of a Network. Simply process the Nodes in the chunk sequentially.

Parameters

- **network** – Network corresponding with the chunk
- **chunk** – The chunk of the network to analyze

```
class fastr.execution.networkanalyzer.NetworkAnalyzer
```

Bases: *object*

Base class for NetworkAnalyzers

```
__dict__ = dict_proxy({‘__dict__’: <attribute ‘__dict__’ of ‘NetworkAnalyzer’ objects>, ‘__weakref__’: <attribute ‘__weakref__’ of ‘NetworkAnalyzer’ objects>})
```

```
__module__ = 'fastr.execution.networkanalyzer'
```

```
__weakref__
```

list of weak references to the object (if defined)

```
analyze_network(network, chunk)
```

Analyze a chunk of a Network.

Parameters

- **network** – Network corresponding with the chunk
- **chunk** – The chunk of the network to analyze

networkchunker Module

This module contains the NetworkChunker class and its default implementation the DefaultNetworkChunker

```
class fastr.execution.networkchunker.DefaultNetworkChunker
```

Bases: *fastr.execution.networkchunker.NetworkChunker*

The default implementation of the NetworkChunker. It tries to create as large as possible chunks so the execution blocks as little as possible.

```
__init__()
```

```
__module__ = 'fastr.execution.networkchunker'
```

`chunck_network (network)`

Create a list of Network chunks that can be pre-analyzed completely. Each chunk needs to be executed before the next can be analyzed and executed.

The returned chunks are (at the moment) in the format of a tuple (start, nodes) which are both tuples. The tuple contain the nodes where to start execution (should ready if previous chunks are done) and all nodes of the chunk respectively.

Parameters `network` – Network to split into chunks

Returns tuple containing chunks

`class fastr.execution.networkchunker.NetworkChunker`

Bases: `object`

The base class for NetworkChunkers. A Network chunker is a class that takes a Network and produces a list of chunks that can each be analyzed and executed in one go.

`__dict__ = dict_proxy({‘__dict__’: <attribute ‘__dict__’ of ‘NetworkChunker’ objects>, ‘__module__’: ‘fastr.execution.networkchunker’}`

`__weakref__`

list of weak references to the object (if defined)

`chunck_network (network)`

Create a list of Network chunks that can be pre-analyzed completely. Each chunk needs to be executed before the next can be analyzed and executed.

Parameters `network` – Network to split into chunks

Returns list containing chunks

networkrun Module

Network module containing Network facilitators and analysers.

`class fastr.execution.networkrun.NetworkRun (network)`

Bases: `fastr.core.serializable.Serializable`

The Network class represents a workflow. This includes all Nodes (including ConstantNodes, SourceNodes and Sinks) and Links.

`NETWORK_DUMP_FILE_NAME = ‘__fastr_network__.json’`

`SINK_DUMP_FILE_NAME = ‘__sink_data__.json’`

`SOURCE_DUMP_FILE_NAME = ‘__source_data__.pickle.gz’`

`__eq__ (other)`

Compare two Networks and see if they are equal.

Parameters `other` (`Network`) –

Returns flag indicating that the Networks are the same

Return type `bool`

`__getitem__ (item)`

Get an item by its fullid. The fullid can point to a link, node, input, output or even subinput/suboutput.

Parameters `item` (`str, unicode`) – fullid of the item to retrieve

Returns the requested item

`__getstate__()`
Retrieve the state of the Network

Returns the state of the object

Rtype dict

`__init__(network)`
Create a new, empty Network

Parameters `name (str)` – name of the Network

Returns newly created Network

Raises `OSError` – if the tmp mount in the fastr.config is not a writable directory

`__module__ = 'fastr.execution.networkrun'`

`__ne__(other)`
Tests for non-equality, this is the negated version `__eq__`

`__repr__()`

`__setstate__(state)`
Set the state of the Network by the given state. This completely overwrites the old state!

Parameters `state (dict)` – The state to populate the object with

Returns None

`abort()`

`check_id(id_)`
Check if an id for an object is valid and unused in the Network. The method will always returns True if it does not raise an exception.

Parameters `id (str)` – the id to check

Returns True

Raises

- `FastrValueError` – if the id is not correctly formatted
- `FastrValueError` – if the id is already in use

`constantlist`

`execute(sourcedata, sinkdata, execution_plugin=None, tmpdir=None, cluster_queue=None)`
Execute the Network with the given data. This will analyze the Network, create jobs and send them to the execution backend of the system.

Parameters

- `sourcedata (dict)` – dictionary containing all data for the sources
- `sinkdata (dict)` – dictionary containing directives for the sinks
- `execution_plugin (str)` – the execution plugin to use (None will use the config value)

Raises

- `FastrKeyError` – if a source has not corresponding key in sourcedata
- `FastrKeyError` – if a sink has not corresponding key in sinkdata

fullid
The fullid of the Network

generate_jobs()

global_id
The global id of the Network, this is different for networks used in macronodes, as they still have parents.

id
The id of the Network. This is a read only property.

job_finished(job, execution_interface)
Call-back handler for when a job is finished. Will collect the results and handle blocking jobs. This function is automatically called when the execution plugin finished a job.

Parameters `job` (*Job*) – the job that finished

job_finished_callback

job_status_callback

long_id

network

nodegroups
Give an overview of the nodegroups in the network

set_data(sourcedata, sinkdata)

sinklist

sourcelist

noderun Module

A module to maintain a run of a network node.

class fastr.execution.noderun.NodeRun(node, parent)
Bases: *fastr.core.updateable.Updateable, fastr.core.serializable.Serializable*

The class encapsulating a node in the network. The node is responsible for setting and checking inputs and outputs based on the description provided by a tool instance.

__abstractmethods__ = frozenset([])

__dataschemafile__ = ‘NodeRun.schema.json’

__eq__(other)
Compare two Node instances with each other. This function ignores the parent and update status, but tests rest of the dict for equality. equality

Parameters `other` (*NodeRun*) – the other instances to compare to

Returns True if equal, False otherwise

__getstate__()
Retrieve the state of the NodeRun

Returns the state of the object

Rtype dict

__init__(node, parent)
Instantiate a node.

Parameters

- **node** (`Tool`) – The node to base the noderun on
- **parent** (`Network`) – the parent network of the node

Returns the newly created NodeRun

__metaclass__

alias of `ABCMeta`

__module__ = 'fastr.execution.noderun'**__repr__()**

Get a string representation for the NodeRun

Returns the string representation

Return type `str`

__setstate__(state)

Set the state of the NodeRun by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

__str__()

Get a string version for the NodeRun

Returns the string version

Return type `str`

blocking

Indicate that the results of this NodeRun cannot be determined without first executing the NodeRun, causing a blockage in the creation of jobs. A blocking Nodes causes the Chunk borders.

create_job (`sample_id`, `sample_index`, `job_data`, `job_dependencies`, `**kwargs`)

Create a job based on the sample id, job data and job dependencies.

Parameters

- **sample_id** (`SampleId`) – the id of the corresponding sample
- **sample_index** (`SampleIndex`) – the index of the corresponding sample
- **job_data** (`dict`) – dictionary containing all input data for the job
- **job_dependencies** – other jobs that need to finish before this job can run

Returns the created job

Return type `Job`

classmethod createobj (`state`, `network=None`)**dimnames**

Names of the dimensions in the NodeRun output. These will be reflected in the SampleIdList of this NodeRun.

execute()

Execute the node and create the jobs that need to run

Returns list of jobs to run

Return type list of `Jobs`

find_source_index (*target_index, target, source*)**fullid**

The full defining ID for the NodeRun inside the network

get_sourced_nodes ()

A list of all Nodes connected as sources to this NodeRun

Returns list of all nodes that are connected to an input of this node**global_id**

The global defining ID for the Node from the main network (goes out of macro nodes to root network)

id

The id of the NodeRun

input_groups**A list of input groups for this NodeRun. An input group is InputGroup object filled according to the NodeRun****listeners**

All the listeners requesting output of this node, this means the listeners of all Outputs and SubOutputs

merge_dimensions**name**

Name of the Tool the NodeRun was based on. In case a Toolless NodeRun was used the class name is given.

outputszie

Size of the outputs in this NodeRun

parent

The parent network of this node.

required_cores

Number of cores required for the execution of this NodeRun

required_memory

Amount of memory required for the execution of this NodeRun. Follows the format d+[mMgG] so 500M or 4g would be valid ways to specify 500 megabytes or 4 gigabyte of memory.

required_time

Amount of time required for the execution of this NodeRun. Follows the format of a number of second or H:M:S, with H the number of hours, M the number of minutes and S the number of seconds.

set_result (*job, failed_annotation*)

Incorporate result of a job into the NodeRun.

Parameters

- **job** (*Type*) – job of which the result to store
- **failed_annotation** – A set of annotations, None if no errors else containing a tuple describing the errors

status**tool****update_input_groups ()**

Update all input groups in this node

sinknoderun Module

```
class fastr.execution.sinknoderun.SinkNodeRun (node, parent)
    Bases: fastr.execution.noderun.NodeRun
```

Class which handles where the output goes. This can be any kind of file, e.g. image files, textfiles, config files, etc.

```
__abstractmethods__ = frozenset([])
__dataschemafile__ = 'SinkNodeRun.schema.json'
__getstate__ ()
__init__ (node, parent)
    Instantiation of the SinkNodeRun.
```

Parameters

- **node** ([Node](#)) – The Node that this Run is based on.
- **parent** ([NetworkRun](#)) – The NetworkRun that this NodeRun belongs to

Returns newly created sink node run

```
__module__ = 'fastr.execution.sinknoderun'
__setstate__ (state)
```

```
create_job (sample_id, sample_index, job_data, job_dependencies, **kwargs)
    Create a job for a sink based on the sample id, job data and job dependencies.
```

Parameters

- **sample_id** ([SampleId](#)) – the id of the corresponding sample
- **job_data** ([dict](#)) – dictionary containing all input data for the job
- **job_dependencies** – other jobs that need to finish before this job can run

Returns the created job

Return type [Job](#)

datatype

The datatype of the data this sink can store.

execute()

Execute the sink node and create the jobs that need to run

Returns list of jobs to run

Return type list of [Jobs](#)

input

The default input of the sink NodeRun

set_data(*data*)

Set the targets of this sink node.

Parameters **data** ([dict](#) or list of urls) – the targets rules for where to write the data

The target rules can include a few fields that can be filled out:

field	description
sample_id	the sample id of the sample written in string form
cardinality	the cardinality of the sample written
ext	the extension of the datatype of the written data, including the .
extension	the extension of the datatype of the written data, excluding the .
network	the id of the network the sink is part of
node	the id of the node of the sink
timestamp	the iso formatted datetime the network execution started
uuid	the uuid of the network run (generated using <code>uuid.uuid1()</code>)

An example of a valid target could be:

```
>>> target = 'vfs://output_mnt/some/path/image_{sample_id}_{cardinality}{ext}'
```

Note: The `{ext}` and `{extension}` are very similar but are both offered. In many cases having a name.`{extension}` will feel like the correct way to do it. However, if you have DataTypes with and without extension that can both be exported by the same sink, this would cause either `name.ext` or `name`.`to be generated. In this particular case name{ext} can help as it will create either name.ext or name.`

`set_result(job, failed_annotation)`

Incorporate result of a sink job into the Network.

Parameters

- **job** (`Type`) – job of which the result to store
- **failed_annotation** (`set`) – A set of annotations, None if no errors else containing a tuple describing the errors

sourcenoderun Module

`class fastr.execution.sourcenoderun.SourceNodeRun(node, parent)`

Bases: `fastr.execution.flownoderun.FlowNodeRun`

Class providing a connection to data resources. This can be any kind of file, stream, database, etc from which data can be received.

```
__abstractmethods__ = frozenset()
__dataschemafile__ = 'SourceNodeRun.schema.json'
__eq__(other)
```

Compare two Node instances with each other. This function ignores the parent and update status, but tests rest of the dict for equality. equality

Parameters `other` (`NodeRun`) – the other instances to compare to

Returns True if equal, False otherwise

```
__getstate__()
```

Retrieve the state of the SourceNodeRun

Returns the state of the object

Rtype dict

```
__init__(node, parent)
```

Instantiation of the SourceNodeRun.

Parameters

- **node** ([Node](#)) – The Node that this Run is based on.
- **parent** ([NetworkRun](#)) – The NetworkRun that this NodeRun belongs to

Returns newly created sink node run

__module__ = ‘fastr.execution.sourcenoderun’

__setstate__ (state)

Set the state of the SourceNodeRun by the given state.

Parameters **state** ([dict](#)) – The state to populate the object with

Returns None

create_job (sample_id, sample_index, job_data, job_dependencies, **kwargs)

datatype

The datatype of the data this source supplies.

dimnames

Names of the dimensions in the SourceNodeRun output. These will be reflected in the SampleIdLists.

execute()

Execute the source node and create the jobs that need to run

Returns list of jobs to run

Return type list of [Jobs](#)

output

Shorthand for self.outputs['output']

outputszie

The size of output of this SourceNodeRun

set_data (data, ids=None)

Set the data of this source node.

Parameters

- **data** ([dict](#), [OrderedDict](#) or list of urls) – the data to use
- **ids** – if data is a list, a list of accompanying ids

sourcegroup

valid

This does nothing. It only overloads the valid method of NodeRun(). The original is intended to check if the inputs are connected to some output. Since this class does not implement inputs, it is skipped.

class [fastr.execution.sourcenoderun.ConstantNodeRun](#) (node, parent)

Bases: [fastr.execution.sourcenoderun.SourceNodeRun](#)

Class encapsulating one output for which a value can be set. For example used to set a scalar value to the input of a node.

__abstractmethods__ = frozenset([])

__dataschemafile__ = ‘ConstantNodeRun.schema.json’

__getstate__ ()

Retrieve the state of the ConstantNodeRun

Returns the state of the object

Rtype dict**__init__(node, parent)**

Instantiation of the ConstantNodeRun.

Parameters

- **datatype** – The datatype of the output.
- **data** – the prefilled data to use.
- **id** – The url pattern.

This class should never be instantiated directly (unless you know what you are doing). Instead create a constant using the network class like shown in the usage example below.

usage example:

```
>>> import fastr
>>> network = fastr.Network()
>>> source = network.create_source(datatype=fastr.typeList['ITKImageFile'],  
    ↴id_='sourceN')
```

or alternatively create a constant node by assigning data to an item in an InputDict:

```
>>> node_a.inputs['in'] = ['some', 'data']
```

which automatically creates and links a ConstantNodeRun to the specified Input

__module__ = 'fastr.execution.sourcenoderun'**__setstate__(state)**

Set the state of the ConstantNodeRun by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

data

The data stored in this constant node

execute()

Execute the constant node and create the jobs that need to run

Returns list of jobs to run

Return type list of *Jobs*

set_data(data=None, ids=None)

Set the data of this constant node in the correct way. This is mainly for compatibility with the parent class SourceNodeRun

Parameters

- **data** (*dict* or list of urls) – the data to use
- **ids** – if data is a list, a list of accompanying ids

resources Package**resources Package**

Subpackages

datatypes Package

datatypes Package

AnalyzeImageFile Module

Boolean Module

Directory Module

FilePrefix Module

Float Module

ITKImageFile Module

Int Module

JsonFile Module

MetaImageFile Module

NiftiImageFile Module

NiftiImageFileCompressed Module

NiftiImageFileUncompressed Module

Number Module

ProvNFile Module

String Module

TifImageFile Module

TxtFile Module

UnsignedInt Module

tools Package

tools Package

Subpackages

fastr Package

Subpackages

util Package

Subpackages

0.1 Package

Subpackages

bin Package

auto_prefix Module

auto_prefix_negate Module

delay Module

fail Module

passthroughauto Module

range Module

stdout Module

test Package

test Package

testdatatype Module

utils Package

utils Package

A collections of utils for fastr (command line tools or non-core functionality)

checksum Module

This module contains a number of functions for checksumming files and objects

```
fastr.utils.checksum.checksum(filepath, algorithm='md5', hasher=None)
```

Generate the checksum of a file

Parameters

- **filepath** (*str*, *list*) – path of the file(s) to checksum
- **algorithm** (*str*) – the algorithm to use
- **hasher** (*_hashlib.HASH*) – a hasher to continue updating (rather than creating a new one)

Returns the checksum

Return type *str*

```
fastr.utils.checksum.checksum_directory(directory, algorithm='md5', hasher=None)
```

Generate the checksum of an entire directory

Parameters

- **directory** (*str*) – path of the file(s) to checksum
- **algorithm** (*str*) – the algorithm to use
- **hasher** (*_hashlib.HASH*) – a hasher to continue updating (rather than creating a new one)

Returns the checksum

Return type *str*

```
fastr.utils.checksum.hashsum(objects, hasher=None)
```

Generate the md5 checksum of (a) python object(s)

Parameters

- **objects** – the objects to hash
- **hasher** – the hasher to use as a base

Returns the hash generated

Return type *str*

```
fastr.utils.checksum.md5_checksum(filepath)
```

Generate the md5 checksum of a file

Parameters **filepath** (*str*, *list*) – path of the file(s) to checksum

Returns the checksum

Return type *str*

```
fastr.utils.checksum.sha1_checksum(filepath)
```

Generate the sha1 checksum of a file

Parameters **filepath** (*str*, *list*) – path of the file(s) to checksum

Returns the checksum

Return type *str*

classproperty Module

Module containing the code to create class properties.

`class fastr.utils.classproperty.ClassPropertyDescriptor (fget)`

Bases: `object`

A descriptor that can act like a property for a class.

`__dict__ = dict_proxy({'__module__': 'fastr.utils.classproperty', '__dict__': <attribute '__dict__' of 'ClassPropertyDescriptor' objects at 0x0000000000000000>, '__weakref__': <attribute '__weakref__' of 'ClassPropertyDescriptor' objects at 0x0000000000000000>})`

`__get__(obj, cls=None)`

`__init__(fget)`

`__module__ = 'fastr.utils.classproperty'`

`__weakref__`

list of weak references to the object (if defined)

`fastr.utils.classproperty.classproperty(func)`

Decorator to create a “class property”

Parameters `func` – the function to wrap

Returns a class property

Return type `ClassPropertyDescriptor`

clear_pycs Module

A small tool to wipe all .pyc files from fastr

`fastr.utils.clear_pycs.dir_list(directory)`

Find all .pyc files

Parameters `directory` (`str`) – directory to search

Returns all .pyc files

Return type list

`fastr.utils.clear_pycs.main()`

Main entry point

compare Module

Module to compare various fastr specific things such as a execution directory or a reference directory.

`fastr.utils.compare.compare_execution_dir(path1, path2)`

`fastr.utils.compare.compare_job_dirs(sample, node, node_dir1, node_dir2)`

`fastr.utils.compare.compare_job_output_data(output, job1, job2)`

`fastr.utils.compare.compare_set(set1, set2, path, sub_compare_func, f_args=None, f_kwargs=None)`

Compare two sets and dispatch each item to a sub comparison function

Parameters

- `set1` (`Iterable`) – first set of items

- **set2** (*Iterable*) – second set of items
- **path** (*str*) – identifier of the data location
- **sub_compare_func** – function to apply to items
- **f_args** – args to pass to sub_compare_func
- **f_kwargs** – kwargs to pass to sub_compare_func

Returns generator that iterates over the differences

Return type generator

```
fastr.utils.compare.compare_value_dict_item(key, data1, data2, path)
```

```
fastr.utils.compare.compare_value_list(data1, data2, path, key=None)
```

dicteq Module

Some helper function to compare dictionaries and find the parts of the dict that are different. This is mostly to help in debugging.

```
fastr.utils.dicteq.dicteq(self, other)
    Compare two dicts for equality
```

Parameters

- **self** – the first object to compare
- **other** – the oth

Returns

```
fastr.utils.dicteq.diffdict(self, other, path=None, visited=None)
```

Find the differences in two dictionaries.

Parameters

- **self** – the first object to compare
- **other** (*dict*) – other dictionary
- **path** (*list*) – the path for nested dicts (too keep track of recursion)

Returns list of messages indicating the differences

Return type list

```
fastr.utils.dicteq.diffobj(self, other, path=None, visited=None)
```

Compare two objects by comparing their __dict__ entries

Parameters

- **self** – the first object to compare
- **other** – other objects to compare
- **path** (*list*) – the path for nested dicts (too keep track of recursion)

Returns list of messages

Return type list

```
fastr.utils.dicteq.diffobj_str(self, other)
```

Compare two objects by comparing their __dict__ entries, but returns the differences in a single string ready for logging.

Parameters

- **self** – the first object to compare
- **other** – other object to compare to

Returns the description of the differences

Return type str

filesynchelper Module

Some helper functions that aid with NFS file sync issues.

class fastr.utils.filesynchelper.FileSyncHelper

```
__init__()
__module__ = 'fastr.utils.filesynchelper'
has_file_promise(url)
job_finished(jobfile)
load(url)
make_file_promise(url)
store(url, data)
wait_for_file(path, timeout=300)
wait_for_job(jobfile)
wait_for_pickle(url, timeout=300)
wait_for vfs_url(vfs_url, timeout=300)
fastr.utils.filesynchelper.filesynchelper_enabled()
```

gettools Module

fastr.utils.gettools.main()

iohelpers Module

```
fastr.utils.iohelpers.load_gpickle(path, retry_scheme=None)
fastr.utils.iohelpers.load_json(path)
fastr.utils.iohelpers.save_gpickle(path, data)
fastr.utils.iohelpers.save_json(path, data, indent=2)
```

jsonschema.parser Module

The JSON schema parser validates a json data structure and if possible casts data to the correct type and fills out default values. The result in a valid document that can be used to construct objects.

```
class fastr.utils.jsonschema.parser.FastrRefResolver(base_uri, referrer, store=(),
                                                     cache_remote=True, handlers=())
```

Bases: jsonschema.validators.RefResolver

Adapted version of the RefResolver for handling inter-file references more to our liking

```
__init__(base_uri, referrer, store=(), cache_remote=True, handlers=())
```

Create a new FastrRefResolver

Parameters

- **base_uri** (`str`) – URI of the referring document
- **referrer** – the actual referring document
- **store** (`dict`) – a mapping from URIs to documents to cache
- **cache_remote** (`bool`) – whether remote refs should be cached after first resolution
- **handlers** (`dict`) – a mapping from URI schemes to functions that should be used to retrieve them

```
__module__ = 'fastr.utils.jsonschema.parser'
```

```
classmethod from_schema(schema, *args, **kwargs)
```

Instantiate a RefResolver based on a schema

```
static readfastrschema(name)
```

Open a json file based on a fastr:// url that points to a file in the fastr.schemadir

Parameters `name` (`str`) – the url of the file to open

Returns the resulting json schema data

```
static readfile(filename)
```

Open a json file based on a simple filename

Parameters `filename` (`str`) – the path of the file to read

Returns the resulting json schema data

```
fastr.utils.jsonschema.parser.any_of_draft4 validator, any_of, instance, schema)
```

The oneOf directory needs to be done stepwise, because a validation even if it fails will try to change types / set defaults etc. Therefore we first create a copy of the data per subschema and test if they match. Then for all the schemas that are valid, we perform the validation on the actual data so that only the valid subschemas will effect the data.

Parameters

- **validator** – the json schema validator
- **any_of** (`dict`) – the current oneOf
- **instance** – the current object instance
- **schema** (`dict`) – the current json schema

```
fastr.utils.jsonschema.parser.extend validator_cls)
```

Extend the given jsonschema.IValidator with the Seep layer.

```
fastr.utils.jsonschemaparser.getblueprinter(uri, blueprint=None)
```

Instantiate the given data using the blueprinter.

Parameters **blueprint** – a blueprint (JSON Schema with Seep properties)

```
fastr.utils.jsonschemaparser.items_prevalidate(validation, items, instance, schema)
```

The pre-validation function for items

Parameters

- **validator** – the json schema validator
- **items** (*dict*) – the current items
- **instance** – the current object instance
- **schema** (*dict*) – the current json schema

```
fastr.utils.jsonschemaparser.not_draft4(validation, not_schema, instance, schema)
```

The not needs to use a temporary copy of the instance, not to change the instance with the invalid schema

Parameters

- **validator** – the json schema validator
- **not_schema** (*dict*) – the current oneOf
- **instance** – the current object instance
- **schema** (*dict*) – the current json schema

```
fastr.utils.jsonschemaparser.one_of_draft4(validation, one_of, instance, schema)
```

The one_of directory needs to be done stepwise, because a validation even if it fails will try to change types / set defaults etc. Therefore we first create a copy of the data per subschema and test if they match. Once we found a proper match, we only validate that branch on the real data so that only the valid piece of schema will effect the data.

Parameters

- **validator** – the json schema validator
- **one_of** (*dict*) – the current one_of
- **instance** – the current object instance
- **schema** (*dict*) – the current json schema

```
fastr.utils.jsonschemaparser.pattern_properties_valid(validation, pattern_properties, instance, schema)
```

The pre-validation function for patternProperties

Parameters

- **validator** – the json schema validator
- **pattern_properties** (*dict*) – the current patternProperties
- **instance** (*dict*) – the current object instance
- **schema** (*dict*) – the current json schema

```
fastr.utils.jsonschemaparser.properties_postvalidate(validation, properties, instance, schema)
```

All arguments must be used because this function is called like this # pylint: disable=unused-argument The post-validation function for properties

Parameters

- **validator** – the json schema validator
- **properties** (*dict*) – the current properties
- **instance** – the current object instance
- **schema** (*dict*) – the current json schema

```
fastr.utils.jsonschemaparser.properties_prevalidate(validator, properties, instance,  
                                              schema)
```

The pre-validation function for properties

Parameters

- **validator** – the json schema validator
- **properties** (*dict*) – the current properties
- **instance** – the current object instance
- **schema** (*dict*) – the current json schema

multiprocesswrapper Module

```
fastr.utils.multiprocesswrapper.function_wrapper(filepath, fnc_name, *args, **kwargs)
```

pim_publisher Module

```
class fastr.utils.pim_publisher.PimPublisher(uri=None)
```

Bases: *object*

Class to publish to PIM

```
PIM_STATUS_MAPPING = {<JobState.execution_done: ('execution_done', 'in_progress', False)>: 'running', <JobState.n
```

```
_dict_ = dict_proxy({'__dict__': <attribute '__dict__' of 'PimPublisher' objects>, '__module__': 'fastr.utils.pim_publ
```

```
_init_(uri=None)
```

```
_module_ = 'fastr.utils.pim_publisher'
```

```
_weakref_
```

list of weak references to the object (if defined)

```
pim_register_run(network)
```

```
pim_serialize_network(network, scope=None, network_data=None)
```

Serialize Network in the correct for to use with PIM.

Returns json data for PIM

```
pim_update_status(network_run, job)
```

procutils Module

```
fastr.utils.procutils.which(name)
```

Find executable by name on the PATH, returns the executable that will be found in case it is used for a Popen call

rest_generation Module

`fastr.utils.rest_generation.create_rest_table(data, headers)`

Create a ReST table from data. The data should be a list of columns and the headers should be a list of column names.

Parameters

- **data** (*list*) – List of lists/tuples representing the columns
- **headers** (*list*) – List of strings for the column names

Returns a string representing the table in ReST

Return type str

schematotable Module

A module to generate reStructuredText tables from json schema files

`class fastr.utils.schematotable.SchemaPrinter(schema, skipfirst=False)`

Bases: object

Object that create a table in reStructuedText from a json schema

`__dict__ = dict_proxy({'parse': <function parse>, '__module__': 'fastr.utils.schematotable', 'descend': <function descend>})`

`__init__(schema, skipfirst=False)`

Create the printer object

Parameters

- **schema** (*dict*) – the json schema to print
- **skipfirst** (*bool*) – flag to indicate that the first line should not be printed

`__module__ = 'fastr.utils.schematotable'`

`__str__()`

String representation of json schema (that is the printed table)

`__weakref__`

list of weak references to the object (if defined)

`descend(properties)`

Descend into a subschema

Parameters `properties (dict)` – the properties in the subschema

`parse(schema=None)`

Parse a schema

Parameters `schema (dict)` – the schema to parse

`printlines()`

Given a parsed schema (parsing happens when the object is constructed), print all the lines

Returns the printed table

Return type str

sysinfo Module

This module contains function to help gather system information use for the provenance of the Job execution.

`fastr.utils.sysinfo.get_cpu_usage()`

Get the current CPU usage

Returns CPU usage info

Return type dict

`fastr.utils.sysinfo.get_drmaa_info()`

Get information about the SGE cluster (if applicable)

Returns cluster info

Return type dict

`fastr.utils.sysinfo.get_hostinfo()`

Get all information about the current host machine

Returns host info

Return type dict

`fastr.utils.sysinfo.get_memory_usage()`

Get the current memory usage

Returns memory usage info

Return type dict

`fastr.utils.sysinfo.get_mounts()`

Get the current mounts known on the system

Returns mount info

Return type dict

`fastr.utils.sysinfo.get_os()`

Get information about the OS

Returns OS information

Return type dict

`fastr.utils.sysinfo.get_processes()`

Get a list of all currently running processes

Returns process information

Return type list

`fastr.utils.sysinfo.get_python()`

Get information about the currently used Python implementation

Returns python info

Return type dict

`fastr.utils.sysinfo.get_sysinfo()`

Get system information (cpu, memory, mounts and users)

Returns system information

Return type dict

`fastr.utils.sysinfo.get_users()`

Get current users on the system

Returns user info

Return type dict

`fastr.utils.sysinfo.namedtuple_to_dict(ntuple)`

Helper function to convert a named tuple into a dict

Parameters ntuple (namedtuple) – the namedtuple to convert

Returns named tuple as a dict

Return type dict

verify Module

`fastr.utils.verify.verify_resource_loading(filename)`

`fastr.utils.verify.verify_tool(filename)`

Verify that a file

xmldict Module

This module contains tool for converting python dictionaries into XML object and vice-versa.

`fastr.utils.xmldict.dump(data, filehandle)`

Write a dict to an XML file

Parameters

- **data** – data to write
- **filehandle** – file handle to write to

`fastr.utils.xmldict.dumps(data)`

Write a dict to an XML string

Parameters data – data to write

Returns the XML data

Return type str

`fastr.utils.xmldict.load(filehandle)`

Load an xml file and parse it to a dict

Parameters filehandle – file handle to load

Returns the parsed data

`fastr.utils.xmldict.loads(data)`

Load an xml string and parse it to a dict

Parameters data (str) – the xml data to load

Returns the parsed data

Subpackages

cmd Package

cmd Package

```
fastr.utils.cmd.add_parser_doc_link(parser,filepath)
fastr.utils.cmd.find_commands()
fastr.utils.cmd.get_command_module(command)
fastr.utils.cmd.main()
fastr.utils.cmd.print_help(commands=None)
```

cat Module

```
fastr.utils.cmd.cat.fastr_cat(infile, path)
fastr.utils.cmd.cat.get_parser()
fastr.utils.cmd.cat.main()
    Print information from a job file
```

dump Module

```
fastr.utils.cmd.dump.create_zip(directory, output_file)
fastr.utils.cmd.dump.get_parser()
fastr.utils.cmd.dump.main()
    Dump the contents of a network run tempdir into a zip for remote assistance
```

execute Module

```
fastr.utils.cmd.execute.get_parser()
fastr.utils.cmd.execute.main()
    Execute a fastr job file
```

extract_argparse Module

```
fastr.utils.cmd.extract_argparse.cardinality_from_nargs(value)
fastr.utils.cmd.extract_argparse.datatype_from_type(type_, metavar)
fastr.utils.cmd.extract_argparse.extract_argparser(filepath)
fastr.utils.cmd.extract_argparse.find_argparser(entry, basename='/home/docs/checkouts/readthedocs.org/user_
build')
fastr.utils.cmd.extract_argparse.get_parser()
fastr.utils.cmd.extract_argparse.main()
    Create a stub for a Tool based on a python script using argparse
```

prov Module

```
fastr.utils.cmd.prov.get_parser()  
fastr.utils.cmd.prov.get_prov_document(result)  
fastr.utils.cmd.prov.main()  
    Get PROV information from the result pickle.
```

run Module

```
fastr.utils.cmd.run.create_network_parser(network)  
fastr.utils.cmd.run.get_parser()  
fastr.utils.cmd.run.main()  
    Run a Network from the commandline
```

test Module

```
fastr.utils.cmd.test.check_network(args)  
fastr.utils.cmd.test.check_networks(args)  
fastr.utils.cmd.test.check_tool(args)  
fastr.utils.cmd.test.check_tools(args)  
fastr.utils.cmd.test.directory(path)  
    Make sure the path is a valid directory for argparse  
fastr.utils.cmd.test.get_parser()  
fastr.utils.cmd.test.main()  
    Run the tests of a tool to verify the proper function  
fastr.utils.cmd.test.tool(value)  
    Make sure the value is a correct tool for argparse or reference directory
```

trace Module

```
fastr.utils.cmd.trace.get_parser()  
fastr.utils.cmd.trace.main()  
    Trace samples/sinks from a run  
fastr.utils.cmd.trace.print_job_result(job_file)  
fastr.utils.cmd.trace.print_sample_sink(sink_data, dirname, sample_sink_tuples, verbose)  
fastr.utils.cmd.trace.print_samples(sink_data, sample_ids, verbose)  
fastr.utils.cmd.trace.print_sinks(sink_data, sink_ids, verbose)  
fastr.utils.cmd.trace.read_sink_data(infile)  
fastr.utils.cmd.trace.switch_sample_sink(sink_data)
```

verify Module

```
fastr.utils.cmd.verify.get_parser()  
fastr.utils.cmd.verify.main()  
    Print information from a job file
```

webapp Module

```
fastr.utils.cmd.webapp.get_parser()  
fastr.utils.cmd.webapp.main()  
    Start the fastr webapp and open in a new browser tab  
fastr.utils.cmd.webapp.open_url(url)
```

secrets Package**secrets Package****secretprovider Module****secretservice Module****Subpackages****exceptions Package****exceptions Package****couldnotdeletecredentials Module****couldnotretrievecredentials Module****couldnotsetcredentials Module****notimplemented Module****providerNotFound Module****providers Package****providers Package****keyringprovider Module****netrcprovider Module**

web Package**web Package****api Module**

```
class fastr.web.api.NetworkApi (api=None, *args, **kwargs)
    Bases: flask_restplus.resource.Resource

    __module__ = 'fastr.web.api'
    endpoint = 'api_network'

    get (id_)
        Get a Network json description from the server

    mediatypes (resource_cls)

    methods = ['GET']

class fastr.web.api.NetworkListApi (api=None, *args, **kwargs)
    Bases: flask_restplus.resource.Resource

    __module__ = 'fastr.web.api'
    endpoint = 'api_networks'

    get (*args, **kwargs)
        Get a list of the networks

    mediatypes (resource_cls)

    methods = ['GET']

class fastr.web.api.ObjectUrl (object_classs, **kwargs)
    Bases: flask_restplus.fields.Raw

    __init__ (object_classs, **kwargs)
    __module__ = 'fastr.web.api'
    __schema_type__ = 'string'
    __slotnames__ = []
    format (value)

class fastr.web.api.Run (id_, network, source_data, sink_data)
    Bases: object

    __dict__ = dict_proxy({'status': <function status>, '__module__': 'fastr.web.api', 'abort': <function abort>, '__dict__': None})
    __init__ (id_, network, source_data, sink_data)
    __module__ = 'fastr.web.api'
    __weakref__
        list of weak references to the object (if defined)
    abort ()
    run_network (network, source_data, sink_data, abort_lock)
    status ()
```

```

class fastr.web.api.RunApi (api=None, *args, **kwargs)
    Bases: flask_restplus.resource.Resource

        Run API documentation

        __module__ = 'fastr.web.api'

        delete (id_)
            Abort a Network run and stop all associated execution

        endpoint = 'api_run'

        get (*args, **kwargs)
            Get information about a Network run

        mediatypes (resource_cls)
        methods = ['DELETE', 'GET']

class fastr.web.api.RunListApi (api=None, *args, **kwargs)
    Bases: flask_restplus.resource.Resource

        __module__ = 'fastr.web.api'

        endpoint = 'api_runs'

        get (*args, **kwargs)
            Get a list of all Network runs on the server

        mediatypes (resource_cls)
        methods = ['GET', 'POST']

        post ()
            Create a new Network run and start execution

        request_parser = <flask_restplus.reqparse.RequestParser object>

class fastr.web.api.StatusApi (api=None, *args, **kwargs)
    Bases: flask_restplus.resource.Resource

        __module__ = 'fastr.web.api'

        endpoint = 'api_status'

        get (id_)
            Get the status of a Network Run on the server

        mediatypes (resource_cls)
        methods = ['GET']

class fastr.web.api.SubUrl (object_classs, subfield, **kwargs)
    Bases: flask_restplus.fields.Raw

        __init__ (object_classs, subfield, **kwargs)
        __module__ = 'fastr.web.api'
        schema_type = 'string'

        format (value)

class fastr.web.api.ToolApi (api=None, *args, **kwargs)
    Bases: flask_restplus.resource.Resource

        __module__ = 'fastr.web.api'

```

```
endpoint = 'api_version_tool'

get (id_, version=None)
    Get a Tool json description from the server

mediatypes (resource_cls)

methods = ['GET']

class fastr.web.api.ToolListApi (api=None, *args, **kwargs)
    Bases: flask_restplus.resource.Resource

    __module__ = 'fastr.web.api'

endpoint = 'api_tools'

get (*args, **kwargs)
    Get a list of all Tools known to the server

mediatypes (resource_cls)

methods = ['GET']

fastr.web.api.network_lock_thread (lock, network)

fastr.web.api.network_runner (network, source_data, sink_data, chuck_status, job_status,
                             job_results, abort_lock)

fastr.web.api.update_job_result (job, job_status, job_results)

fastr.web.api.update_status (job, job_status)
```

run Module

```
fastr.web.run.main()

fastr.web.run.runapp (debug=False)
```

views Module

```
fastr.web.views.doc()

fastr.web.views.index()

fastr.web.views.network (name=None)

fastr.web.views.networks()

fastr.web.views.prov()

fastr.web.views.shutdown()

fastr.web.views.shutdown_server()

fastr.web.views.tool (toolname=None, version=None)

fastr.web.views.websocket_client()
```

CHAPTER 4

Indices and tables

- genindex
- modindex
- search

Python Module Index

f

fastr.`__init__`, 65
fastr.configmanager, 77
fastr.core, 116
fastr.core.basemanager, 116
fastr.core.baseplugin, 118
fastr.core.datatypemanager, 120
fastr.core.dimension, 122
fastr.core.inputgroup, 124
fastr.core.inputgroupcombiner, 126
fastr.core.inputoutput, 128
fastr.core.interface, 140
fastr.core.ioplugin, 142
fastr.core.link, 145
fastr.core.network, 148
fastr.core.networkmanager, 152
fastr.core.node, 152
fastr.core.objectmanager, 159
fastr.core.pluginmanager, 160
fastr.core.provenance, 163
fastr.core.samples, 164
fastr.core.serializable, 170
fastr.core.target, 172
fastr.core.test, 180
fastr.core.tool, 174
fastr.core.toolmanager, 176
fastr.core.updateable, 177
fastr.core.version, 179
fastr.core.vfs, 180
fastr.data, 181
fastr.data.url, 181
fastr.datatypes, 79
fastr.examples, 183
fastr.examples.`__generate_reference__`,
 183
fastr.examples.add_ints, 183
fastr.examples.add_ints_s3, 183
fastr.examples.auto_prefix, 183
fastr.examples.collapse, 183
fastr.examples.collapse_expand, 183
fastr.examples.cross_validation, 184
fastr.examples.elastix_nipype, 184
fastr.examples.expand, 184
fastr.examples.failing_network, 184
fastr.examples.filecopy, 184
fastr.examples.input_groups, 184
fastr.examples.macro_node, 185
fastr.examples.macro_node2, 185
fastr.examples.shift_links, 185
fastr.examples.source_sink, 185
fastr.exceptions, 89
fastr.execution, 186
fastr.execution.environmentmodules, 186
fastr.execution.executionpluginmanager,
 187
fastr.execution.executionscript, 191
fastr.execution.flownoderun, 191
fastr.execution.inputoutputrun, 192
fastr.execution.job, 202
fastr.execution.linkrun, 209
fastr.execution.macronoderun, 212
fastr.execution.networkanalyzer, 213
fastr.execution.networkchunker, 213
fastr.execution.networkrun, 214
fastr.execution.noderun, 216
fastr.execution.sinknoderun, 219
fastr.execution.sourcenoderun, 220
fastr.plugins, 95
fastr.resources, 222
fastr.utils, 224
fastr.utils.checksum, 224
fastr.utils.classproperty, 226
fastr.utils.clear_pycs, 226
fastr.utils.cmd, 235
fastr.utils.cmd.cat, 235
fastr.utils.cmd.dump, 235
fastr.utils.cmd.execute, 235
fastr.utils.cmd.extract_argparse, 235
fastr.utils.cmd.prov, 236

fastr.utils.cmd.run, 236
fastr.utils.cmd.test, 236
fastr.utils.cmd.trace, 236
fastr.utils.cmd.verify, 237
fastr.utils.cmd.webapp, 237
fastr.utils.compare, 226
fastr.utils.dicteq, 227
fastr.utils.filesynchelper, 228
fastr.utils.gettools, 228
fastr.utils.iohelpers, 228
fastr.utils.jsonschemaparser, 229
fastr.utils.multiprocesswrapper, 231
fastr.utils.pim_publisher, 231
fastr.utils.procutils, 231
fastr.utils.rest_generation, 232
fastr.utils.schematotable, 232
fastr.utils.sysinfo, 233
fastr.utils.verify, 234
fastr.utils.xmltodict, 234
fastr.version, 115
fastr.web, 238
fastr.web.api, 238
fastr.web.run, 240
fastr.web.views, 240

Symbols

- __abstractmethods__ (fastr.__init__.ConstantNode attribute), 74
- __abstractmethods__ (fastr.__init__.Link attribute), 69
- __abstractmethods__ (fastr.__init__.Node attribute), 72
- __abstractmethods__ (fastr.__init__.SinkNode attribute), 76
- __abstractmethods__ (fastr.__init__.SourceNode attribute), 75
- __abstractmethods__ (fastr.core.basemanager.BaseManager attribute), 117
- __abstractmethods__ (fastr.core.baseplugin.BasePlugin attribute), 118
- __abstractmethods__ (fastr.core.baseplugin.Plugin attribute), 119
- __abstractmethods__ (fastr.core.datatypemanager.DataTypeManager attribute), 120
- __abstractmethods__ (fastr.core.dimension.ForwardsDimensions attribute), 123
- __abstractmethods__ (fastr.core.dimension.HasDimensions attribute), 123
- __abstractmethods__ (fastr.core.inputgroup.InputGroup attribute), 124
- __abstractmethods__ (fastr.core.inputgroupcombiner.BaseInputGroupCombiner attribute), 126
- __abstractmethods__ (fastr.core.inputgroupcombiner.DefaultInputGroupCombiner attribute), 127
- __abstractmethods__ (fastr.core.inputgroupcombiner.MergingInputGroupCombiner attribute), 127
- __abstractmethods__ (fastr.core.inputoutput.AdvancedFlowOutput attribute), 128
- __abstractmethods__ (fastr.core.inputoutput.BaseInput attribute), 128
- __abstractmethods__ (fastr.core.inputoutput.BaseInputOutput attribute), 129
- __abstractmethods__ (fastr.core.inputoutput.BaseOutput attribute), 130
- __abstractmethods__ (fastr.core.inputoutput.Input attribute), 131
- __abstractmethods__ (fastr.core.inputoutput.MacroOutput attribute), 133
- __abstractmethods__ (fastr.core.inputoutput.Output attribute), 133
- __abstractmethods__ (fastr.core.inputoutput.SourceOutput attribute), 135
- __abstractmethods__ (fastr.core.inputoutput.SubInput attribute), 136
- __abstractmethods__ (fastr.core.inputoutput.SubOutput attribute), 138
- __abstractmethods__ (fastr.core.interface.Interface attribute), 140
- __abstractmethods__ (fastr.core.interface.InterfacePluginManager attribute), 141
- __abstractmethods__ (fastr.core.ioplugin.IOPlugin attribute), 142
- __abstractmethods__ (fastr.core.ioplugin.IOPluginManager attribute), 144
- __abstractmethods__ (fastr.core.link.Link attribute), 146
- __abstractmethods__ (fastr.core.networkmanager.NetworkManager attribute), 152
- __abstractmethods__ (fastr.core.node.AdvancedFlowNode attribute), 152
- __abstractmethods__ (fastr.core.node.ConstantNode attribute), 152
- __abstractmethods__ (fastr.core.node.FlowNode attribute), 153
- __abstractmethods__ (fastr.core.node.MacroNode attribute), 154
- __abstractmethods__ (fastr.core.node.Node attribute), 155
- __abstractmethods__ (fastr.core.node.SinkNode attribute), 157
- __abstractmethods__ (fastr.core.node.SourceNode attribute), 158
- __abstractmethods__ (fastr.core.objectmanager.ObjectManager attribute), 159
- __abstractmethods__ (fastr.core.pluginmanager.BasePluginManager attribute), 160
- __abstractmethods__ (fastr.core.pluginmanager.PluginManager attribute), 160

attribute), 161
__abstractmethods__(fastr.core.pluginmanager.PluginSubManager attribute), 162
__abstractmethods__(fastr.core.pluginmanager.PluginsView attribute), 162
__abstractmethods__(fastr.core.samples.ContainsSamples attribute), 164
__abstractmethods__(fastr.core.samples.HasSamples attribute), 164
__abstractmethods__(fastr.core.samples.SampleCollection attribute), 165
__abstractmethods__(fastr.core.samples.SampleValue attribute), 169
__abstractmethods__(fastr.core.target.ProcessUsageCollection attribute), 172
__abstractmethods__(fastr.core.target.Target attribute), 173
__abstractmethods__(fastr.core.target.TargetManager attribute), 173
__abstractmethods__(fastr.core.toolmanager.ToolManager attribute), 176
__abstractmethods__(fastr.core.updateable.Updateable attribute), 177
__abstractmethods__(fastr.datatypes.AnalyzeImageFile attribute), 79
__abstractmethods__(fastr.datatypes.AnyFile attribute), 79
__abstractmethods__(fastr.datatypes.AnyType attribute), 79
__abstractmethods__(fastr.datatypes.BaseDataType attribute), 79
__abstractmethods__(fastr.datatypes.Boolean attribute), 81
__abstractmethods__(fastr.datatypes.DataType attribute), 81
__abstractmethods__(fastr.datatypes.Deferred attribute), 82
__abstractmethods__(fastr.datatypes.Directory attribute), 83
__abstractmethods__(fastr.datatypes.EnumType attribute), 83
__abstractmethods__(fastr.datatypes.FilePrefix attribute), 83
__abstractmethods__(fastr.datatypes.Float attribute), 84
__abstractmethods__(fastr.datatypes.ITKImageFile attribute), 84
__abstractmethods__(fastr.datatypes.Int attribute), 84
__abstractmethods__(fastr.datatypes.JsonFile attribute), 84
__abstractmethods__(fastr.datatypes.MetaImageFile attribute), 85
__abstractmethods__(fastr.datatypes.NiftiImageFile attribute), 85
__abstractmethods__(fastr.datatypes.NiftiImageFileCompressed attribute), 85
__abstractmethods__(fastr.datatypes.NiftiImageFileUncompressed attribute), 85
__abstractmethods__(fastr.datatypes.Number attribute), 86
__abstractmethods__(fastr.datatypes.ProvNFile attribute), 86
__abstractmethods__(fastr.datatypes.String attribute), 86
__abstractmethods__(fastr.datatypes.TifImageFile attribute), 86
__abstractmethods__(fastr.datatypes.TxtFile attribute), 86
__abstractmethods__(fastr.datatypes.TypeGroup attribute), 87
__abstractmethods__(fastr.datatypes.URLType attribute), 87
__abstractmethods__(fastr.datatypes.UnsignedInt attribute), 88
__abstractmethods__(fastr.datatypes.ValueType attribute), 88
__abstractmethods__(fastr.execution.executionpluginmanager.ExecutionPlugin attribute), 189
__abstractmethods__(fastr.execution.executionpluginmanager.ExecutionPlugin attribute), 190
__abstractmethods__(fastr.execution.flownoderun.AdvancedFlowNodeRun attribute), 191
__abstractmethods__(fastr.execution.flownoderun.FlowNodeRun attribute), 191
__abstractmethods__(fastr.execution.inputoutputrun.AdvancedFlowOutput attribute), 192
__abstractmethods__(fastr.execution.inputoutputrun.BaseInputRun attribute), 192
__abstractmethods__(fastr.execution.inputoutputrun.InputRun attribute), 192
__abstractmethods__(fastr.execution.inputoutputrun.MacroOutputRun attribute), 194
__abstractmethods__(fastr.execution.inputoutputrun.OutputRun attribute), 194
__abstractmethods__(fastr.execution.inputoutputrun.SourceOutputRun attribute), 197
__abstractmethods__(fastr.execution.inputoutputrun.SubInputRun attribute), 198
__abstractmethods__(fastr.execution.inputoutputrun.SubOutputRun attribute), 200
__abstractmethods__(fastr.execution.linkrun.LinkRun attribute), 210
__abstractmethods__(fastr.execution.macronoderun.MacroNodeRun attribute), 212
__abstractmethods__(fastr.execution.noderun.NodeRun attribute), 216
__abstractmethods__(fastr.execution.sinknoderun.SinkNodeRun attribute), 219
__abstractmethods__(fastr.execution.sourcenoderun.ConstantNodeRun attribute), 221

__abstractmethods__ (fastr.execution.sourcenoderun.SourceNodeRains__() (fastr.core.samples.HasSamples method),
 attribute), 220
 __abstractmethods__ (fastr.plugins.BlockingExecution
 attribute), 96
 __abstractmethods__ (fastr.plugins.CommaSeperatedValueFiledataschemafile__ (fastr.__init__.ConstantNode
 attribute), 96
 __abstractmethods__ (fastr.plugins.CrossValidation
 attribute), 97
 __abstractmethods__ (fastr.plugins.DRMAAExecution
 attribute), 97
 __abstractmethods__ (fastr.plugins.DockerTarget
 attribute), 98
 __abstractmethods__ (fastr.plugins.FastrInterface
 attribute), 100
 __abstractmethods__ (fastr.plugins.FileSystem attribute),
 101
 __abstractmethods__ (fastr.plugins.FlowInterface
 attribute), 102
 __abstractmethods__ (fastr.plugins.LinearExecution
 attribute), 103
 __abstractmethods__ (fastr.plugins.LocalBinaryTarget
 attribute), 105
 __abstractmethods__ (fastr.plugins.NipypeInterface
 attribute), 106
 __abstractmethods__ (fastr.plugins.Null attribute), 106
 __abstractmethods__ (fastr.plugins.ProcessPoolExecution
 attribute), 107
 __abstractmethods__ (fastr.plugins.RQExecution
 attribute), 107
 __abstractmethods__ (fastr.plugins.Reference attribute),
 108
 __abstractmethods__ (fastr.plugins.S3Filesystem
 attribute), 108
 __abstractmethods__ (fastr.plugins.StrongrExecution
 attribute), 109
 __abstractmethods__ (fastr.plugins.VirtualFileSystem
 attribute), 110
 __abstractmethods__ (fastr.plugins.VirtualFileSystemRegularExpressittribute), 112
 __abstractmethods__ (fastr.plugins.VirtualFileSystemValueList
 attribute), 113
 __abstractmethods__ (fastr.plugins.XNATStorage
 attribute), 115
 __add__() (fastr.configmanager.EmptyDefault method),
 78
 __add__() (fastr.core.samples.SampleBaseId method),
 164
 __add__() (fastr.core.samples.SampleItemBase method),
 167
 __add__() (fastr.core.samples.SamplePayload method),
 169
 __add__() (fastr.core.samples.SampleValue method), 169
 __contains__() (fastr.core.objectmanager.ObjectManager
 method), 159
 164
 __contains__() (fastr.core.samples.SampleCollection
 method), 165
 __dataschemafile__ (fastr.__init__.Link attribute), 69
 __dataschemafile__ (fastr.__init__.Network attribute), 66
 __dataschemafile__ (fastr.__init__.Node attribute), 72
 __dataschemafile__ (fastr.__init__.SinkNode attribute),
 76
 __dataschemafile__ (fastr.__init__.SourceNode
 attribute), 75
 __dataschemafile__ (fastr.core.link.Link attribute), 146
 __dataschemafile__ (fastr.core.network.Network
 attribute), 148
 __dataschemafile__ (fastr.core.node.ConstantNode
 attribute), 152
 __dataschemafile__ (fastr.core.node.Node attribute), 155
 __dataschemafile__ (fastr.core.node.SinkNode attribute),
 157
 __dataschemafile__ (fastr.core.node.SourceNode
 attribute), 158
 __dataschemafile__ (fastr.core.tool.Tool attribute), 174
 __dataschemafile__ (fastr.execution.linkrun.LinkRun
 attribute), 210
 __dataschemafile__ (fastr.execution.noderun.NodeRun
 attribute), 216
 __dataschemafile__ (fastr.execution.sinknoderun.SinkNodeRun
 attribute), 219
 __dataschemafile__ (fastr.execution.sourcenoderun.ConstantNodeRun
 attribute), 221
 __dataschemafile__ (fastr.execution.sourcenoderun.SourceNodeRun
 attribute), 220
 __dataschemafile__ (fastr.plugins.FastrInterface
 attribute), 100
 __dataschemafile__ (fastr.plugins.FlowInterface
 attribute), 102
 __del__() (fastr.execution.executionpluginmanager.ExecutionPlugin
 method), 189
 __delitem__() (fastr.configmanager.EmptyDefault
 method), 78
 __delitem__() (fastr.core.basemanager.BaseManager
 method), 117
 __delitem__() (fastr.core.inputgroup.InputGroup
 method), 124
 __delitem__() (fastr.core.pluginmanager.PluginsView
 method), 162
 __delitem__() (fastr.core.samples.SampleCollection
 method), 165
 __delitem__() (fastr.core.samples.SampleValue method),
 169
 __dict__ (fastr.configmanager.Config attribute), 77
 __dict__ (fastr.configmanager.EmptyDefault attribute),

78
__dict__ (fastr.core.baseplugin.BasePlugin attribute), 118
__dict__ (fastr.core.dimension.Dimension attribute), 122
__dict__ (fastr.core.dimension.HasDimensions attribute),
 123
__dict__ (fastr.core.interface.InputSpec attribute), 140
__dict__ (fastr.core.interface.InterfaceResult attribute),
 141
__dict__ (fastr.core.interface.OutputSpec attribute), 142
__dict__ (fastr.core.pluginmanager.plugin_option_type
attribute), 162
__dict__ (fastr.core.provenance.Provenance attribute),
 163
__dict__ (fastr.core.samples.SampleBaseId attribute),
 164
__dict__ (fastr.core.samples.SampleItemBase attribute),
 167
__dict__ (fastr.core.serializable.PassThroughSerializer
attribute), 170
__dict__ (fastr.core.serializable.Serializable attribute),
 170
__dict__ (fastr.core.target.SystemUsageInfo attribute),
 172
__dict__ (fastr.core.updateable.Updateable attribute), 177
__dict__ (fastr.core.version.Version attribute), 179
__dict__ (fastr.execution.environmentmodules.Environment
attribute), 186
__dict__ (fastr.execution.networkanalyzer.NetworkAnalyzer
attribute), 213
__dict__ (fastr.execution.networkchunker.NetworkChunker
attribute), 214
__dict__ (fastr.utils.classproperty.ClassPropertyDescriptor
attribute), 226
__dict__ (fastr.utils.pim_publisher.PimPublisher
attribute), 231
__dict__ (fastr.utils.schematatable.SchemaPrinter
attribute), 232
__dict__ (fastr.web.api.Run attribute), 238
__enter__() (fastr.core.target.Target method), 173
__enter__() (fastr.execution.executionpluginmanager.Execution
method), 189
__enter__() (fastr.plugins.DockerTarget method), 98
__enter__() (fastr.plugins.LocalBinaryTarget
method), 105
__eq__() (fastr.__init__.Link method), 69
__eq__() (fastr.__init__.Network method), 66
__eq__() (fastr.__init__.Node method), 72
__eq__() (fastr.__init__.SourceNode method), 75
__eq__() (fastr.core.dimension.Dimension method), 122
__eq__() (fastr.core.inputoutput.Input method), 131
__eq__() (fastr.core.inputoutput.Output method), 133
__eq__() (fastr.core.inputoutput.SubInput method), 136
__eq__() (fastr.core.inputoutput.SubOutput method), 138
__eq__() (fastr.core.link.Link method), 146
__eq__() (fastr.core.network.Network method), 148
__eq__() (fastr.core.node.Node method), 155
__eq__() (fastr.core.node.SourceNode method), 158
__eq__() (fastr.core.tool.Tool method), 174
__eq__() (fastr.datatypes.BaseDataType method), 79
__eq__() (fastr.datatypes.Directory method), 83
__eq__() (fastr.datatypes.MetaImageFile method), 85
__eq__() (fastr.datatypes.URLType method), 87
__eq__() (fastr.execution.linkrun.LinkRun method), 210
__eq__() (fastr.execution.networkrun.NetworkRun
method), 214
__eq__() (fastr.execution.noderun.NodeRun method),
 216
__eq__() (fastr.execution.sourcenoderun.SourceNodeRun
method), 220
__eq__() (fastr.plugins.FastrInterface method), 100
__eq__() (fastr.plugins.FlowInterface method), 102
__eq__() (fastr.plugins.NipypeInterface method), 106
__exit__() (fastr.core.target.Target method), 173
__exit__() (fastr.execution.executionpluginmanager.ExecutionPlugin
method), 189
__exit__() (fastr.plugins.DockerTarget method), 98
__exit__() (fastr.plugins.LocalBinaryTarget method), 105
__format__() (fastr.core.baseplugin.PluginState method),
 119
__format__() (fastr.execution.environmentmodules.ModuleSystem
method), 187
__format__() (fastr.execution.executionpluginmanager.JobAction
method), 190
__format__() (fastr.execution.job.JobState method), 207
__get__() (fastr.utils.classproperty.ClassPropertyDescriptor
method), 226
__getattr__() (fastr.core.pluginmanager.LazyModule
method), 161
__getitem__() (fastr.__init__.Network method), 66
__getitem__() (fastr.configmanager.EmptyDefault
method), 78
__getitem__() (fastr.core.basemanager.BaseManager
method), 117
__getitem__() (fastr.core.inputgroup.InputGroup
method), 124
__getitem__() (fastr.core.inputoutput.Input method), 131
__getitem__() (fastr.core.inputoutput.Output method),
 133
__getitem__() (fastr.core.inputoutput.SourceOutput
method), 135
__getitem__() (fastr.core.inputoutput.SubInput method),
 136
__getitem__() (fastr.core.inputoutput.SubOutput
method), 138
__getitem__() (fastr.core.network.Network method), 148
__getitem__() (fastr.core.objectmanager.ObjectManager
method), 159
__getitem__() (fastr.core.pluginmanager.BasePluginManager

method), 160
`__getitem__()` (fastr.core.pluginmanager.PluginsView
 method), 162
`__getitem__()` (fastr.core.samples.ContainsSamples
 method), 164
`__getitem__()` (fastr.core.samples.HasSamples method),
 164
`__getitem__()` (fastr.core.samples.SampleCollection
 method), 165
`__getitem__()` (fastr.core.samples.SampleValue method),
 169
`__getitem__()` (fastr.core.target.ProcessUsageCollection
 method), 172
`__getitem__()` (fastr.execution.inputoutputrun.InputRun
 method), 192
`__getitem__()` (fastr.execution.inputoutputrun.OutputRun
 method), 194
`__getitem__()` (fastr.execution.inputoutputrun.SourceOutput
 method), 197
`__getitem__()` (fastr.execution.inputoutputrun.SubInputRun
 method), 198
`__getitem__()` (fastr.execution.inputoutputrun.SubOutputRun
 method), 200
`__getitem__()` (fastr.execution.linkrun.LinkRun method),
 210
`__getitem__()` (fastr.execution.networkrun.NetworkRun
 method), 214
`__getnewargs__()` (fastr.core.pluginmanager.plugin_option_type
 method), 162
`__getnewargs__()` (fastr.core.samples.SampleItemBase
 method), 167
`__getnewargs__()` (fastr.core.target.SystemUsageInfo
 method), 172
`__getstate__()` (fastr.__init__.ConstantNode method), 74
`__getstate__()` (fastr.__init__.Link method), 69
`__getstate__()` (fastr.__init__.Network method), 66
`__getstate__()` (fastr.__init__.Node method), 72
`__getstate__()` (fastr.__init__.SinkNode method), 76
`__getstate__()` (fastr.__init__.SourceNode method), 75
`__getstate__()` (fastr.core.inputoutput.BaseInputOutput
 method), 129
`__getstate__()` (fastr.core.inputoutput.Input method), 131
`__getstate__()` (fastr.core.inputoutput.Output method),
 134
`__getstate__()` (fastr.core.inputoutput.SubInput method),
 137
`__getstate__()` (fastr.core.inputoutput.SubOutput
 method), 139
`__getstate__()` (fastr.core.interface.Interface method), 140
`__getstate__()` (fastr.core.link.Link method), 146
`__getstate__()` (fastr.core.network.Network method), 149
`__getstate__()` (fastr.core.node.ConstantNode method),
 152
`__getstate__()` (fastr.core.node.MacroNode method), 154
`__getstate__()` (fastr.core.node.Node method), 155
`__getstate__()` (fastr.core.node.SinkNode method), 157
`__getstate__()` (fastr.core.node.SourceNode method), 158
`__getstate__()` (fastr.core.pluginmanager.plugin_option_type
 method), 162
`__getstate__()` (fastr.core.samples.SampleValue method),
 169
`__getstate__()` (fastr.core.serializable.Serializable
 method), 170
`__getstate__()` (fastr.core.target.SystemUsageInfo
 method), 172
`__getstate__()` (fastr.core.tool.Tool method), 174
`__getstate__()` (fastr.core.updateable.Updateable
 method), 177
`__getstate__()` (fastr.datatypes.BaseDataType method),
 79
`__getstate__()` (fastr.datatypes.Deferred method), 82
`__getstate__()` (fastr.execution.inputoutputrun.InputRun
 method), 193
`__getstate__()` (fastr.execution.inputoutputrun.OutputRun
 method), 195
`__getstate__()` (fastr.execution.inputoutputrun.SubInputRun
 method), 199
`__getstate__()` (fastr.execution.inputoutputrun.SubOutputRun
 method), 200
`__getstate__()` (fastr.execution.job.Job method), 202
`__getstate__()` (fastr.execution.linkrun.LinkRun method),
 210
`__getstate__()` (fastr.execution.macronoderun.MacroNodeRun
 method), 212
`__getstate__()` (fastr.execution.networkrun.NetworkRun
 method), 214
`__getstate__()` (fastr.execution.noderun.NodeRun
 method), 216
`__getstate__()` (fastr.execution.sinknoderun.SinkNodeRun
 method), 219
`__getstate__()` (fastr.execution.sourcenoderun.ConstantNodeRun
 method), 221
`__getstate__()` (fastr.execution.sourcenoderun.SourceNodeRun
 method), 220
`__getstate__()` (fastr.plugins.FastrInterface method), 100
`__getstate__()` (fastr.plugins.FlowInterface method), 102
`__getstate__()` (fastr.plugins.NipypeInterface method),
 106
`__iadd__()` (fastr.configmanager.EmptyDefault method),
 78
`__init__()` (fastr.__init__.ConstantNode method), 74
`__init__()` (fastr.__init__.Link method), 70
`__init__()` (fastr.__init__.Network method), 66
`__init__()` (fastr.__init__.Node method), 72
`__init__()` (fastr.__init__.SinkNode method), 76
`__init__()` (fastr.__init__.SourceNode method), 75
`__init__()` (fastr.configmanager.Config method), 77
`__init__()` (fastr.configmanager.EmptyDefault method),

78
 __init__() (fastr.core.basemanager.BaseManager method), 117
 __init__() (fastr.core.baseplugin.BasePlugin method), 118
 __init__() (fastr.core.datatypemanager.DataTypeManager method), 120
 __init__() (fastr.core.dimension.Dimension method), 122
 __init__() (fastr.core.inputgroup.InputGroup method), 124
 __init__() (fastr.core.inputgroupcombiner.BaseInputGroupCombiner method), 126
 __init__() (fastr.core.inputgroupcombiner.MergingInputGroupCombiner) (fastr.datatypes.BaseDataType method), 79
 __init__() (fastr.datatypes.DataType method), 81
 __init__() (fastr.core.inputoutput.BaseInput method), 128
 __init__() (fastr.core.inputoutput.BaseInputOutput method), 129
 __init__() (fastr.core.inputoutput.BaseOutput method), 130
 __init__() (fastr.core.inputoutput.Input method), 131
 __init__() (fastr.core.inputoutput.Output method), 134
 __init__() (fastr.core.inputoutput.SourceOutput method), 136
 __init__() (fastr.core.inputoutput.SubInput method), 137
 __init__() (fastr.core.inputoutput.SubOutput method), 139
 __init__() (fastr.core.interface.InterfacePluginManager method), 141
 __init__() (fastr.core.interface.InterfaceResult method), 141
 __init__() (fastr.core.ioplugin.IOPlugin method), 142
 __init__() (fastr.core.ioplugin.IOPluginManager method), 144
 __init__() (fastr.core.link.Link method), 146
 __init__() (fastr.core.network.Network method), 149
 __init__() (fastr.core.node.ConstantNode method), 152
 __init__() (fastr.core.node.FlowNode method), 153
 __init__() (fastr.core.node.MacroNode method), 154
 __init__() (fastr.core.node.Node method), 155
 __init__() (fastr.core.node.SinkNode method), 157
 __init__() (fastr.core.node.SourceNode method), 158
 __init__() (fastr.core.objectmanager.ObjectManager method), 160
 __init__() (fastr.core.pluginmanager.BasePluginManager method), 160
 __init__() (fastr.core.pluginmanager.LazyModule method), 161
 __init__() (fastr.core.pluginmanager.PluginManager method), 161
 __init__() (fastr.core.pluginmanager.PluginSubManager method), 162
 __init__() (fastr.core.pluginmanager.PluginsView method), 162
 __init__() (fastr.core.provenance.Provenance method), 163
 __init__() (fastr.core.samples.SampleCollection method), 165
 __init__() (fastr.core.samples.SampleValue method), 169
 __init__() (fastr.core.target.ProcessUsageCollection method), 172
 __init__() (fastr.core.target.TargetManager method), 173
 __init__() (fastr.core.tool.Tool method), 174
 __init__() (fastr.core.updateable.Updateable method), 177
 __init__() (fastr.datatypes.BaseDataType method), 79
 __init__() (fastr.datatypes.DataType method), 81
 __init__() (fastr.datatypes.Deferred method), 82
 __init__() (fastr.datatypes.EnumType method), 83
 __init__() (fastr.datatypes.TypeGroup method), 87
 __init__() (fastr.datatypes.URLType method), 87
 __init__() (fastr.datatypes.ValueType method), 88
 __init__() (fastr.exceptions.FastrError method), 90
 __init__() (fastr.exceptions.FastrExecutableNotFoundError method), 90
 __init__() (fastr.exceptions.FastrSerializationError method), 93
 __init__() (fastr.execution.environmentmodules.EnvironmentModules method), 186
 __init__() (fastr.execution.executionpluginmanager.ExecutionPlugin method), 189
 __init__() (fastr.execution.executionpluginmanager.ExecutionPluginManager method), 190
 __init__() (fastr.execution.inputoutputrun.BaseInputRun method), 192
 __init__() (fastr.execution.inputoutputrun.InputRun method), 193
 __init__() (fastr.execution.inputoutputrun.OutputRun method), 195
 __init__() (fastr.execution.inputoutputrun.SourceOutputRun method), 197
 __init__() (fastr.execution.inputoutputrun.SubInputRun method), 199
 __init__() (fastr.execution.inputoutputrun.SubOutputRun method), 200
 __init__() (fastr.execution.job.InlineJob method), 202
 __init__() (fastr.execution.job.Job method), 202
 __init__() (fastr.execution.job.JobState method), 207
 __init__() (fastr.execution.job.SinkJob method), 208
 __init__() (fastr.execution.linkrun.LinkRun method), 210
 __init__() (fastr.execution.macronoderun.MacroNodeRun method), 212
 __init__() (fastr.execution.networkchunker.DefaultNetworkChunker method), 213
 __init__() (fastr.execution.networkrun.NetworkRun method), 215
 __init__() (fastr.execution.noderun.NodeRun method), 216
 __init__() (fastr.execution.sinknoderun.SinkNodeRun

method), 219
`__init__()` (`fastr.execution.sourcenoderun.ConstantNodeRun` method), 222
`__init__()` (`fastr.execution.sourcenoderun.SourceNodeRun` method), 220
`__init__()` (`fastr.plugins.BlockingExecution` method), 96
`__init__()` (`fastr.plugins.CommaSeperatedValueFile` method), 97
`__init__()` (`fastr.plugins.DRMAAExecution` method), 97
`__init__()` (`fastr.plugins.DockerTarget` method), 98
`__init__()` (`fastr.plugins.FastrInterface` method), 100
`__init__()` (`fastr.plugins.FileSystem` method), 101
`__init__()` (`fastr.plugins.FlowInterface` method), 103
`__init__()` (`fastr.plugins.LinearExecution` method), 103
`__init__()` (`fastr.plugins.LocalBinaryTarget` method), 105
`__init__()` (`fastr.plugins.NipypeInterface` method), 106
`__init__()` (`fastr.plugins.Null` method), 106
`__init__()` (`fastr.plugins.ProcessPoolExecution` method), 107
`__init__()` (`fastr.plugins.RQExecution` method), 107
`__init__()` (`fastr.plugins.Reference` method), 108
`__init__()` (`fastr.plugins.S3Filesystem` method), 108
`__init__()` (`fastr.plugins.StrongrExecution` method), 109
`__init__()` (`fastr.plugins.VirtualFileSystem` method), 110
`__init__()` (`fastr.plugins.VirtualFileSystemRegularExpression` method), 112
`__init__()` (`fastr.plugins.VirtualFileSystemValueList` method), 113
`__init__()` (`fastr.plugins.XNATStorage` method), 115
`__init__()` (`fastr.utils.classproperty.ClassPropertyDescriptor` method), 226
`__init__()` (`fastr.utils.filesynchelperFileSyncHelper` method), 228
`__init__()` (`fastr.utils.jsonschemasparser.FastrRefResolver` method), 229
`__init__()` (`fastr.utils.pim_publisher.PimPublisher` method), 231
`__init__()` (`fastr.utils.schematatable.SchemaPrinter` method), 232
`__init__()` (`fastr.web.api.ObjectUrl` method), 238
`__init__()` (`fastr.web.api.Run` method), 238
`__init__()` (`fastr.web.api.SubUrl` method), 239
`__iter__()` (`fastr.core.basemanager.BaseManager` method), 117
`__iter__()` (`fastr.core.inputgroupcombiner.BaseInputGroupCombiner` method), 126
`__iter__()` (`fastr.core.inputoutput.BaseInputOutput` method), 129
`__iter__()` (`fastr.core.ioplugin.IOPluginManager` method), 144
`__iter__()` (`fastr.core.pluginmanager.PluginsView` method), 162
`__iter__()` (`fastr.core.samples.HasSamples` method), 164
`__iter__()` (`fastr.core.samples.SampleCollection` method), 165
`__keytransform__()` (`fastr.core.samples.SampleValue` method), 169
`__keytransform__()` (`fastr.core.basemanager.BaseManager` method), 117
`__keytransform__()` (`fastr.core.datatypemanager.DataTypeManager` method), 120
`__keytransform__()` (`fastr.core.ioplugin.IOPluginManager` method), 144
`__keytransform__()` (`fastr.core.objectmanager.ObjectManager` method), 160
`__len__()` (`fastr.core.basemanager.BaseManager` method), 117
`__len__()` (`fastr.core.inputoutput.SubOutput` method), 139
`__len__()` (`fastr.core.pluginmanager.PluginsView` method), 162
`__len__()` (`fastr.core.samples.SampleCollection` method), 166
`__len__()` (`fastr.core.samples.SampleValue` method), 169
`__len__()` (`fastr.core.target.ProcessUsageCollection` method), 172
`__len__()` (`fastr.execution.inputoutputrun.SubOutputRun` method), 201
`__lshift__()` (`fastr.core.inputoutput.BaseInput` method), 128
`__metaclass__` (`fastr.__init__.Node` attribute), 72
`__metaclass__` (`fastr.core.basemanager.BaseManager` attribute), 117
`__metaclass__` (`fastr.core.baseplugin.BasePlugin` attribute), 118
`__metaclass__` (`fastr.core.dimension.HasDimensions` attribute), 123
`__metaclass__` (`fastr.core.inputgroup.InputGroup` attribute), 124
`__metaclass__` (`fastr.core.inputgroupcombiner.BaseInputGroupCombiner` attribute), 126
`__metaclass__` (`fastr.core.interface.Interface` attribute), 141
`__metaclass__` (`fastr.core.ioplugin.IOPlugin` attribute), 142
`__metaclass__` (`fastr.core.node.Node` attribute), 155
`__metaclass__` (`fastr.core.samples.HasSamples` attribute), 164
`__metaclass__` (`fastr.core.target.Target` attribute), 173
`__metaclass__` (`fastr.core.updateable.Updateable` attribute), 177
`__metaclass__` (`fastr.execution.noderun.NodeRun` attribute), 217
`__module__` (`fastr.__init__.ConstantNode` attribute), 74
`__module__` (`fastr.__init__.Link` attribute), 70
`__module__` (`fastr.__init__.Network` attribute), 66
`__module__` (`fastr.__init__.Node` attribute), 72
`__module__` (`fastr.__init__.SinkNode` attribute), 76
`__module__` (`fastr.__init__.SourceNode` attribute), 75

__module__ (fastr.configmanager.Config attribute), 77
__module__ (fastr.configmanager.EmptyDefault attribute), 78
__module__ (fastr.core.basemanager.BaseManager attribute), 117
__module__ (fastr.core.baseplugin.BasePlugin attribute), 118
__module__ (fastr.core.baseplugin.Plugin attribute), 119
__module__ (fastr.core.baseplugin.PluginMeta attribute), 119
__module__ (fastr.core.baseplugin.PluginState attribute), 119
__module__ (fastr.core.datatypemanager.DataTypeManager attribute), 120
__module__ (fastr.core.dimension.Dimension attribute), 122
__module__ (fastr.core.dimension.ForwardsDimensions attribute), 123
__module__ (fastr.core.dimension.HasDimensions attribute), 123
__module__ (fastr.core.inputgroup.InputGroup attribute), 124
__module__ (fastr.core.inputgroupcombiner.BaseInputGroup attribute), 126
__module__ (fastr.core.inputgroupcombiner.DefaultInputGroup attribute), 127
__module__ (fastr.core.inputgroupcombiner.MergingInputGroup attribute), 127
__module__ (fastr.core.inputoutput.AdvancedFlowOutput attribute), 128
__module__ (fastr.core.inputoutput.BaseInput attribute), 128
__module__ (fastr.core.inputoutput.BaseInputOutput attribute), 129
__module__ (fastr.core.inputoutput.BaseOutput attribute), 130
__module__ (fastr.core.inputoutput.Input attribute), 131
__module__ (fastr.core.inputoutput.MacroOutput attribute), 133
__module__ (fastr.core.inputoutput.Output attribute), 134
__module__ (fastr.core.inputoutput.SourceOutput attribute), 136
__module__ (fastr.core.inputoutput.SubInput attribute), 137
__module__ (fastr.core.inputoutput.SubOutput attribute), 139
__module__ (fastr.core.interface.InputSpec attribute), 140
__module__ (fastr.core.interface.Interface attribute), 141
__module__ (fastr.core.interface.InterfacePluginManager attribute), 141
__module__ (fastr.core.interface.InterfaceResult attribute), 141
__module__ (fastr.core.interface.OutputSpec attribute), 142
__module__ (fastr.core.ioplugin.IOPlugin attribute), 142
__module__ (fastr.core.ioplugin.IOPluginManager attribute), 144
__module__ (fastr.core.link.Link attribute), 147
__module__ (fastr.core.network.Network attribute), 149
__module__ (fastr.core.networkmanager.NetworkManager attribute), 152
__module__ (fastr.core.node.AdvancedFlowNode attribute), 152
__module__ (fastr.core.node.ConstantNode attribute), 153
__module__ (fastr.core.node.FlowNode attribute), 154
__module__ (fastr.core.node.InputDict attribute), 154
__module__ (fastr.core.node.MacroNode attribute), 154
__module__ (fastr.core.node.Node attribute), 155
__module__ (fastr.core.node.OutputDict attribute), 157
__module__ (fastr.core.node.SinkNode attribute), 158
__module__ (fastr.core.node.SourceNode attribute), 159
__module__ (fastr.core.objectmanager.ObjectManager attribute), 160
__module__ (fastr.core.pluginmanager.BasePluginManager attribute), 161
__module__ (fastr.core.pluginmanager.LazyModule attribute), 161
__module__ (fastr.core.pluginmanager.PluginManager attribute), 161
__module__ (fastr.core.pluginmanager.PluginSubManager attribute), 162
__module__ (fastr.core.pluginmanager.PluginsView attribute), 162
__module__ (fastr.core.pluginmanager.plugin_option_type attribute), 162
__module__ (fastr.core.provenance.Provenance attribute), 163
__module__ (fastr.core.samples.ContainsSamples attribute), 164
__module__ (fastr.core.samples.HasSamples attribute), 164
__module__ (fastr.core.samples.SampleBaseId attribute), 164
__module__ (fastr.core.samples.SampleCollection attribute), 166
__module__ (fastr.core.samples.SampleId attribute), 166
__module__ (fastr.core.samples.SampleIndex attribute), 166
__module__ (fastr.core.samples.SampleItem attribute), 167
__module__ (fastr.core.samples.SampleItemBase attribute), 167
__module__ (fastr.core.samples.SamplePayload attribute), 169
__module__ (fastr.core.samples.SampleValue attribute), 169

__module__(fastr.core.serializable.PassThroughSerializer attribute), 170
 __module__(fastr.core.serializable.Serializable attribute), 170
 __module__(fastr.core.target.ProcessUsageCollection attribute), 172
 __module__(fastr.core.target.SystemUsageInfo attribute), 172
 __module__(fastr.core.target.Target attribute), 173
 __module__(fastr.core.target.TargetManager attribute), 174
 __module__(fastr.core.tool.Tool attribute), 174
 __module__(fastr.core.toolmanager.ToolManager attribute), 176
 __module__(fastr.core.updateable.Updateable attribute), 177
 __module__(fastr.core.updateable.UpdateableMeta attribute), 178
 __module__(fastr.core.version.Version attribute), 179
 __module__(fastr.datatypes.AnalyzeImageFile attribute), 79
 __module__(fastr.datatypes.AnyFile attribute), 79
 __module__(fastr.datatypes.AnyType attribute), 79
 __module__(fastr.datatypes.BaseDataType attribute), 80
 __module__(fastr.datatypes.Boolean attribute), 81
 __module__(fastr.datatypes.DataType attribute), 81
 __module__(fastr.datatypes.Deferred attribute), 82
 __module__(fastr.datatypes.Directory attribute), 83
 __module__(fastr.datatypes.EnumType attribute), 83
 __module__(fastr.datatypes.FilePrefix attribute), 83
 __module__(fastr.datatypes.Float attribute), 84
 __module__(fastr.datatypes.ITKImageFile attribute), 84
 __module__(fastr.datatypes.Int attribute), 84
 __module__(fastr.datatypes.JsonFile attribute), 84
 __module__(fastr.datatypes.MetaImageFile attribute), 85
 __module__(fastr.datatypes.NiftiImageFile attribute), 85
 __module__(fastr.datatypes.NiftiImageFileCompressed attribute), 85
 __module__(fastr.datatypes.NiftiImageFileUncompressed attribute), 85
 __module__(fastr.datatypes.Number attribute), 86
 __module__(fastr.datatypes.ProvNFile attribute), 86
 __module__(fastr.datatypes.String attribute), 86
 __module__(fastr.datatypes.TifImageFile attribute), 86
 __module__(fastr.datatypes.TxtFile attribute), 86
 __module__(fastr.datatypes.TypeGroup attribute), 87
 __module__(fastr.datatypes.URLType attribute), 87
 __module__(fastr.datatypes.UnsignedInt attribute), 88
 __module__(fastr.datatypes.ValueType attribute), 88
 __module__(fastr.exceptions.FastrAttributeError attribute), 89
 __module__(fastr.exceptions.FastrCannotChangeAttributeError attribute), 89
 __module__(fastr.exceptions.FastrCardinalityError attribute), 89
 __module__(fastr.exceptions.FastrCollectorError attribute), 89
 __module__(fastr.exceptions.FastrDataTypeFileNotReadable attribute), 89
 __module__(fastr.exceptions.FastrDataTypeMismatchError attribute), 89
 __module__(fastr.exceptions.FastrDataTypeNotAvailableError attribute), 89
 __module__(fastr.exceptions.FastrDataTypeNotInstantiableError attribute), 89
 __module__(fastr.exceptions.FastrDataTypeValueError attribute), 90
 __module__(fastr.exceptions.FastrError attribute), 90
 __module__(fastr.exceptions.FastrErrorInSubprocess attribute), 90
 __module__(fastr.exceptions.FastrExecutableNotFoundError attribute), 90
 __module__(fastr.exceptions.FastrExecutionError attribute), 90
 __module__(fastr.exceptions.FastrIOError attribute), 90
 __module__(fastr.exceptions.FastrImportError attribute), 91
 __module__(fastr.exceptions.FastrIndexError attribute), 91
 __module__(fastr.exceptions.FastrIndexNonexistent attribute), 91
 __module__(fastr.exceptions.FastrKeyError attribute), 91
 __module__(fastr.exceptions.FastrLookupError attribute), 91
 __module__(fastr.exceptions.FastrMountUnknownError attribute), 91
 __module__(fastr.exceptions.FastrNetworkMismatchError attribute), 91
 __module__(fastr.exceptions.FastrNetworkUnknownError attribute), 91
 __module__(fastr.exceptions.FastrNoValidTargetException attribute), 91
 __module__(fastr.exceptions.FastrNodeAlreadyPreparedError attribute), 92
 __module__(fastr.exceptions.FastrNodeNotPreparedError attribute), 92
 __module__(fastr.exceptions.FastrNodeNotValidError attribute), 92
 __module__(fastr.exceptions.FastrNotExecutableError attribute), 92
 __module__(fastr.exceptions.FastrNotImplementedError attribute), 92
 __module__(fastr.exceptions.FastrOSSError attribute), 92
 __module__(fastr.exceptions.FastrObjectUnknownError attribute), 92
 __module__(fastr.exceptions.FastrOptionalModuleNotFoundError)

attribute), 92
__module__(fastr.exceptions.FastrOutputValidationAttribute), 92
__module__(fastr.exceptions.FastrParentMismatchAttribute), 93
__module__(fastr.exceptions.FastrPluginCapabilityNotImplementedAttribute), 93
__module__(fastr.exceptions.FastrPluginNotAvailableAttribute), 93
__module__(fastr.exceptions.FastrPluginNotLoadedAttribute), 93
__module__(fastr.exceptions.FastrResultFileNotFoundException), 93
__module__(fastr.exceptions.FastrSerializationErrorAttribute), 93
__module__(fastr.exceptions.FastrSerializationIgnoreDefaultAttribute), 93
__module__(fastr.exceptions.FastrSerializationInvalidDataAttribute), 94
__module__(fastr.exceptions.FastrSerializationMethodAttribute), 94
__module__(fastr.exceptions.FastrSinkDataUnavailableAttribute), 94
__module__(fastr.exceptions.FastrSizeInvalidAttribute), 94
__module__(fastr.exceptions.FastrSizeMismatchAttribute), 94
__module__(fastr.exceptions.FastrSizeUnknownAttribute), 94
__module__(fastr.exceptions.FastrSourceDataUnavailableAttribute), 94
__module__(fastr.exceptions.FastrStateErrorAttribute), 94
__module__(fastr.exceptions.FastrSubprocessNotFinishedAttribute), 94
__module__(fastr.exceptions.FastrToolNotFoundError), 95
__module__(fastr.exceptions.FastrToolTargetNotFoundError), 95
__module__(fastr.exceptions.FastrToolUnknownErrorAttribute), 95
__module__(fastr.exceptions.FastrTypeErrorAttribute), 95
__module__(fastr.exceptions.FastrUnknownURLSchemeAttribute), 95
__module__(fastr.exceptions.FastrValueErrorAttribute), 95
__module__(fastr.exceptions.FastrVersionInvalidErrorAttribute), 95
__module__(fastr.exceptions.FastrVersionMismatchErrorAttribute), 95
__module__(fastr.execution.environmentmodules.EnvironmentModule), 186
__module__(fastr.execution.environmentmodules.ModuleSystem), 186
attribute), 187
__module__(fastr.execution.executionpluginmanager.ExecutionPluginAttribute), 189
__module__(fastr.execution.executionpluginmanager.ExecutionPluginManagerAttribute), 190
__module__(fastr.execution.executionpluginmanager.JobActionAttribute), 190
__module__(fastr.execution.flownoderun.AdvancedFlowNodeRunAttribute), 191
__module__(fastr.execution.flownoderun.FlowNodeRunAttribute), 191
__module__(fastr.execution.inputoutputrun.AdvancedFlowOutputRunAttribute), 192
__module__(fastr.execution.inputoutputrun.BaseInputRunAttribute), 192
__module__(fastr.execution.inputoutputrun.InputRunAttribute), 193
__module__(fastr.execution.inputoutputrun.MacroOutputRunAttribute), 194
__module__(fastr.execution.inputoutputrun.OutputRunAttribute), 195
__module__(fastr.execution.inputoutputrun.SourceOutputRunAttribute), 198
__module__(fastr.execution.inputoutputrun.SubInputRunAttribute), 199
__module__(fastr.execution.inputoutputrun.SubOutputRunAttribute), 201
__module__(fastr.execution.job.InlineJobAttribute), 202
__module__(fastr.execution.job.JobAttribute), 203
__module__(fastr.execution.job.JobStateAttribute), 208
__module__(fastr.execution.job.SinkJobAttribute), 208
__module__(fastr.execution.job.SourceJobAttribute), 209
__module__(fastr.execution.linkrun.LinkRunAttribute), 211
__module__(fastr.execution.macronoderun.MacroNodeRunAttribute), 212
__module__(fastr.execution.networkanalyzer.DefaultNetworkAnalyzerAttribute), 213
__module__(fastr.execution.networkanalyzer.NetworkAnalyzerAttribute), 213
__module__(fastr.execution.networkchunker.DefaultNetworkChunkerAttribute), 213
__module__(fastr.execution.networkchunker.NetworkChunkerAttribute), 214
__module__(fastr.execution.networkrun.NetworkRunAttribute), 215
__module__(fastr.execution.noderun.NodeRunAttribute), 217
__module__(fastr.execution.sinknoderun.SinkNodeRunAttribute), 219
__module__(fastr.execution.sourcenoderun.ConstantNodeRunAttribute), 222
__module__(fastr.execution.sourcenoderun.SourceNodeRunAttribute), 222

attribute), 221
`__module__` (fastr.plugins.BlockingExecution attribute), 96
`__module__` (fastr.plugins.CommaSepreatedValueFile attribute), 97
`__module__` (fastr.plugins.CrossValidation attribute), 97
`__module__` (fastr.plugins.DRMAAExecution attribute), 97
`__module__` (fastr.plugins.DockerTarget attribute), 98
`__module__` (fastr.plugins.FastrInterface attribute), 100
`__module__` (fastr.plugins.FileSystem attribute), 101
`__module__` (fastr.plugins.FlowInterface attribute), 103
`__module__` (fastr.plugins.LinearExecution attribute), 103
`__module__` (fastr.plugins.LocalBinaryTarget attribute), 105
`__module__` (fastr.plugins.NipypeInterface attribute), 106
`__module__` (fastr.plugins.Null attribute), 106
`__module__` (fastr.plugins.ProcessPoolExecution attribute), 107
`__module__` (fastr.plugins.RQExecution attribute), 107
`__module__` (fastr.plugins.Reference attribute), 108
`__module__` (fastr.plugins.S3Filesystem attribute), 108
`__module__` (fastr.plugins.StrongrExecution attribute), 109
`__module__` (fastr.plugins.VirtualFileSystem attribute), 110
`__module__` (fastr.plugins.VirtualFileSystemRegularExpression) new
`__module__` (fastr.plugins.VirtualFileSystemValueList attribute), 113
`__module__` (fastr.plugins.XNATStorage attribute), 115
`__module__` (fastr.utils.classproperty.ClassPropertyDescriptor attribute), 226
`__module__` (fastr.utils.filesynchelperFileSyncHelper attribute), 228
`__module__` (fastr.utils.jsonschemaparser.FastrRefResolver attribute), 229
`__module__` (fastr.utils.pim_publisher.PimPublisher attribute), 231
`__module__` (fastr.utils.schematatable.SchemaPrinter attribute), 232
`__module__` (fastr.web.api.NetworkApi attribute), 238
`__module__` (fastr.web.api.NetworkListApi attribute), 238
`__module__` (fastr.web.api.ObjectUrl attribute), 238
`__module__` (fastr.web.api.Run attribute), 238
`__module__` (fastr.web.api.RunApi attribute), 239
`__module__` (fastr.web.api.RunListApi attribute), 239
`__module__` (fastr.web.api.StatusApi attribute), 239
`__module__` (fastr.web.api.SubUrl attribute), 239
`__module__` (fastr.web.api.ToolApi attribute), 239
`__module__` (fastr.web.api.ToolListApi attribute), 240
`__ne__()` (fastr.__init__.Network method), 66
`__ne__()` (fastr.core.dimension.Dimension method), 122
`__ne__()` (fastr.core.network.Network method), 149
`__ne__()` (fastr.datatypes.BaseDataType method), 80
`__ne__()` (fastr.execution.networkrun.NetworkRun method), 215
`__new__()` (fastr.core.baseplugin.PluginState static method), 120
`__new__()` (fastr.core.interface.InputSpec static method), 140
`__new__()` (fastr.core.interface.OutputSpec static method), 142
`__new__()` (fastr.core.pluginmanager.plugin_option_type static method), 162
`__new__()` (fastr.core.samples.SampleBaseId static method), 164
`__new__()` (fastr.core.samples.SampleItem static method), 167
`__new__()` (fastr.core.samples.SampleItemBase static method), 167
`__new__()` (fastr.core.samples.SamplePayload static method), 169
`__new__()` (fastr.core.target.SystemUsageInfo static method), 172
`__new__()` (fastr.core.updateable.UpdateableMeta static method), 178
`__new__()` (fastr.core.version.Version static method), 179
`__new__()` (fastr.datatypes.TypeGroup static method), 87
`__new__()` (fastr.execution.environmentmodules.ModuleSystem static method), 187
`__new__()` (fastr.execution.executionpluginmanager.JobAction static method), 190
`__new__()` (fastr.execution.job.JobState static method), 208
`__radd__()` (fastr.configmanager.EmptyDefault method), 78
`__radd__()` (fastr.core.samples.SampleBaseId method), 164
`__radd__()` (fastr.core.samples.SampleValue method), 169
`__reduce_ex__()` (fastr.core.baseplugin.PluginState method), 120
`__reduce_ex__()` (fastr.datatypes.BaseDataType method), 80
`__reduce_ex__()` (fastr.datatypes.EnumType method), 83
`__reduce_ex__()` (fastr.execution.environmentmodules.ModuleSystem method), 187
`__reduce_ex__()` (fastr.execution.executionpluginmanager.JobAction method), 190
`__reduce_ex__()` (fastr.execution.job.JobState method), 208
`__repr__()` (fastr.__init__.Link method), 70
`__repr__()` (fastr.__init__.Network method), 66
`__repr__()` (fastr.__init__.Node method), 72
`__repr__()` (fastr.configmanager.Config method), 77

`__repr__()` (fastr.core.basemanager.BaseManager method), 117
`__repr__()` (fastr.core.baseplugin.BasePlugin method), 118
`__repr__()` (fastr.core.baseplugin.PluginMeta method), 119
`__repr__()` (fastr.core.baseplugin.PluginState method), 120
`__repr__()` (fastr.core.dimension.Dimension method), 122
`__repr__()` (fastr.core.inputoutput.BaseInputOutput method), 129
`__repr__()` (fastr.core.link.Link method), 147
`__repr__()` (fastr.core.network.Network method), 149
`__repr__()` (fastr.core.node.Node method), 155
`__repr__()` (fastr.core.pluginmanager.LazyModule method), 161
`__repr__()` (fastr.core.pluginmanager.plugin_option_type method), 162
`__repr__()` (fastr.core.samples.SampleBaseId method), 165
`__repr__()` (fastr.core.samples.SampleCollection method), 166
`__repr__()` (fastr.core.samples.SampleIndex method), 166
`__repr__()` (fastr.core.samples.SampleItemBase method), 168
`__repr__()` (fastr.core.samples.SampleValue method), 169
`__repr__()` (fastr.core.target.SystemUsageInfo method), 172
`__repr__()` (fastr.core.tool.Tool method), 174
`__repr__()` (fastr.core.version.Version method), 180
`__repr__()` (fastr.datatypes.BaseDataType method), 80
`__repr__()` (fastr.datatypes.Deferred method), 82
`__repr__()` (fastr.exceptions.FastrSerializationError method), 93
`__repr__()` (fastr.execution.environmentmodules.Environment Modules method), 186
`__repr__()` (fastr.execution.environmentmodules.ModuleSystem) setstate__() (fastr.core.inputoutput.Output method), 134
`__repr__()` (fastr.execution.executionpluginmanager.JobAction) setstate__() (fastr.core.inputoutput.SubInput method), 137
`__repr__()` (fastr.execution.executionpluginmanager.JobAction) setstate__() (fastr.core.inputoutput.SubOutput method), 139
`__repr__()` (fastr.execution.job.Job method), 203
`__repr__()` (fastr.execution.job.JobState method), 208
`__repr__()` (fastr.execution.job.SinkJob method), 208
`__repr__()` (fastr.execution.job.SourceJob method), 209
`__repr__()` (fastr.execution.linkrun.LinkRun method), 211
`__repr__()` (fastr.execution.networkrun.NetworkRun method), 215
`__repr__()` (fastr.execution.noderun.NodeRun method), 217
`__rrshift__()` (fastr.core.inputoutput.BaseInput method), 128
`__schema_type__` (fastr.web.api.ObjectUrl attribute), 238
`__schema_type__` (fastr.web.api.SubUrl attribute), 239
`__setitem__()` (fastr.configmanager.EmptyDefault method), 78
`__setitem__()` (fastr.core.basemanager.BaseManager method), 118
`__setitem__()` (fastr.core.inputgroup.InputGroup method), 124
`__setitem__()` (fastr.core.inputoutput.Input method), 131
`__setitem__()` (fastr.core.node.InputDict method), 154
`__setitem__()` (fastr.core.node.OutputDict method), 157
`__setitem__()` (fastr.core.pluginmanager.PluginManager method), 161
`__setitem__()` (fastr.core.pluginmanager.PluginsView method), 162
`__setitem__()` (fastr.core.samples.ContainsSamples method), 164
`__setitem__()` (fastr.core.samples.SampleCollection method), 166
`__setitem__()` (fastr.core.samples.SampleValue method), 169
`__setitem__()` (fastr.execution.inputoutputrun.OutputRun method), 195
`__setitem__()` (fastr.execution.inputoutputrun.SourceOutputRun method), 198
`__setitem__()` (fastr.execution.inputoutputrun.SubOutputRun method), 201
`__setstate__()` (fastr.__init__.ConstantNode method), 74
`__setstate__()` (fastr.__init__.Link method), 70
`__setstate__()` (fastr.__init__.Network method), 66
`__setstate__()` (fastr.__init__.Node method), 72
`__setstate__()` (fastr.__init__.SinkNode method), 76
`__setstate__()` (fastr.__init__.SourceNode method), 75
`__setstate__()` (fastr.core.inputoutput.BaseInputOutput method), 129
`__setstate__()` (fastr.core.inputoutput.Input method), 131
`__setstate__()` (fastr.core.inputoutput.Output method), 134
`__setstate__()` (fastr.core.inputoutput.SubInput method), 137
`__setstate__()` (fastr.core.inputoutput.SubOutput method), 139
`__setstate__()` (fastr.core.interface.Interface method), 141
`__setstate__()` (fastr.core.link.Link method), 147
`__setstate__()` (fastr.core.network.Network method), 149
`__setstate__()` (fastr.core.node.ConstantNode method), 153
`__setstate__()` (fastr.core.node.MacroNode method), 154
`__setstate__()` (fastr.core.node.Node method), 156
`__setstate__()` (fastr.core.node.SinkNode method), 158
`__setstate__()` (fastr.core.node.SourceNode method), 159
`__setstate__()` (fastr.core.samples.SampleValue method), 169
`__setstate__()` (fastr.core.tool.Tool method), 174
`__setstate__()` (fastr.core.updateable.Updateable method),

__setstate__(fastr.datatypes.BaseDataType method), 80
 __setstate__(fastr.datatypes.Deferred method), 82
 __setstate__(fastr.execution.inputoutputrun.InputRun method), 193
 __setstate__(fastr.execution.inputoutputrun.OutputRun method), 195
 __setstate__(fastr.execution.inputoutputrun.SubInputRun method), 199
 __setstate__(fastr.execution.inputoutputrun.SubOutputRun method), 201
 __setstate__(fastr.execution.job.Job method), 203
 __setstate__(fastr.execution.linkrun.LinkRun method), 211
 __setstate__(fastr.execution.macronoderun.MacroNodeRun method), 212
 __setstate__(fastr.execution.networkrun.NetworkRun method), 215
 __setstate__(fastr.execution.noderun.NodeRun method), 217
 __setstate__(fastr.execution.sinknoderun.SinkNodeRun method), 219
 __setstate__(fastr.execution.sourcenoderun.ConstantNodeRun method), 222
 __setstate__(fastr.execution.sourcenoderun.SourceNodeRun method), 221
 __setstate__(fastr.plugins.FastrInterface method), 100
 __setstate__(fastr.plugins.FlowInterface method), 103
 __setstate__(fastr.plugins.NipypeInterface method), 106
 __slotnames__(fastr.web.api.ObjectUrl attribute), 238
 __slots__(fastr.core.pluginmanager.plugin_option_type attribute), 163
 __slots__(fastr.core.target.SystemUsageInfo attribute), 172
 __str__(fastr.__init__.Node method), 73
 __str__(fastr.core.baseplugin.BasePlugin method), 118
 __str__(fastr.core.baseplugin.PluginState method), 120
 __str__(fastr.core.inputoutput.Input method), 132
 __str__(fastr.core.inputoutput.Output method), 134
 __str__(fastr.core.inputoutput.SubInput method), 137
 __str__(fastr.core.inputoutput.SubOutput method), 139
 __str__(fastr.core.node.Node method), 156
 __str__(fastr.core.samples.SampleBaseId method), 165
 __str__(fastr.core.samples.SampleIndex method), 166
 __str__(fastr.core.tool.Tool method), 174
 __str__(fastr.core.version.Version method), 180
 __str__(fastr.datatypes.BaseDataType method), 80
 __str__(fastr.datatypes.Boolean method), 81
 __str__(fastr.exceptions.FastrError method), 90
 __str__(fastr.exceptions.FastrExecutableNotFoundError method), 90
 __str__(fastr.exceptions.FastrSerializationError method), 93
 __str__(fastr.execution.environmentmodules.ModuleSystem method), 187
 __str__(fastr.execution.executionpluginmanager.JobAction method), 190
 __str__(fastr.execution.inputoutputrun.InputRun method), 193
 __str__(fastr.execution.inputoutputrun.OutputRun method), 196
 __str__(fastr.execution.inputoutputrun.SubInputRun method), 199
 __str__(fastr.execution.inputoutputrun.SubOutputRun method), 201
 __str__(fastr.execution.job.JobState method), 208
 __str__(fastr.execution.noderun.NodeRun method), 217
 __str__(fastr.utils.schematable.SchemaPrinter method), 232
 __updatefunc__(fastr.core.inputgroup.InputGroup method), 124
 __updatefunc__(fastr.core.updateable.Updateable method), 177
 __updateinprogress__(fastr.core.updateable.Updateable attribute), 177
 __updatetriggers__(fastr.core.inputgroup.InputGroup attribute), 124
 __updatetriggers__(fastr.core.updateable.Updateable attribute), 178
 __updating__(fastr.core.updateable.Updateable attribute), 178
 __weakref__(fastr.configmanager.Config attribute), 77
 __weakref__(fastr.configmanager.EmptyDefault attribute), 78
 __weakref__(fastr.core.baseplugin.BasePlugin attribute), 118
 __weakref__(fastr.core.dimension.Dimension attribute), 122
 __weakref__(fastr.core.dimension.HasDimensions attribute), 123
 __weakref__(fastr.core.interface.InterfaceResult attribute), 141
 __weakref__(fastr.core.pluginmanager.LazyModule attribute), 161
 __weakref__(fastr.core.provenance.Provenance attribute), 163
 __weakref__(fastr.core.serializable.PassThroughSerializer attribute), 170
 __weakref__(fastr.core.serializable.Serializable attribute), 170
 __weakref__(fastr.core.updateable.Updateable attribute), 178
 __weakref__(fastr.exceptions.FastrError attribute), 90
 __weakref__(fastr.exceptions.FastrIOError attribute), 90
 __weakref__(fastr.exceptions.FastrOSError attribute), 92
 __weakref__(fastr.execution.environmentmodules.EnvironmentModules

attribute), 186
`__weakref__` (fastr.execution.networkanalyzer.NetworkAnalyzer attribute), 213
`__weakref__` (fastr.execution.networkchunker.NetworkChunker attribute), 214
`__weakref__` (fastr.utils.classproperty.ClassPropertyDescriptor attribute), 226
`__weakref__` (fastr.utils.pim_publisher.PimPublisher attribute), 231
`__weakref__` (fastr.utils.schematatable.SchemaPrinter attribute), 232
`__weakref__` (fastr.web.api.Run attribute), 238
`_item_extension()` (fastr.core.basemanager.BaseManager method), 116
`_load_item()` (fastr.core.basemanager.BaseManager method), 116

A

`abort()` (fastr.execution.networkrun.NetworkRun method), 215
`abort()` (fastr.web.api.Run method), 238
`abstract` (fastr.plugins.VirtualFileSystem attribute), 110
`action()` (fastr.datatypes.DataType method), 81
`action()` (fastr.datatypes.Directory method), 83
`activity()` (fastr.core.provenance.Provenance method), 163
`add_link()` (fastr.__init__.Network method), 66
`add_link()` (fastr.core.network.Network method), 149
`add_link()` (fastr.Network method), 62
`add_node()` (fastr.__init__.Network method), 67
`add_node()` (fastr.core.network.Network method), 149
`add_node()` (fastr.Network method), 62
`add_parser_doc_link()` (in module fastr.utils.cmd), 235
`add_stepid()` (fastr.__init__.Network method), 67
`add_stepid()` (fastr.core.network.Network method), 149
`AdvancedFlowNode` (class in fastr.core.node), 152
`AdvancedFlowNodeRun` (class in fastr.execution.flownoderun), 191
`AdvancedFlowOutput` (class in fastr.core.inputoutput), 128
`AdvancedFlowOutputRun` (class in fastr.execution.inputoutputrun), 192
`agent()` (fastr.core.provenance.Provenance method), 163
`aggregate()` (fastr.core.target.ProcessUsageCollection method), 172
`analyze_network()` (fastr.execution.networkanalyzer.DefaultNetworkAnalyzer method), 213
`analyze_network()` (fastr.execution.networkanalyzer.NetworkAnalyzer method), 213
`AnalyzeImageFile` (class in fastr.datatypes), 79
`any_of_draft4()` (in module fastr.utils.jsonschemaparser), 229
`AnyFile` (class in fastr.datatypes), 79
`AnyType` (class in fastr.datatypes), 79

append() (fastr.configmanager.EmptyDefault method), 78
`append()` (fastr.core.inputoutput.Input method), 132
`append()` (fastr.core.target.ProcessUsageCollection method), 172
`asdict()` (fastr.configmanager.EmptyDefault method), 78
`list()` (fastr.configmanager.EmptyDefault method), 78
`authors` (fastr.core.tool.Tool attribute), 175
`automatic` (fastr.core.inputoutput.BaseOutput attribute), 130
`automatic` (fastr.execution.inputoutputrun.OutputRun attribute), 196
`avail()` (fastr.execution.environmentmodules.EnvironmentModules method), 186
`avail_modules` (fastr.execution.environmentmodules.EnvironmentModules attribute), 186

B

`BaseDataType` (class in fastr.datatypes), 79
`BaseInput` (class in fastr.core.inputoutput), 128
`BaseInputGroupCombiner` (class in fastr.core.inputgroupcombiner), 126
`BaseInputOutput` (class in fastr.core.inputoutput), 129
`BaseInputRun` (class in fastr.execution.inputoutputrun), 192
`BaseManager` (class in fastr.core.basemanager), 116
`basename()` (in module fastr.data.url), 181
`BaseOutput` (class in fastr.core.inputoutput), 130
`BasePlugin` (class in fastr.core.baseplugin), 118
`BasePluginManager` (class in fastr.core.pluginmanager), 160
`blocking` (fastr.__init__.Node attribute), 73
`blocking` (fastr.core.inputoutput.Output attribute), 134
`blocking` (fastr.core.node.FlowNode attribute), 154
`blocking` (fastr.core.node.Node attribute), 156
`blocking` (fastr.execution.flownoderun.FlowNodeRun attribute), 191
`blocking` (fastr.execution.inputoutputrun.OutputRun attribute), 196
`blocking` (fastr.execution.noderun.NodeRun attribute), 217
`BlockingExecution` (class in fastr.plugins), 95
`Boolean` (class in fastr.datatypes), 81
`build` (fastr.core.version.Version attribute), 180

C

`call_endanalyz()` (fastr.execution.job.Job static method), 203
`calender` (fastr.core.updateable.UpdateableMeta class method), 178
`call_subprocess()` (fastr.plugins.LocalBinaryTarget method), 105
`cancel` (fastr.execution.executionpluginmanager.JobAction attribute), 190

cancel_job() (`fastr.execution.executionpluginmanager.ExecutionPlugin` method), 189
 method), 189
cancelled (`fastr.execution.job.JobState` attribute), 208
CANCELS_DEPENDENCIES
 (`fastr.execution.executionpluginmanager.ExecutionPlugin` attribute), 100
 attribute), 188
CANCELS_DEPENDENCIES
 (`fastr.plugins.DRMAAExecution` attribute), 97
cardinality (`fastr.core.samples.SampleItemBase` attribute), 168
cardinality() (`fastr.__init__.Link` method), 70
cardinality() (`fastr.core.inputoutput.BaseInputOutput` method), 129
cardinality() (`fastr.core.inputoutput.Input` method), 132
cardinality() (`fastr.core.inputoutput.Output` method), 134
cardinality() (`fastr.core.inputoutput.SourceOutput` method), 136
cardinality() (`fastr.core.inputoutput.SubInput` method), 137
cardinality() (`fastr.core.inputoutput.SubOutput` method), 139
cardinality() (`fastr.core.link.Link` method), 147
cardinality() (`fastr.execution.inputoutputrun.InputRun` method), 193
cardinality() (`fastr.execution.inputoutputrun.OutputRun` method), 196
cardinality() (`fastr.execution.inputoutputrun.SourceOutputRun` method), 198
cardinality() (`fastr.execution.inputoutputrun.SubInputRun` method), 199
cardinality() (`fastr.execution.inputoutputrun.SubOutputRun` method), 201
cardinality() (`fastr.execution.linkrun.LinkRun` method), 211
cardinality_from_nargs() (in module `fastr.utils.cmd.extract_argparse`), 235
cast() (`fastr.core.samples.SampleValue` method), 169
check_cardinality() (`fastr.core.inputoutput.BaseInputOutput` method), 130
check_finished() (`fastr.plugins.RQExecution` method), 107
check_finished() (`fastr.plugins.StrongrExecution` method), 109
check_id() (`fastr.__init__.Network` method), 67
check_id() (`fastr.core.network.Network` method), 149
check_id() (`fastr.execution.networkrun.NetworkRun` method), 215
check_input_id() (`fastr.plugins.FastrInterface` method), 100
check_job_requirements()
 (`fastr.execution.executionpluginmanager.ExecutionPlugin` method), 189
check_job_status() (`fastr.execution.executionpluginmanager.ExecutionPlugin` method), 100
check_network() (in module `fastr.utils.cmd.test`), 236
check_networks() (in module `fastr.utils.cmd.test`), 236
check_output_id() (`fastr.plugins.FastrInterface` method), 100
check_tool() (in module `fastr.utils.cmd.test`), 236
check_tools() (in module `fastr.utils.cmd.test`), 236
checksum() (`fastr.datatypes.BaseDataType` method), 80
checksum() (`fastr.datatypes.Deferred` method), 82
checksum() (`fastr.datatypes.FilePrefix` method), 83
checksum() (`fastr.datatypes.JsonFile` method), 84
checksum() (`fastr.datatypes.MetaImageFile` method), 85
checksum() (`fastr.datatypes.URLType` method), 87
checksum() (in module `fastr.utils.checksum`), 224
checksum_directory() (in module `fastr.utils.checksum`), 225
chunck_network() (`fastr.execution.networkchunker.DefaultNetworkChunker` method), 213
chunck_network() (`fastr.execution.networkchunker.NetworkChunker` method), 214
cite (`fastr.core.tool.Tool` attribute), 175
classproperty() (in module `fastr.utils.classproperty`), 226
ClassPropertyDescriptor (class in `fastr.utils.classproperty`), 226
cleanup() (`fastr.core.baseplugin.BasePlugin` method), 119
cleanup() (`fastr.core.ioplugin.IOPlugin` method), 142
cleanup() (`fastr.core.ioplugin.IOPluginManager` method), 144
cleanup() (`fastr.execution.executionpluginmanager.ExecutionPlugin` method), 189
cleanup() (`fastr.plugins.BlockingExecution` method), 96
cleanup() (`fastr.plugins.DRMAAExecution` method), 97
cleanup() (`fastr.plugins.LinearExecution` method), 103
cleanup() (`fastr.plugins.ProcessPoolExecution` method), 107
cleanup() (`fastr.plugins.RQExecution` method), 107
cleanup() (`fastr.plugins.S3Filesystem` method), 108
cleanup() (`fastr.plugins.StrongrExecution` method), 109
cleanup() (`fastr.plugins.XNATStorage` method), 115
clear() (`fastr.core.inputgroup.InputGroup` method), 124
clear() (`fastr.core.inputoutput.Input` method), 132
clear() (`fastr.execution.environmentmodules.EnvironmentModules` method), 186
clear_version() (in module `fastr.version`), 115
collapse (`fastr.__init__.Link` attribute), 70
collapse (`fastr.core.link.Link` attribute), 147
collapse (`fastr.execution.linkrun.LinkRun` attribute), 211
collapse_indexes (`fastr.__init__.Link` attribute), 71
collapse_indexes (`fastr.core.link.Link` attribute), 147
collapse_indexes (`fastr.execution.linkrun.LinkRun` attribute), 211
FileNotFoundException (`fastr.plugins.FastrInterface` static method), 100
ExecutionPluginArgument_provenance()

(fastr.core.provenance.Provenance method), 163
collect_jobs() (fastr.plugins.DRMAAExecution method), 97
collect_provenance() (fastr.core.provenance.Provenance method), 163
collect_results() (fastr.plugins.FastrInterface method), 100
collector_plugin_type (fastr.plugins.FastrInterface attribute), 100
collectors (fastr.plugins.FastrInterface attribute), 100
combine() (fastr.core.samples.SampleItemBase static method), 168
combine_dimensions() (fastr.core.dimension.ForwardsDimensions method), 123
command (fastr.core.tool.Tool attribute), 175
COMMAND_DUMP (fastr.execution.job.Job attribute), 202
command_version (fastr.core.tool.Tool attribute), 175
commandfile (fastr.execution.job.Job attribute), 203
commandurl (fastr.execution.job.Job attribute), 203
CommaSeparatedValueFile (class in fastr.plugins), 96
compare_execution_dir() (in module fastr.utils.compare), 226
compare_job_dirs() (in module fastr.utils.compare), 226
compare_job_output_data() (in module fastr.utils.compare), 226
compare_output_data() (fastr.core.tool.Tool static method), 175
compare_set() (in module fastr.utils.compare), 226
compare_value_dict_item() (in module fastr.utils.compare), 227
compare_value_list() (in module fastr.utils.compare), 227
Config (class in fastr.configmanager), 77
configuration_fields (fastr.core.baseplugin.BasePlugin attribute), 119
configuration_fields (fastr.plugins.DRMAAExecution attribute), 98
configuration_fields (fastr.plugins.ProcessPoolExecution attribute), 107
configuration_fields (fastr.plugins.RQExecution attribute), 107
configuration_fields (fastr.plugins.StrongrExecution attribute), 109
connect() (fastr.plugins.XNATStorage method), 115
constantlist (fastr.execution.networkrun.NetworkRun attribute), 215
ConstantNode (class in fastr.__init__), 74
ConstantNode (class in fastr.core.node), 152
ConstantNodeRun (class in fastr.__init__), 65
ConstantNodeRun (class in fastr.execution.sourcenoderun), 221
container (fastr.plugins.DockerTarget attribute), 99
ContainsSamples (class in fastr.core.samples), 164
content() (fastr.datatypes.AnalyzeImageFile class method), 79
content() (fastr.datatypes.MetaImageFile class method), 85
content() (fastr.datatypes.URLType class method), 87
copy_file_dir() (fastr.plugins.VirtualFileSystem static method), 110
cpu_percent (fastr.core.target.SystemUsageInfo attribute), 173
create_constant() (fastr.__init__.Network method), 67
create_constant() (fastr.core.network.Network method), 150
create_enumtype() (fastr.core.datatypemanager.DataTypeManager Dimensions method), 120
create_ioplugin_tool() (fastr.core.ioplugin.IOPluginManager static method), 144
create_job() (fastr.execution.noderun.NodeRun method), 217
create_job() (fastr.execution.sinknoderun.SinkNodeRun method), 219
create_job() (fastr.execution.sourcenoderun.SourceNodeRun method), 221
create_link() (fastr.__init__.Network method), 67
create_link() (fastr.core.network.Network method), 150
create_link() (fastr.Network method), 62
create_link_from() (fastr.core.inputoutput.BaseInput method), 128
create_macro() (fastr.__init__.Network method), 68
create_macro() (fastr.core.network.Network method), 150
create_macro_network() (in module fastr.examples.macro_node), 185
create_macro_network() (in module fastr.examples.macro_node2), 185
create_native_spec() (fastr.plugins.DRMAAExecution method), 98
create_network() (in module fastr.examples.add_ints), 183
create_network() (in module fastr.examples.add_ints_s3), 183
create_network() (in module fastr.examples.auto_prefix), 183
create_network() (in module fastr.examples.collapse), 183
create_network() (in module fastr.examples.collapse_expand), 183
create_network() (in module fastr.examples.cross_validation), 184
create_network() (in module fastr.examples.elastix_nipype), 184
create_network() (in module fastr.examples.expand), 184
create_network() (in module fastr.examples.failing_network), 184
create_network() (in module fastr.examples.filecopy), 184

create_network()	(in fastr.examples.input_groups),	184	module	CrossValidation (class in fastr.plugins),	97
create_network()	(in fastr.examples.macro_node),	185	module	data (fastr.__init__.ConstantNode attribute),	75
create_network()	(in fastr.examples.macro_node2),	185	module	data (fastr.core.basemanager.BaseManager attribute),	118
create_network() (in module fastr.examples.shift_links),	185		module	data (fastr.core.node.ConstantNode attribute),	153
create_network() (in module fastr.examples.source_sink),	185		data (fastr.core.pluginmanager.PluginSubManager attribute),	162	
create_network_parser() (in module fastr.utils.cmd.run),	236		data (fastr.core.samples.SampleItemBase attribute),	168	
create_node() (fastr.__init__.Network method),	68		data (fastr.execution.sourcenoderun.ConstantNodeRun attribute),	222	
create_node() (fastr.core.network.Network method),	150		data_uri() (fastr.core.provenance.Provenance static method),	163	
create_node() (fastr.Network method),	62		DataType (class in fastr.datatypes),	81	
create_output_cardinality() (fastr.core.inputoutput.Output static method),	135		datatype (fastr.__init__.SinkNode attribute),	76	
create_output_cardinality()			datatype (fastr.__init__.SourceNode attribute),	76	
(fastr.execution.inputoutputrun.OutputRun static method),	196		datatype (fastr.core.inputoutput.BaseInputOutput attribute),	130	
create_payload() (fastr.execution.job.Job method),	203		datatype (fastr.core.inputoutput.Input attribute),	132	
create_payload() (fastr.execution.job.SinkJob method),	208		datatype (fastr.core.inputoutput.Output attribute),	135	
create_reference() (fastr.__init__.Network method),	68		datatype (fastr.core.inputoutput.SubOutput attribute),	140	
create_reference() (fastr.core.network.Network method),	150		datatype (fastr.core.node.SinkNode attribute),	158	
create_reference() (fastr.core.tool.Tool method),	175		datatype (fastr.core.node.SourceNode attribute),	159	
create_reference() (in module fastr.examples.__generate_reference__),	183		datatype (fastr.execution.inputoutputrun.InputRun attribute),	193	
create_rest_table() (in module fastr.utils.rest_generation),	232		datatype (fastr.execution.inputoutputrun.OutputRun attribute),	196	
create_sink() (fastr.__init__.Network method),	68		datatype (fastr.execution.inputoutputrun.SubOutputRun attribute),	201	
create_sink() (fastr.core.network.Network method),	150		datatype (fastr.execution.sinknoderun.SinkNodeRun attribute),	219	
create_sink() (fastr.Network method),	63		datatype (fastr.execution.sourcenoderun.SourceNodeRun attribute),	221	
create_source() (fastr.__init__.Network method),	68		datatype_from_type() (in module fastr.utils.cmd.extract_argparse),	235	
create_source() (fastr.core.network.Network method),	151		DataTypeManager (class in fastr.core.datatypemanager),	120	
create_source() (fastr.Network method),	63		date_version_matcher (fastr.core.version.Version attribute),	180	
create_super_macro_node() (in module fastr.examples.macro_node),	185		debug (fastr.configmanager.Config attribute),	77	
create_vfs_url() (in module fastr.data.url),	181		DEFAULT_FIELDS (fastr.configmanager.Config attribute),	77	
create_zip() (in module fastr.utils.cmd.dump),	235		DefaultInputGroupCombiner (class in fastr.core.inputgroupcombiner),	127	
created (fastr.execution.job.JobState attribute),	208		DefaultNetworkAnalyzer (class in fastr.execution.networkanalyzer),	213	
createobj() (fastr.__init__.Link class method),	71		DefaultNetworkChunker (class in fastr.execution.networkchunker),	213	
createobj() (fastr.__init__.Node class method),	73		Deferred (class in fastr.datatypes),	81	
createobj() (fastr.core.link.Link class method),	147		delete() (fastr.web.api.RunApi method),	239	
createobj() (fastr.core.node.Node class method),	156		descend() (fastr.utils.schematable.SchemaPrinter method),	232	
createobj() (fastr.core.serializable.Serializable method),	170		description (fastr.core.inputoutput.BaseInputOutput attribute),	130	
createobj() (fastr.execution.linkrun.LinkRun method),	211				
createobj() (fastr.execution.noderun.NodeRun method),	217				

description (fastr.core.inputoutput.SubInput attribute), 137
description (fastr.core.tool.Tool attribute), 175
description (fastr.datatypes.AnalyzeImageFile attribute), 79
description (fastr.datatypes.AnyFile attribute), 79
description (fastr.datatypes.AnyType attribute), 79
description (fastr.datatypes.BaseDataType attribute), 80
description (fastr.datatypes.Boolean attribute), 81
description (fastr.datatypes.Directory attribute), 83
description (fastr.datatypes.EnumType attribute), 83
description (fastr.datatypes.FilePrefix attribute), 84
description (fastr.datatypes.Float attribute), 84
description (fastr.datatypes.Int attribute), 84
description (fastr.datatypes.ITKImageFile attribute), 84
description (fastr.datatypes.JsonFile attribute), 84
description (fastr.datatypes.MetaImageFile attribute), 85
description (fastr.datatypes.NiftiImageFile attribute), 85
description (fastr.datatypes.NiftiImageFileCompressed attribute), 85
description (fastr.datatypes.NiftiImageFileUncompressed attribute), 85
description (fastr.datatypes.Number attribute), 86
description (fastr.datatypes.ProvNFile attribute), 86
description (fastr.datatypes.String attribute), 86
description (fastr.datatypes.TifImageFile attribute), 86
description (fastr.datatypes.TxtFile attribute), 86
description (fastr.datatypes.UnsignedInt attribute), 88
description (fastr.execution.inputoutputrun.SubInputRun attribute), 199
destroy() (fastr.__init__.Link method), 71
destroy() (fastr.core.link.Link method), 147
destroy() (fastr.execution.linkrun.LinkRun method), 211
dicteq() (in module fastr.utils.dicteq), 227
diffdict() (in module fastr.utils.dicteq), 227
diffobj() (in module fastr.utils.dicteq), 227
diffobj_str() (in module fastr.utils.dicteq), 227
Dimension (class in fastr.core.dimension), 122
dimensionality (fastr.core.samples.SampleItemBase attribute), 168
dimensions (fastr.__init__.Link attribute), 71
dimensions (fastr.__init__.Node attribute), 73
dimensions (fastr.__init__.SourceNode attribute), 76
dimensions (fastr.core.dimension.ForwardsDimensions attribute), 123
dimensions (fastr.core.dimension.HasDimensions attribute), 123
dimensions (fastr.core.inputgroup.InputGroup attribute), 125
dimensions (fastr.core.inputgroupcombiner.BaseInputGroup attribute), 126
dimensions (fastr.core.inputoutput.AdvancedFlowOutput attribute), 128
dimensions (fastr.core.inputoutput.Input attribute), 132
dimensions (fastr.core.inputoutput.MacroOutput attribute), 133
dimensions (fastr.core.inputoutput.Output attribute), 135
dimensions (fastr.core.inputoutput.SubInput attribute), 137
dimensions (fastr.core.link.Link attribute), 148
dimensions (fastr.core.node.FlowNode attribute), 154
dimensions (fastr.core.node.Node attribute), 156
dimensions (fastr.core.node.SourceNode attribute), 159
dimensions (fastr.core.samples.ContainsSamples attribute), 164
dimensions (fastr.core.samples.SampleCollection attribute), 166
dimensions (fastr.execution.inputoutputrun.InputRun attribute), 193
dimensions (fastr.execution.inputoutputrun.MacroOutputRun attribute), 194
dimensions (fastr.execution.inputoutputrun.SourceOutputRun attribute), 198
dimensions (fastr.execution.inputoutputrun.SubInputRun attribute), 199
dimensions (fastr.execution.linkrun.LinkRun attribute), 212
dimnames (fastr.__init__.Node attribute), 73
dimnames (fastr.core.dimension.HasDimensions attribute), 123
dimnames (fastr.core.node.Node attribute), 156
dimnames (fastr.execution.flownoderun.FlowNodeRun attribute), 191
dimnames (fastr.execution.noderun.NodeRun attribute), 217
dimnames (fastr.execution.sourcenoderun.SourceNodeRun attribute), 221
dir_list() (in module fastr.utils.clear_pycs), 226
Directory (class in fastr.datatypes), 82
directory() (in module fastr.utils.cmd.test), 236
dirname() (in module fastr.data.url), 181
dirurl() (in module fastr.data.url), 181
doc() (in module fastr.web.views), 240
DockerTarget (class in fastr.plugins), 98
done (fastr.execution.job.JobState attribute), 208
draw() (fastr.__init__.ConstantNode method), 75
draw() (fastr.__init__.Link method), 71
draw() (fastr.__init__.Network method), 68
draw() (fastr.__init__.Node method), 73
draw() (fastr.__init__.SinkNode method), 77
draw() (fastr.__init__.SourceNode method), 76
draw() (fastr.core.link.Link method), 148
draw() (fastr.core.network.Network method), 151
draw() (fastr.core.node.ConstantNode method), 153
draw() (fastr.core.node.MacroNode method), 154
draw() (fastr.core.node.Node method), 156
draw() (fastr.core.node.SinkNode method), 158
draw() (fastr.core.node.SourceNode method), 159

draw_id() (fastr.__init__.Node method), 73
draw_id() (fastr.core.node.Node method), 156
draw_link_target() (fastr.__init__.Node method), 73
draw_link_target() (fastr.core.node.MacroNode method), 154
draw_link_target() (fastr.core.node.Node method), 156
draw_network() (fastr.__init__.Network method), 68
draw_network() (fastr.core.network.Network method), 151
draw_network() (fastr.Network method), 63
DRMAAExecution (class in fastr.plugins), 97
dump() (fastr.core.serializable.Serializable method), 170
dump() (in module fastr.utils.xmltodict), 234
dumpf() (fastr.core.serializable.Serializable method), 170
dumpfuncs (fastr.core.serializable.Serializable attribute), 171
dumps() (fastr.core.serializable.PassThroughSerializer static method), 170
dumps() (fastr.core.serializable.Serializable method), 171
dumps() (in module fastr.utils.xmltodict), 234
DYNAMIC_LIBRARY_PATH_DICT
 (fastr.plugins.LocalBinaryTarget attribute), 105

E

empty (fastr.core.inputgroup.InputGroup attribute), 125
EmptyDefault (class in fastr.configmanager), 78
endpoint (fastr.web.api.NetworkApi attribute), 238
endpoint (fastr.web.api.NetworkListApi attribute), 238
endpoint (fastr.web.api.RunApi attribute), 239
endpoint (fastr.web.api.RunListApi attribute), 239
endpoint (fastr.web.api.StatusApi attribute), 239
endpoint (fastr.web.api.ToolApi attribute), 239
endpoint (fastr.web.api.ToolListApi attribute), 240
ensure_tmp_dir() (fastr.execution.job.Job method), 203
entity() (fastr.core.provenance.Provenance method), 163
EnumType (class in fastr.datatypes), 83
EnvironmentModules
 (class in fastr.execution.environmentmodules), 186
envmod (fastr.execution.environmentmodules.ModuleSystem attribute), 187
examplesdir (fastr.configmanager.Config attribute), 77
exception (fastr.execution.environmentmodules.Environment attribute), 186
excerpt() (fastr.exceptions.FastrError method), 90
exec_worker() (fastr.plugins.LinearExecution method), 103
execute() (fastr.__init__.Network method), 69
execute() (fastr.core.interface.Interface method), 141
execute() (fastr.core.network.Network method), 151
execute() (fastr.core.tool.Tool method), 175
execute() (fastr.execution.flownoderun.AdvancedFlowNode method), 191
execute() (fastr.execution.job.Job method), 203

execute() (fastr.execution.macronoderun.MacroNodeRun method), 212
execute() (fastr.execution.networkrun.NetworkRun method), 215
execute() (fastr.execution.noderun.NodeRun method), 217
execute() (fastr.execution.sinknoderun.SinkNodeRun method), 219
execute() (fastr.execution.sourcenoderun.ConstantNodeRun method), 222
execute() (fastr.execution.sourcenoderun.SourceNodeRun method), 221
execute() (fastr.plugins.CrossValidation static method), 97
execute() (fastr.plugins.FastrInterface method), 100
execute() (fastr.plugins.FlowInterface method), 103
execute() (fastr.plugins.NipypeInterface method), 106
execute_job() (in module fastr.execution.executionscript), 191
execution_done (fastr.execution.job.JobState attribute), 208
execution_failed (fastr.execution.job.JobState attribute), 208
execution_plugin (fastr.configmanager.Config attribute), 77
ExecutionPlugin (class in fastr.execution.executionpluginmanager), 187
ExecutionPluginManager (class in fastr.execution.executionpluginmanager), 190
executionscript (fastr.configmanager.Config attribute), 77
expand (fastr.__init__.Link attribute), 71
expand (fastr.core.link.Link attribute), 148
expand (fastr.execution.linkrun.LinkRun attribute), 212
expand() (fastr.core.samples.SampleIndex method), 167
expand_url() (fastr.core.ioplugin.IOPlugin method), 142
expand_url() (fastr.core.ioplugin.IOPluginManager method), 144
expand_url() (fastr.plugins.CommaSeparatedValueFile method), 97
expand_url() (fastr.plugins.S3Filesystem method), 108
expand_url() (fastr.plugins.VirtualFileSystem method), 110
expand_url() (fastr.plugins.VirtualFileSystemRegularExpression method), 112
expand_url() (fastr.plugins.VirtualFileSystemValueList method), 113
expand_url() (fastr.plugins.XNATStorage method), 115
expanding (fastr.core.interface.Interface attribute), 141
expanding (fastr.plugins.FastrInterface attribute), 101
expanding (fastr.plugins.FlowInterface attribute), 103
expanding (fastr.plugins.NipypeInterface attribute), 106
extend() (fastr.configmanager.EmptyDefault method), 78

extend() (in module `fastr.utils.jsonschemaparser`), 229
extension (fastr.datatypes.AnalyzeImageFile attribute), 79
extension (fastr.datatypes.BaseDataType attribute), 80
extension (fastr.datatypes.Directory attribute), 83
extension (fastr.datatypes.FilePrefix attribute), 84
extension (fastr.datatypes.JsonFile attribute), 84
extension (fastr.datatypes.MetaImageFile attribute), 85
extension (fastr.datatypes.NiftiImageFileCompressed attribute), 85
extension (fastr.datatypes.NiftiImageFileUncompressed attribute), 85
extension (fastr.datatypes.ProvNFile attribute), 86
extension (fastr.datatypes.TifImageFile attribute), 86
extension (fastr.datatypes.TxtFile attribute), 86
extra (fastr.core.version.Version attribute), 180
extra_string (fastr.core.version.Version attribute), 180
extract_argparser() (in module `fastr.utils.cmd.extract_argparse`), 235
extrainfofile (fastr.execution.job.Job attribute), 203
extrainfourl (fastr.execution.job.Job attribute), 203

F

failed (fastr.core.baseplugin.PluginState attribute), 120
failed (fastr.execution.job.JobState attribute), 208
failed_annotations (fastr.core.samples.SampleItemBase attribute), 168
fastr.__init__ (module), 65
fastr.configmanager (module), 77
fastr.core (module), 116
fastr.core.basemanager (module), 116
fastr.core.baseplugin (module), 118
fastr.core.datatypemanager (module), 120
fastr.core.dimension (module), 122
fastr.core.inputgroup (module), 124
fastr.core.inputgroupcombiner (module), 126
fastr.core.inputoutput (module), 128
fastr.core.interface (module), 140
fastr.core.ioplugin (module), 142
fastr.core.link (module), 145
fastr.core.network (module), 148
fastr.core.networkmanager (module), 152
fastr.core.node (module), 152
fastr.core.objectmanager (module), 159
fastr.core.pluginmanager (module), 160
fastr.core.provenance (module), 163
fastr.core.samples (module), 164
fastr.core.serializable (module), 170
fastr.core.target (module), 172
fastr.core.test (module), 180
fastr.core.tool (module), 174
fastr.core.toolmanager (module), 176
fastr.core.updateable (module), 177
fastr.core.version (module), 179

fastr.core.vfs (module), 180
fastr.data (module), 181
fastr.data.url (module), 181
fastr.datatypes (module), 79
fastr.examples (module), 183
fastr.examples.__generate_reference__ (module), 183
fastr.examples.add_ints (module), 183
fastr.examples.add_ints_s3 (module), 183
fastr.examples.auto_prefix (module), 183
fastr.examples.collapse (module), 183
fastr.examples.collapse_expand (module), 183
fastr.examples.cross_validation (module), 184
fastr.examples.elastix_nipype (module), 184
fastr.examples.expand (module), 184
fastr.examples.failing_network (module), 184
fastr.examples.filecopy (module), 184
fastr.examples.input_groups (module), 184
fastr.examples.macro_node (module), 185
fastr.examples.macro_node2 (module), 185
fastr.examples.shift_links (module), 185
fastr.examples.source_sink (module), 185
fastr.exceptions (module), 89
fastr.execution (module), 186
fastr.execution.environmentmodules (module), 186
fastr.execution.executionpluginmanager (module), 187
fastr.execution.executionscript (module), 191
fastr.execution.flownoderun (module), 191
fastr.execution.inputoutputrun (module), 192
fastr.execution.job (module), 202
fastr.execution.linkrun (module), 209
fastr.execution.macronoderun (module), 212
fastr.execution.networkanalyzer (module), 213
fastr.execution.networkchunker (module), 213
fastr.execution.networkrun (module), 214
fastr.execution.noderun (module), 216
fastr.execution.sinknoderun (module), 219
fastr.execution.sourcenoderun (module), 220
fastr.plugins (module), 95
fastr.resources (module), 222
fastr.utils (module), 224
fastr.utils.checksum (module), 224
fastr.utils.classproperty (module), 226
fastr.utils.clear_pycs (module), 226
fastr.utils.cmd (module), 235
fastr.utils.cmd.cat (module), 235
fastr.utils.cmd.dump (module), 235
fastr.utils.cmd.execute (module), 235
fastr.utils.cmd.extract_argparse (module), 235
fastr.utils.cmd.prov (module), 236
fastr.utils.cmd.run (module), 236
fastr.utils.cmd.test (module), 236
fastr.utils.cmd.trace (module), 236
fastr.utils.cmd.verify (module), 237
fastr.utils.cmd.webapp (module), 237

fastr.utils.compare (module), 226
 fastr.utils.dicteq (module), 227
 fastr.utils.filesynchelper (module), 228
 fastr.utils.gettools (module), 228
 fastr.utils.iohelpers (module), 228
 fastr.utils.jsonschema (module), 229
 fastr.utils.multiprocesswrapper (module), 231
 fastr.utils.pim_publisher (module), 231
 fastr.utils.procutils (module), 231
 fastr.utils.rest_generation (module), 232
 fastr.utils.schematatable (module), 232
 fastr.utils.sysinfo (module), 233
 fastr.utils.verify (module), 234
 fastr.utils.xmltodict (module), 234
 fastr.version (module), 115
 fastr.web (module), 238
 fastr.web.api (module), 238
 fastr.web.run (module), 240
 fastr.web.views (module), 240
 fastr_cat() (in module fastr.utils.cmd.cat), 235
 fastr_isinstance() (in module fastr.datatypes), 88
 FastrAttributeError, 89
 FastrCannotChangeAttributeError, 89
 FastrCardinalityError, 89
 FastrCollectorError, 89
 FastrDataTypeFileNotReadable, 89
 FastrDataTypeMismatchError, 89
 FastrDataTypeNotFoundError, 89
 FastrDataTypeNotInstantiableError, 89
 FastrDataTypeValueError, 89
 FastrError, 90
 FastrErrorInSubprocess, 90
 FastrExecutableNotFoundError, 90
 FastrExecutionError, 90
 FastrImportError, 90
 FastrIndexError, 91
 FastrIndexNonexistent, 91
 FastrInterface (class in fastr.plugins), 99
 FastrIOError, 90
 FastrKeyError, 91
 FastrLookupError, 91
 FastrMountUnknownError, 91
 FastrNetworkMismatchError, 91
 FastrNetworkUnknownError, 91
 FastrNodeAlreadyPreparedError, 91
 FastrNodeNotPreparedError, 92
 FastrNodeNotValidError, 92
 FastrNotExecutableError, 92
 FastrNotImplementedError, 92
 FastrNoValidTargetException, 91
 FastrObjectUnknownError, 92
 FastrOptionalModuleNotFoundError, 92
 FastrOSError, 92
 FastrOutputValidation, 92

FastrParentMismatchError, 93
 FastrPluginCapabilityNotImplemented, 93
 FastrPluginNotAvailable, 93
 FastrPluginNotLoaded, 93
 FastrRefResolver (class in fastr.utils.jsonschema), 229
 FastrResultFileNotFound, 93
 FastrSerializationError, 93
 FastrSerializationIgnoreDefaultError, 93
 FastrSerializationInvalidDataError, 93
 FastrSerializationMethodError, 94
 FastrSinkDataUnavailableError, 94
 FastrSizeInvalidError, 94
 FastrSizeMismatchError, 94
 FastrSizeUnknownError, 94
 FastrSourceDataUnavailableError, 94
 FastrStateError, 94
 FastrSubprocessNotFinished, 94
 FastrToolNotFoundError, 94
 FastrToolTargetNotFound, 95
 FastrToolUnknownError, 95
 FastrTypeError, 95
 FastrUnknownURLSchemeError, 95
 FastrValueError, 95
 FastrVersionInvalidError, 95
 FastrVersionMismatchError, 95
 fetch_url() (fastr.core.ioplugin.IOPlugin method), 142
 fetch_url() (fastr.plugins.FileSystem method), 101
 fetch_url() (fastr.plugins.S3Filesystem method), 108
 fetch_url() (fastr.plugins.VirtualFileSystem method), 110
 fetch_url() (fastr.plugins.XNATStorage method), 115
 fetch_value() (fastr.core.ioplugin.IOPlugin method), 142
 fetch_value() (fastr.plugins.FileSystem method), 102
 fetch_value() (fastr.plugins.S3Filesystem method), 109
 fetch_value() (fastr.plugins.VirtualFileSystem method), 110

filename (fastr.core.pluginmanager.PluginOptionType attribute), 163
 filename (fastr.datatypes.AnalyzeImageFile attribute), 79
 filename (fastr.datatypes.BaseDataType attribute), 80
 filename (fastr.datatypes.Boolean attribute), 81
 filename (fastr.datatypes.Directory attribute), 83
 filename (fastr.datatypes.FilePrefix attribute), 84
 filename (fastr.datatypes.Float attribute), 84
 filename (fastr.datatypes.Int attribute), 84
 filename (fastr.datatypes.ITKImageFile attribute), 84
 filename (fastr.datatypes.JsonFile attribute), 84
 filename (fastr.datatypes.MetaImageFile attribute), 85
 filename (fastr.datatypes.NiftiImageFile attribute), 85
 filename (fastr.datatypes.NiftiImageFileCompressed attribute), 85
 filename (fastr.datatypes.NiftiImageFileUncompressed attribute), 85
 filename (fastr.datatypes.Number attribute), 86

filename (fastr.datatypes.ProvNFile attribute), 86
filename (fastr.datatypes.String attribute), 86
filename (fastr.datatypes.TifImageFile attribute), 86
filename (fastr.datatypes.TxtFile attribute), 86
filename (fastr.datatypes.UnsignedInt attribute), 88
filename (fastr.plugins.BlockingExecution attribute), 96
filename (fastr.plugins.CommaSeperatedValueFile attribute), 97
filename (fastr.plugins.CrossValidation attribute), 97
filename (fastr.plugins.DockerTarget attribute), 99
filename (fastr.plugins.DRMAAExecution attribute), 98
filename (fastr.plugins.FastrInterface attribute), 101
filename (fastr.plugins.FileSystem attribute), 102
filename (fastr.plugins.FlowInterface attribute), 103
filename (fastr.plugins.LinearExecution attribute), 103
filename (fastr.plugins.LocalBinaryTarget attribute), 105
filename (fastr.plugins.NipypeInterface attribute), 106
filename (fastr.plugins.Null attribute), 106
filename (fastr.plugins.ProcessPoolExecution attribute), 107
filename (fastr.plugins.Reference attribute), 108
filename (fastr.plugins.RQExecution attribute), 107
filename (fastr.plugins.S3Filesystem attribute), 109
filename (fastr.plugins.StrongrExecution attribute), 109
filename (fastr.plugins.VirtualFileSystemRegularExpression attribute), 112
filename (fastr.plugins.VirtualFileSystemValueList attribute), 113
filename (fastr.plugins.XNATStorage attribute), 115
FilePrefix (class in fastr.datatypes), 83
FileSyncHelper (class in fastr.utils.filesynchelper), 228
filesynchelper_enabled() (in module fastr.utils.filesynchelper), 228
filesynchelper_url (fastr.configmanager.Config attribute), 77
FileSystem (class in fastr.plugins), 101
fill_output_argument() (fastr.execution.job.Job class method), 203
filter_plugin() (fastr.core.pluginmanager.PluginsView method), 162
find_argparser() (in module fastr.utils.cmd.extract_argparse), 235
find_commands() (in module fastr.utils.cmd), 235
find_member() (fastr.core.updateable.UpdateableMeta class method), 178
find_source_index() (fastr.__init__.Node method), 73
find_source_index() (fastr.core.inputgroup.InputGroup method), 125
find_source_index() (fastr.core.node.Node method), 156
find_source_index() (fastr.execution.noderun.NodeRun method), 217
finished (fastr.execution.job.JobState attribute), 208
Float (class in fastr.datatypes), 84
flow_plugin_type (fastr.plugins.FlowInterface attribute), 103
flow_plugins (fastr.plugins.FlowInterface attribute), 103
FlowInterface (class in fastr.plugins), 102
FlowNode (class in fastr.core.node), 153
FlowNodeRun (class in fastr.execution.flownoderun), 191
format() (fastr.web.api.ObjectUrl method), 238
format() (fastr.web.api.SubUrl method), 239
ForwardsDimensions (class in fastr.core.dimension), 123
from_schema() (fastr.utils.jsonschemaparser.FastrRefResolver class method), 229
full_split() (in module fastr.data.url), 181
fullid (fastr.__init__.Link attribute), 71
fullid (fastr.__init__.Network attribute), 69
fullid (fastr.__init__.Node attribute), 73
fullid (fastr.core.baseplugin.BasePlugin attribute), 119
fullid (fastr.core.datatypemanager.DataTypeManager attribute), 120
fullid (fastr.core.inputgroup.InputGroup attribute), 125
fullid (fastr.core.inputgroupcombiner.BaseInputGroupCombiner attribute), 126
fullid (fastr.core.inputoutput.BaseInputOutput attribute), 130
fullid (fastr.core.inputoutput.Input attribute), 132
fullid (fastr.core.inputoutput.Output attribute), 135
fullid (fastr.core.inputoutput.SubInput attribute), 137
fullid (fastr.core.inputoutput.SubOutput attribute), 140
fullid (fastr.core.link.Link attribute), 148
fullid (fastr.core.network.Network attribute), 151
fullid (fastr.core.node.Node attribute), 156
fullid (fastr.core.samples.SampleCollection attribute), 166
fullid (fastr.core.tool.Tool attribute), 175
fullid (fastr.datatypes.BaseDataType attribute), 80
fullid (fastr.execution.inputoutputrun.InputRun attribute), 193
fullid (fastr.execution.inputoutputrun.OutputRun attribute), 196
fullid (fastr.execution.inputoutputrun.SubInputRun attribute), 199
fullid (fastr.execution.inputoutputrun.SubOutputRun attribute), 201
fullid (fastr.execution.job.Job attribute), 204
fullid (fastr.execution.linkrun.LinkRun attribute), 212
fullid (fastr.execution.networkrun.NetworkRun attribute), 215
fullid (fastr.execution.noderun.NodeRun attribute), 218
function_wrapper() (in module fastr.utils.multiprocesswrapper), 231

G

GE_NATIVE_SPEC (fastr.plugins.DRMAAExecution attribute), 97

generate_all_references() (in module fastr.examples.__generate_reference__), 183

generate_jobs() (fastr.execution.networkrun.NetworkRun method), 216

get() (fastr.web.api.NetworkApi method), 238

get() (fastr.web.api.NetworkListApi method), 238

get() (fastr.web.api.RunApi method), 239

get() (fastr.web.api.RunListApi method), 239

get() (fastr.web.api.StatusApi method), 239

get() (fastr.web.api.ToolApi method), 240

get() (fastr.web.api.ToolListApi method), 240

get_arguments() (fastr.plugins.FastrInterface method), 101

get_base_version() (in module fastr.version), 115

get_command() (fastr.plugins.FastrInterface method), 101

get_command_module() (in module fastr.utils.cmd), 235

get_cpu_usage() (in module fastr.utils.sysinfo), 233

get_deferred() (fastr.execution.job.Job method), 204

get_drmaa_info() (in module fastr.utils.sysinfo), 233

get_field() (fastr.configmanager.Config method), 77

get_hg_info() (in module fastr.version), 116

get_hostinfo() (in module fastr.utils.sysinfo), 233

get_job() (fastr.execution.executionpluginmanager.ExecutionPlugin method), 189

get_memory_usage() (in module fastr.utils.sysinfo), 233

get_mounts() (in module fastr.utils.sysinfo), 233

get_object_version() (fastr.core.networkmanager.NetworkManager method), 152

get_object_version() (fastr.core.objectmanager.ObjectManager method), 160

get_object_version() (fastr.core.toolmanager.ToolManager method), 176

get_os() (in module fastr.utils.sysinfo), 233

get_output_datatype() (fastr.execution.job.Job method), 204

get_output_datatype() (fastr.execution.job.SourceJob method), 209

get_output_info() (fastr.core.node.MacroNode method), 154

get_output_info() (fastr.execution.macronoderun.MacroNode method), 213

get_parent_provenance() (fastr.core.provenance.Provenance method), 163

get_parser() (in module fastr.utils.cmd.cat), 235

get_parser() (in module fastr.utils.cmd.dump), 235

get_parser() (in module fastr.utils.cmd.execute), 235

get_parser() (in module fastr.utils.cmd.extract_argparse), 235

get_parser() (in module fastr.utils.cmd.prov), 236

get_parser() (in module fastr.utils.cmd.run), 236

get_parser() (in module fastr.utils.cmd.test), 236

get_parser() (in module fastr.utils.cmd.trace), 236

get_parser() (in module fastr.utils.cmd.verify), 237

get_parser() (in module fastr.utils.cmd.webapp), 237

get_path_from_url() (in module fastr.data.url), 182

get_processes() (in module fastr.utils.sysinfo), 233

get_prov_document() (in module fastr.utils.cmd.prov), 236

get_python() (in module fastr.utils.sysinfo), 233

get_result() (fastr.execution.job.InlineJob method), 202

get_result() (fastr.execution.job.Job method), 204

get_result() (fastr.execution.job.SinkJob method), 208

get_saved_version() (in module fastr.version), 116

get_serializer() (fastr.core.serializable.Serializable class method), 171

get_sourced_nodes() (fastr.__init__.Node method), 73

get_sourced_nodes() (fastr.core.inputoutput.Input method), 132

get_sourced_nodes() (fastr.core.inputoutput.SubInput method), 137

get_sourced_nodes() (fastr.core.node.Node method), 156

get_sourced_nodes() (fastr.execution.inputoutputrun.InputRun method), 193

get_sourced_nodes() (fastr.execution.inputoutputrun.SubInputRun method), 199

get_sourced_nodes() (fastr.execution.noderun.NodeRun method), 218

get_sourced_outputs() (fastr.core.inputoutput.Input method), 132

get_sourced_outputs() (fastr.core.inputoutput.SubInput method), 138

get_sourced_outputs() (fastr.execution.inputoutputrun.InputRun method), 194

get_sourced_outputs() (fastr.execution.inputoutputrun.SubInputRun method), 199

get_specials() (fastr.plugins.FastrInterface method), 101

get_status() (fastr.execution.executionpluginmanager.ExecutionPlugin method), 189

get_sysinfo() (in module fastr.utils.sysinfo), 233

get_type() (fastr.core.datatypemanager.DataTypeManager method), 121

get_type() (fastr.plugins.NipypeInterface method), 106

get_url_scheme() (in module fastr.data.url), 182

get_users() (in module fastr.utils.sysinfo), 233

get_value() (fastr.execution.job.Job class method), 204

getblueprinter() (in module fastr.utils.jsonschemaparser), 229

global_id (fastr.__init__.Network attribute), 69

global_id (fastr.__init__.Node attribute), 73

global_id (fastr.core.network.Network attribute), 151

global_id (fastr.core.node.Node attribute), 156

global_id (fastr.execution.networkrun.NetworkRun attribute), 216

global_id (fastr.execution.noderun.NodeRun attribute), 218

guess_type() (fastr.core.datatypemanager.DataTypeManager init_provenance() method), 121

H

has_file_promise() (fastr.utils.filesynchelperFileSyncHelper method), 228

has_type() (fastr.core.datatypemanager.DataTypeManager method), 121

HasDimensions (class in fastr.core.dimension), 123

hash (fastr.core.tool.Tool attribute), 175

hash_inputs() (fastr.execution.job.Job method), 204

hash_inputs() (fastr.execution.job.SinkJob method), 208

hash_inputs() (fastr.execution.job.SourceJob method), 209

hash_results() (fastr.execution.job.Job method), 204

hashsum() (in module fastr.utils.checksum), 225

HasSamples (class in fastr.core.samples), 164

help (fastr.core.tool.Tool attribute), 175

hold (fastr.execution.executionpluginmanager.JobAction attribute), 190

hold (fastr.execution.job.JobState attribute), 208

hold_job() (fastr.execution.executionpluginmanager.Execution method), 189

I

id (fastr.__init__.Network attribute), 69

id (fastr.__init__.Node attribute), 73

id (fastr.core.baseplugin.BasePlugin attribute), 119

id (fastr.core.inputoutput.BaseInputOutput attribute), 130

id (fastr.core.network.Network attribute), 151

id (fastr.core.node.Node attribute), 156

id (fastr.core.pluginmanager.plugin_option_type attribute), 163

id (fastr.core.samples.SampleItemBase attribute), 168

id (fastr.datatypes.BaseDataType attribute), 80

id (fastr.execution.job.Job attribute), 204

id (fastr.execution.job.SinkJob attribute), 209

id (fastr.execution.networkrun.NetworkRun attribute), 216

id (fastr.execution.noderun.NodeRun attribute), 218

id_(fastr.core.node.Node attribute), 156

idle (fastr.execution.job.JobState attribute), 208

ids() (fastr.core.samples.HasSamples method), 164

in_progress (fastr.execution.job.JobState attribute), 208

index (fastr.core.samples.SampleItemBase attribute), 168

index() (fastr.core.inputoutput.Input method), 132

index() (fastr.execution.inputoutputrun.InputRun method), 194

index() (in module fastr.web.views), 240

indexes() (fastr.core.samples.HasSamples method), 164

indexrep (fastr.core.inputoutput.SubOutput attribute), 140

indexrep (fastr.execution.inputoutputrun.SubOutputRun attribute), 201

INFO_DUMP (fastr.execution.job.Job attribute), 202

guess_type() (fastr.core.datatypemanager.DataTypeManager init_provenance() method), 121

InlineJob (class in fastr.execution.job), 202

Input (class in fastr.core.inputoutput), 130

input (fastr.__init__.SinkNode attribute), 77

input (fastr.core.node.SinkNode attribute), 158

input (fastr.execution.sinknoderun.SinkNodeRun attribute), 219

input_group (fastr.core.inputoutput.Input attribute), 133

input_group (fastr.core.inputoutput.SubInput attribute), 138

input_group (fastr.execution.inputoutputrun.InputRun attribute), 194

input_group (fastr.execution.inputoutputrun.SubInputRun attribute), 199

input_groups (fastr.__init__.Node attribute), 73

input_groups (fastr.core.inputgroupcombiner.BaseInputGroupCombiner attribute), 126

input_groups (fastr.core.node.Node attribute), 156

input_groups (fastr.execution.noderun.NodeRun attribute), 218

INPUT_Dict (class in fastr.core.node), 154

InputGroup (class in fastr.core.inputgroup), 124

InputRun (class in fastr.execution.inputoutputrun), 192

inputs (fastr.core.interface.Interface attribute), 141

inputs (fastr.core.node.Node attribute), 156

inputs (fastr.core.tool.Tool attribute), 175

inputs (fastr.plugins.FastrInterface attribute), 101

inputs (fastr.plugins.FlowInterface attribute), 103

inputs (fastr.plugins.NipypeInterface attribute), 106

InputSpec (class in fastr.core.interface), 140

InputSpecBase (in module fastr.core.interface), 140

insert() (fastr.core.inputoutput.Input method), 133

insert() (fastr.execution.inputoutputrun.InputRun method), 194

instantiate (fastr.core.baseplugin.BasePlugin attribute), 119

Int (class in fastr.datatypes), 84

Interface (class in fastr.core.interface), 140

interface_class (fastr.core.tool.Tool attribute), 175

InterfacePluginManager (class in fastr.core.interface), 141

InterfaceResult (class in fastr.core.interface), 141

IOPlugin (class in fastr.core.ioplugin), 142

IOPluginManager (class in fastr.core.ioplugin), 144

is_mapping (fastr.core.samples.SampleValue attribute), 169

is_sequence (fastr.core.samples.SampleValue attribute), 169

is_valid() (fastr.__init__.Network method), 69

is_valid() (fastr.core.network.Network method), 151

isdatatype() (fastr.core.datatypemanager.DataTypeManager static method), 121

i
 isinstance() (fastr.datatypes.BaseDataType class method), 80
 isinstance() (fastr.datatypes.TypeGroup class method), 87
 isloaded() (fastr.execution.environmentmodules.EnvironmentModule class method), 186
 isslice (fastr.core.samples.SampleIndex attribute), 167
 isurl() (fastr.core.ioplugin.IOPlugin static method), 143
 isurl() (in module fastr.data.url), 182
 items() (fastr.core.samples.HasSamples method), 164
 items_prevalidate() (in module fastr.utils.jsonschemasparser), 230
 iter_input_groups() (fastr.core.inputgroupcombiner.BaseInputGroupCombiner class method), 126
 iter_input_groups() (fastr.core.inputgroupcombiner.DefaultInputGroupCombiner class method), 127
 iter_input_groups() (fastr.core.inputgroupcombiner.MergingInputGroupCombiner class method), 127
 iterconvergingindices() (fastr.execution.inputoutputrun.OutputRun class method), 196
 iterelements() (fastr.core.samples.SampleValue method), 169
 iterinputvalues (fastr.core.inputgroup.InputGroup attribute), 125
 iteritems() (fastr.core.inputoutput.SubInput method), 138
 iteritems() (fastr.core.samples.HasSamples method), 164
 iteritems() (fastr.execution.inputoutputrun.SubInputRun method), 200
 itersubinputs() (fastr.core.inputoutput.BaseInput method), 128
 itersubinputs() (fastr.core.inputoutput.Input method), 133
 itersubinputs() (fastr.core.inputoutput.SubInput method), 138
 itersubinputs() (fastr.execution.inputoutputrun.BaseInputRun method), 192
 itersubinputs() (fastr.execution.inputoutputrun.InputRun method), 194
 itersubinputs() (fastr.execution.inputoutputrun.SubInputRun method), 200
 ITKImageFile (class in fastr.datatypes), 84

J
 Job (class in fastr.execution.job), 202
 job (fastr.datatypes.Deferred attribute), 82
 job_finished() (fastr.execution.executionpluginmanager.ExecutedPluginModules class method), 189
 job_finished() (fastr.execution.networkrun.NetworkRun class method), 216
 job_finished() (fastr.utils.filesynchelperFileSyncHelper class method), 228
 job_finished_callback (fastr.execution.networkrun.NetworkRun class attribute), 216
 job_status_callback (fastr.execution.networkrun.NetworkRun class attribute), 216

L
 JobAction (class in fastr.execution.executionpluginmanager), 190
 jobs (fastr.core.samples.SampleItemBase attribute), 168
M
 ModelState (class in fastr.execution.job), 206
 join() (in module fastr.data.url), 182
 json (in module fastr.plugins), 115
 JsonFile (class in fastr.datatypes), 84

N
 LazyModule (class in fastr.core.pluginmanager), 161
 LinearExecution (class in fastr.plugins), 103
P
 PipelineGroupCombine (fastr.execution.inputoutput.SourceOutput attribute), 136
R
 RealizedInputGroupCombiner (fastr.execution.inputoutputrun.SourceOutputRun attribute), 198
 RealizedLinkGroupCombiner (fastr.execution.linkrun.SourceOutputRun attribute), 198
 Link (class in fastr.__init__), 65, 69
 PLink (class in fastr.core.link), 146
 LinkRun (class in fastr.execution.linkrun), 210
 listeners (fastr.__init__.Node attribute), 73
 listeners (fastr.core.inputoutput.Output attribute), 135
 listeners (fastr.core.inputoutput.SubOutput attribute), 140
 listeners (fastr.core.node.Node attribute), 156
 listeners (fastr.execution.inputoutputrun.OutputRun attribute), 197
 listeners (fastr.execution.inputoutputrun.SubOutputRun attribute), 202
 listeners (fastr.execution.noderun.NodeRun attribute), 218
 lmod (fastr.execution.environmentmodules.ModuleSystem attribute), 187
 load() (fastr.core.serializable.Serializable class method), 171
 load() (fastr.execution.environmentmodules.EnvironmentModules class method), 186
 load() (fastr.utils.filesynchelperFileSyncHelper class method), 228
 load() (in module fastr.utils.xmltodict), 234
 load_gpickle() (in module fastr.utils.iohelpers), 228
 load_json() (in module fastr.utils.iohelpers), 228
 load_plugin() (fastr.core.pluginmanager.BasePluginManager class method), 161
 loaded (fastr.core.baseplugin.PluginState attribute), 120
O
 OldEnvironmentModules (fastr.execution.environmentmodules.EnvironmentModules class attribute), 186
 loadf() (fastr.core.serializable.Serializable class method), 171
 loads() (fastr.core.serializable.PassThroughSerializer static method), 170
 loads() (fastr.core.serializable.Serializable class method), 172
P
 LocalBinaryTarget (class in fastr.plugins), 103
 logdir (fastr.configmanager.Config attribute), 77

logfile (fastr.execution.job.Job attribute), 204
logging_config (fastr.configmanager.Config attribute), 77
loglevel (fastr.configmanager.Config attribute), 77
logtype (fastr.configmanager.Config attribute), 77
logurl (fastr.execution.job.Job attribute), 204
long_id (fastr.execution.networkrun.NetworkRun attribute), 216
lookup() (fastr.datatypes.Deferred class method), 82

M

MacroNode (class in fastr.core.node), 154
MacroNodeRun (class in fastr.execution.macronoderun), 212
MacroOutput (class in fastr.core.inputoutput), 133
MacroOutputRun (class in fastr.execution.inputoutputrun), 194
main() (in module fastr.core.ioplugin), 145
main() (in module fastr.examples.add_ints), 183
main() (in module fastr.examples.add_ints_s3), 183
main() (in module fastr.examples.auto_prefix), 183
main() (in module fastr.examples.collapse), 183
main() (in module fastr.examples.collapse_expand), 183
main() (in module fastr.examples.cross_validation), 184
main() (in module fastr.examples.elastix_nipype), 184
main() (in module fastr.examples.expand), 184
main() (in module fastr.examples.failing_network), 184
main() (in module fastr.examples.filecopy), 184
main() (in module fastr.examples.input_groups), 184
main() (in module fastr.examples.macro_node), 185
main() (in module fastr.examples.macro_node2), 185
main() (in module fastr.examples.shift_links), 185
main() (in module fastr.examples.source_sink), 185
main() (in module fastr.execution.executionscript), 191
main() (in module fastr.utils.clear_pycs), 226
main() (in module fastr.utils.cmd), 235
main() (in module fastr.utils.cmd.cat), 235
main() (in module fastr.utils.cmd.dump), 235
main() (in module fastr.utils.cmd.execute), 235
main() (in module fastr.utils.cmd.extract_argparse), 235
main() (in module fastr.utils.cmd.prov), 236
main() (in module fastr.utils.cmd.run), 236
main() (in module fastr.utils.cmd.test), 236
main() (in module fastr.utils.cmd.trace), 236
main() (in module fastr.utils.cmd.verify), 237
main() (in module fastr.utils.cmd.webapp), 237
main() (in module fastr.utils.gettools), 228
main() (in module fastr.web.run), 240
major (fastr.core.version.Version attribute), 180
make_file_promise() (fastr.utils.filesynchelperFileSyncHelper method), 228
mapping_part() (fastr.core.samples.SampleValue method), 169
match_filename() (fastr.core.basemanager.BaseManager method), 118
match_types() (fastr.core.datatypemanager.DataTypeManager method), 121
match_types_any() (fastr.core.datatypemanager.DataTypeManager method), 122
md5_checksum() (in module fastr.utils.checksum), 225
mediatypes() (fastr.web.api.NetworkApi method), 238
mediatypes() (fastr.web.api.NetworkListApi method), 238
mediatypes() (fastr.web.api.RunApi method), 239
mediatypes() (fastr.web.api.RunListApi method), 239
mediatypes() (fastr.web.api.StatusApi method), 239
mediatypes() (fastr.web.api.ToolApi method), 240
mediatypes() (fastr.web.api.ToolListApi method), 240
members (fastr.datatypes.TypeGroup attribute), 87
merge() (fastr.core.inputgroupcombiner.BaseInputGroupCombiner method), 126
merge() (fastr.core.inputgroupcombiner.DefaultInputGroupCombiner method), 127
merge() (fastr.core.inputgroupcombiner.MergingInputGroupCombiner method), 127
merge_dimensions (fastr.__init__.Node attribute), 73
merge_dimensions (fastr.core.node.Node attribute), 156
merge_dimensions (fastr.execution.noderun.NodeRun attribute), 218
merge_failed_annotations() (fastr.core.inputgroupcombiner.BaseInputGroupCombiner method), 126
merge_payloads() (fastr.core.inputgroupcombiner.BaseInputGroupCombiner method), 126
merge_sample_data() (fastr.core.inputgroupcombiner.BaseInputGroupCombiner method), 126
merge_sample_id() (fastr.core.inputgroupcombiner.BaseInputGroupCombiner method), 126
merge_sample_index() (fastr.core.inputgroupcombiner.BaseInputGroupCombiner method), 126
merge_sample_jobs() (fastr.core.inputgroupcombiner.BaseInputGroupCombiner method), 126
MergingInputGroupCombiner (class in fastr.core.inputgroupcombiner), 127
messages (fastr.core.updateable.Updateable attribute), 178
MetaImageFile (class in fastr.datatypes), 85
methods (fastr.web.api.NetworkApi attribute), 238
methods (fastr.web.api.NetworkListApi attribute), 238
methods (fastr.web.api.RunApi attribute), 239
methods (fastr.web.api.RunListApi attribute), 239
methods (fastr.web.api.StatusApi attribute), 239
methods (fastr.web.api.ToolApi attribute), 240
methods (fastr.web.api.ToolListApi attribute), 240
minor (fastr.core.version.Version attribute), 180
module (fastr.core.baseplugin.BasePlugin attribute), 119
module (fastr.datatypes.AnalyzeImageFile attribute), 79
module (fastr.datatypes.Boolean attribute), 81
module (fastr.datatypes.Directory attribute), 83

module (fastr.datatypes.FilePrefix attribute), 84
 module (fastr.datatypes.Float attribute), 84
 module (fastr.datatypes.Int attribute), 84
 module (fastr.datatypes.ITKImageFile attribute), 84
 module (fastr.datatypes.JsonFile attribute), 84
 module (fastr.datatypes.MetaImageFile attribute), 85
 module (fastr.datatypes.NiftiImageFile attribute), 85
 module (fastr.datatypes.NiftiImageFileCompressed attribute), 85
 module (fastr.datatypes.NiftiImageFileUncompressed attribute), 85
 module (fastr.datatypes.Number attribute), 86
 module (fastr.datatypes.ProvNFile attribute), 86
 module (fastr.datatypes.String attribute), 86
 module (fastr.datatypes.TifImageFile attribute), 86
 module (fastr.datatypes.TxtFile attribute), 86
 module (fastr.datatypes.UnsignedInt attribute), 88
 module (fastr.plugins.BlockingExecution attribute), 96
 module (fastr.plugins.CommaSepreatedValueFile attribute), 97
 module (fastr.plugins.CrossValidation attribute), 97
 module (fastr.plugins.DockerTarget attribute), 99
 module (fastr.plugins.DRMAAExecution attribute), 98
 module (fastr.plugins.FastrInterface attribute), 101
 module (fastr.plugins.FileSystem attribute), 102
 module (fastr.plugins.FlowInterface attribute), 103
 module (fastr.plugins.LinearExecution attribute), 103
 module (fastr.plugins.LocalBinaryTarget attribute), 105
 module (fastr.plugins.NipypeInterface attribute), 106
 module (fastr.plugins.Null attribute), 106
 module (fastr.plugins.ProcessPoolExecution attribute), 107
 module (fastr.plugins.Reference attribute), 108
 module (fastr.plugins.RQExecution attribute), 107
 module (fastr.plugins.S3Filesystem attribute), 109
 module (fastr.plugins.StrongrExecution attribute), 109
 module (fastr.plugins.VirtualFileSystemRegularExpression attribute), 112
 module (fastr.plugins.VirtualFileSystemValueList attribute), 113
 module (fastr.plugins.XNATStorage attribute), 115
 ModuleSystem (class in fastr.execution.environmentmodules), 187
 monitor_docker() (fastr.plugins.DockerTarget method), 99
 monitor_process() (fastr.plugins.LocalBinaryTarget method), 105
 mounts (fastr.configmanager.Config attribute), 77

N

name (fastr.__init__.Node attribute), 73
 name (fastr.core.dimension.Dimension attribute), 122
 name (fastr.core.node.Node attribute), 157
 name (fastr.core.pluginmanager.plugin_option_type attribute), 163
 name (fastr.core.tool.Tool attribute), 175
 name (fastr.datatypes.BaseDataType attribute), 80
 name (fastr.execution.noderun.NodeRun attribute), 218
 namedtuple_to_dict() (in module fastr.utils.sysinfo), 234
 namespace (fastr.core.network.Network attribute), 151
 namespace (fastr.core.pluginmanager.plugin_option_type attribute), 163
 namespace (fastr.core.tool.Tool attribute), 175
 NATIVE_SPEC (fastr.plugins.DRMAAExecution attribute), 97
 ndims (fastr.core.dimension.HasDimensions attribute), 123
 ndims (fastr.core.samples.SampleCollection attribute), 166
 ndims (fastr.execution.inputoutputrun.SourceOutputRun attribute), 198
 Network (class in fastr), 62
 Network (class in fastr.__init__), 65, 66
 Network (class in fastr.core.network), 148
 network (fastr.core.node.MacroNode attribute), 155
 network (fastr.execution.networkrun.NetworkRun attribute), 216
 network() (in module fastr.web.views), 240
 NETWORK_DUMP_FILE_NAME (fastr.__init__.Network attribute), 66
 NETWORK_DUMP_FILE_NAME (fastr.core.network.Network attribute), 148
 NETWORK_DUMP_FILE_NAME (fastr.execution.networkrun.NetworkRun attribute), 214
 network_lock_thread() (in module fastr.web.api), 240
 network_run (fastr.execution.macronoderun.MacroNodeRun attribute), 213
 network_runner() (in module fastr.web.api), 240
 NetworkAnalyzer (class in fastr.execution.networkanalyzer), 213
 NetworkApi (class in fastr.web.api), 238
 NetworkChunker (class in fastr.execution.networkchunker), 214
 networklist (in module fastr.core.networkmanager), 152
 NetworkListApi (class in fastr.web.api), 238
 NetworkManager (class in fastr.core.networkmanager), 152
 NetworkRun (class in fastr.execution.networkrun), 214
 networks() (in module fastr.web.views), 240
 networks_path (fastr.configmanager.Config attribute), 77
 NiftiImageFile (class in fastr.datatypes), 85
 NiftiImageFileCompressed (class in fastr.datatypes), 85
 NiftiImageFileUncompressed (class in fastr.datatypes), 85
 NipypeInterface (class in fastr.plugins), 105
 Node (class in fastr.__init__), 71

Node (class in fastr.core.node), 155
 node (fastr.core.inputoutput.BaseInputOutput attribute), 130
 node (fastr.core.inputoutput.SubInput attribute), 138
 node (fastr.core.inputoutput.SubOutput attribute), 140
 node (fastr.execution.inputoutputrun.SubInputRun attribute), 200
 node (fastr.execution.inputoutputrun.SubOutputRun attribute), 202
 node_class (fastr.core.tool.Tool attribute), 175
 nodegroup (fastr.__init__.Node attribute), 73
 nodegroup (fastr.__init__.SourceNode attribute), 76
 nodegroup (fastr.core.node.Node attribute), 157
 nodegroup (fastr.core.node.SourceNode attribute), 159
 nodegroups (fastr.__init__.Network attribute), 69
 nodegroups (fastr.core.network.Network attribute), 151
 nodegroups (fastr.execution.networkrun.NetworkRun attribute), 216
 NodeRun (class in fastr.__init__), 65
 NodeRun (class in fastr.execution.noderun), 216
 nonexistent (fastr.execution.job.JobState attribute), 208
 normurl() (in module fastr.data.url), 182
 not_draft4() (in module fastr.utils.jsonschemaparser), 230
 ns_id (fastr.core.tool.Tool attribute), 175
 Null (class in fastr.plugins), 106
 Number (class in fastr.datatypes), 85

O

object_class (fastr.core.networkmanager.NetworkManager attribute), 152
 object_class (fastr.core.objectmanager.ObjectManager attribute), 160
 object_class (fastr.core.toolmanager.ToolManager attribute), 177
 ObjectManager (class in fastr.core.objectmanager), 159
 ObjectUrl (class in fastr.web.api), 238
 objectversions() (fastr.core.objectmanager.ObjectManager method), 160
 one_of_draft4() (in module fastr.utils.jsonschemaparser), 230
 open_url() (in module fastr.utils.cmd.webapp), 237
 options (fastr.datatypes.EnumType attribute), 83
 Output (class in fastr.core.inputoutput), 133
 output (fastr.__init__.SourceNode attribute), 76
 output (fastr.core.node.SourceNode attribute), 159
 output (fastr.execution.sourcenoderun.SourceNodeRun attribute), 221
 OutputDict (class in fastr.core.node), 157
 OutputRun (class in fastr.execution.inputoutputrun), 194
 outputs (fastr.core.interface.Interface attribute), 141
 outputs (fastr.core.node.Node attribute), 157
 outputs (fastr.core.tool.Tool attribute), 175
 outputs (fastr.plugins.FastrInterface attribute), 101
 outputs (fastr.plugins.FlowInterface attribute), 103

outputs (fastr.plugins.NipypeInterface attribute), 106
 outputsize (fastr.__init__.Node attribute), 73
 outputsize (fastr.core.node.FlowNode attribute), 154
 outputsize (fastr.core.node.Node attribute), 157
 outputsize (fastr.execution.flownoderun.FlowNodeRun attribute), 191
 outputsize (fastr.execution.noderun.NodeRun attribute), 218
 outputsize (fastr.execution.sourcenoderun.SourceNodeRun attribute), 221
 OutputSpec (class in fastr.core.interface), 142
 OutputSpecBase (in module fastr.core.interface), 142

P

parent (fastr.__init__.Link attribute), 71
 parent (fastr.__init__.Node attribute), 73
 parent (fastr.core.inputgroup.InputGroup attribute), 125
 parent (fastr.core.link.Link attribute), 148
 parent (fastr.core.node.Node attribute), 157
 parent (fastr.core.samples.SampleCollection attribute), 166
 parent (fastr.datatypes.BaseDataType attribute), 80
 parent (fastr.execution.linkrun.LinkRun attribute), 212
 parent (fastr.execution.noderun.NodeRun attribute), 218
 parse() (fastr.utils.schematable.SchemaPrinter method), 232
 parsed_value (fastr.datatypes.BaseDataType attribute), 80
 parsed_value (fastr.datatypes.Deferred attribute), 82
 parsed_value (fastr.datatypes.URLType attribute), 88
 PassThroughSerializer (class in fastr.core.serializable), 170
 path (fastr.core.tool.Tool attribute), 175
 path (in module fastr.plugins), 115
 path_to_url() (fastr.core.ioplugin.IOPlugin method), 143
 path_to_url() (fastr.plugins.FileSystem method), 102
 path_to_url() (fastr.plugins.VirtualFileSystem method), 111
 pattern_properties_prevalid() (in module fastr.utils.jsonschemaparser), 230
 pim_host (fastr.configmanager.Config attribute), 77
 pim_register_run() (fastr.utils.pim_publisher.PimPublisher method), 231
 pim_serialize_network() (fastr.utils.pim_publisher.PimPublisher method), 231
PIM_STATUS_MAPPING
 (fastr.utils.pim_publisher.PimPublisher attribute), 231
 pim_update_status() (fastr.utils.pim_publisher.PimPublisher method), 231
 PimPublisher (class in fastr.utils.pim_publisher), 231
 Plugin (class in fastr.core.baseplugin), 119
 plugin_class (fastr.core.datatypemanager.DataTypeManager attribute), 122

plugin_class (fastr.core.pluginmanager.BasePluginManager attribute), 161

plugin_class (fastr.core.pluginmanager.PluginManager attribute), 161

plugin_class (fastr.core.pluginmanager.PluginSubManager attribute), 162

plugin_option_type (class in fastr.core.pluginmanager), 162

PluginManager (class in fastr.core.pluginmanager), 161

PluginMeta (class in fastr.core.baseplugin), 119

plugins_path (fastr.configmanager.Config attribute), 77

PluginState (class in fastr.core.baseplugin), 119

PluginSubManager (class in fastr.core.pluginmanager), 161

PluginsView (class in fastr.core.pluginmanager), 162

poll_datatype() (fastr.core.datatypemanager.DataTypeManager method), 122

pop() (fastr.core.inputgroup.InputGroup method), 125

popitem() (fastr.core.inputgroup.InputGroup method), 125

populate() (fastr.core.basemanager.BaseManager method), 118

populate() (fastr.core.datatypemanager.DataTypeManager method), 122

populate() (fastr.core.ioplugin.IOPluginManager method), 144

populate() (fastr.core.pluginmanager.BasePluginManager method), 161

populate() (fastr.core.toolmanager.ToolManager method), 177

post() (fastr.web.api.RunListApi method), 239

preferred_types (fastr.configmanager.Config attribute), 77

preferred_types (fastr.core.datatypemanager.DataTypeManager attribute), 122

preferred_types (fastr.core.inputoutput.Output attribute), 135

preferred_types (fastr.core.inputoutput.SubOutput attribute), 140

preferred_types (fastr.execution.inputoutputrun.OutputRun attribute), 197

preferred_types (fastr.execution.inputoutputrun.SubOutputRun attribute), 202

preload (fastr.core.baseplugin.PluginState attribute), 120

prepend() (fastr.configmanager.EmptyDefault method), 79

primary (fastr.core.inputgroup.InputGroup attribute), 125

print_help() (in module fastr.utils.cmd), 235

print_job_result() (in module fastr.utils.cmd.trace), 236

print_result() (fastr.core.ioplugin.IOPlugin static method), 143

print_sample_sink() (in module fastr.utils.cmd.trace), 236

print_samples() (in module fastr.utils.cmd.trace), 236

print_sinks() (in module fastr.utils.cmd.trace), 236

printlines() (fastr.utils.schematatable.SchemaPrinter method), 232

process_callbacks() (fastr.execution.executionpluginmanager.ExecutionPlugin method), 190

process_pool_worker_number (fastr.configmanager.Config attribute), 77

processing_callback (fastr.execution.job.JobState attribute), 208

ProcessPoolExecution (class in fastr.plugins), 107

ProcessUsageCollection (class in fastr.core.target), 172

properties_postvalidate() (in module fastr.utils.jsonschemaparser), 230

properties_prevalidate() (in module fastr.utils.jsonschemaparser), 231

protected_modules (fastr.configmanager.Config attribute), 77

proxify() (in module fastr.web.views), 240

PROV_DUMP (fastr.execution.job.Job attribute), 202

Provenance (class in fastr.core.provenance), 163

provenance (fastr.datatypes.Deferred attribute), 82

provfile (fastr.execution.job.Job attribute), 204

ProvNFile (class in fastr.datatypes), 86

provurl (fastr.execution.job.Job attribute), 204

pull_source_data() (fastr.core.ioplugin.IOPlugin method), 143

pull_source_data() (fastr.core.ioplugin.IOPluginManager method), 145

push_sink_data() (fastr.core.ioplugin.IOPlugin method), 143

push_sink_data() (fastr.core.ioplugin.IOPluginManager method), 145

push_sink_data() (fastr.plugins.Reference method), 108

put_url() (fastr.core.ioplugin.IOPlugin method), 143

put_url() (fastr.core.ioplugin.IOPluginManager method), 145

put_url() (fastr.plugins.FileSystem method), 102

put_url() (fastr.plugins.Null method), 106

put_url() (fastr.plugins.S3Filesystem method), 109

put_url() (fastr.plugins.VirtualFileSystem method), 111

put_url() (fastr.plugins.XNATStorage method), 115

put_value() (fastr.core.ioplugin.IOPlugin method), 144

put_value() (fastr.plugins.FileSystem method), 102

put_value() (fastr.plugins.Null method), 106

put_value() (fastr.plugins.S3Filesystem method), 109

put_value() (fastr.plugins.VirtualFileSystem method), 111

Python Enhancement Proposals

- PEP 8, 27
- PEP 8#class-names, 28
- PEP 8#global-variable-names, 28
- PEP 8#method-names-and-instance-variables, 28
- PEP 8#package-and-module-names, 28
- PEP 8#prescriptive-naming-conventions, 28

Q

queue (fastr.execution.executionpluginmanager.JobAction attribute), 190
queue_job() (fastr.execution.executionpluginmanager.ExecutionPlugin method), 190
queued (fastr.execution.job.JobState attribute), 208

R

raw_value (fastr.datatypes.BaseDataType attribute), 81
read_bytes (fastr.core.target.SystemUsageInfo attribute), 173
read_config() (fastr.configmanager.Config method), 77
read_config_files (fastr.configmanager.Config attribute), 78
read_config_string() (fastr.configmanager.Config method), 78
read_sink_data() (in module fastr.utils.cmd.trace), 236
readfastrschema() (fastr.utils.jsonschemasparser.FastrRefResolver static method), 229
readfile() (fastr.utils.jsonschemasparser.FastrRefResolver static method), 229
Reference (class in fastr.plugins), 108
references (fastr.core.tool.Tool attribute), 176
regex (fastr.core.tool.Tool attribute), 176
register_configuration() (fastr.core.baseplugin.BasePlugin class method), 119
register_fields() (fastr.configmanager.Config method), 78
register_job() (fastr.execution.executionpluginmanager.ExecutionPlugin method), 190
register_url_scheme() (fastr.core.ioplugin.IOPluginManager static method), 145
register_url_scheme() (in module fastr.data.url), 182
release_job() (fastr.execution.executionpluginmanager.ExecutionPlugin method), 190
reload() (fastr.core.basemanager.BaseManager method), 118
reload() (fastr.execution.environmentmodules.EnvironmentModule method), 186
remove() (fastr.__init__.Network method), 69
remove() (fastr.core.inputoutput.Input method), 133
remove() (fastr.core.inputoutput.SubInput method), 138
remove() (fastr.core.network.Network method), 151
remove() (fastr.execution.inputoutputrun.InputRun method), 194
request_parser (fastr.web.api.RunListApi attribute), 239
required (fastr.core.inputoutput.BaseInputOutput attribute), 130
required_cores (fastr.__init__.Node attribute), 73
required_cores (fastr.core.node.Node attribute), 157
required_cores (fastr.execution.job.Job attribute), 205
required_cores (fastr.execution.noderun.NodeRun attribute), 218
required_memory (fastr.__init__.Node attribute), 73
required_memory (fastr.core.node.Node attribute), 157

required_memory (fastr.execution.job.Job attribute), 205
required_memory (fastr.execution.noderun.NodeRun attribute), 218

required_time (fastr.__init__.Node attribute), 74

required_time (fastr.core.node.Node attribute), 157

required_time (fastr.execution.job.Job attribute), 205

required_time (fastr.execution.noderun.NodeRun attribute), 218

requirements (fastr.core.tool.Tool attribute), 176

resourcesdir (fastr.configmanager.Config attribute), 78

RESULT_DUMP (fastr.execution.job.Job attribute), 202

resulting_datatype (fastr.core.inputoutput.Output attribute), 135

resulting_datatype (fastr.core.inputoutput.SubOutput attribute), 140

resulting_datatype (fastr.execution.inputoutputrun.OutputRun attribute), 197

resulting_datatype (fastr.execution.inputoutputrun.SubOutputRun attribute), 202

rmem (fastr.core.target.SystemUsageInfo attribute), 173

RQExecution (class in fastr.plugins), 107

Run (class in fastr.web.api), 238

run_command() (fastr.core.target.Target method), 173

run_command() (fastr.plugins.DockerTarget method), 99

run_command() (fastr.plugins.LocalBinaryTarget method), 105

run_job() (fastr.plugins.RQExecution class method), 107

run_network() (fastr.web.api.Run method), 238

RunApi (class in fastr.web.api), 238

runapp() (in module fastr.web.run), 240

RunListApi (class in fastr.web.api), 239

running (fastr.execution.job.JobState attribute), 208

S

S3Filesystem (class in fastr.plugins), 108

SampleBaseId (class in fastr.core.samples), 164

SampleCollection (class in fastr.core.samples), 165

SampleId (class in fastr.core.samples), 166

SampleIndex (class in fastr.core.samples), 166

SampleItem (class in fastr.core.samples), 167

SampleItemBase (class in fastr.core.samples), 167

SamplePayload (class in fastr.core.samples), 168

samples (fastr.core.inputoutput.SubOutput attribute), 140

samples (fastr.core.samples.ContainsSamples attribute), 164

samples (fastr.execution.inputoutputrun.OutputRun attribute), 197

samples (fastr.execution.inputoutputrun.SubOutputRun attribute), 202

SampleValue (class in fastr.core.samples), 169

save_gpickle() (in module fastr.utils.iohelpers), 228

save_json() (in module fastr.utils.iohelpers), 228

save_version() (in module fastr.version), 116

schemadir (fastr.configmanager.Config attribute), 78

SchemaPrinter (class in fastr.utils.schematatable), 232
 scheme (fastr.core.ioplugin.IOPlugin attribute), 144
 scheme (fastr.plugins.CommaSepreatedValueFile attribute), 97
 scheme (fastr.plugins.FileSystem attribute), 102
 scheme (fastr.plugins.Null attribute), 107
 scheme (fastr.plugins.Reference attribute), 108
 scheme (fastr.plugins.S3Filesystem attribute), 109
 scheme (fastr.plugins.VirtualFileSystem attribute), 111
 scheme (fastr.plugins.VirtualFileSystemRegularExpression attribute), 112
 scheme (fastr.plugins.VirtualFileSystemValueList attribute), 113
 scheme (fastr.plugins.XNATStorage attribute), 115
 send_job() (fastr.plugins.DRMAAExecution method), 98
 sequence_part() (fastr.core.samples.SampleValue method), 170
 Serializable (class in fastr.core.serializable), 170
 serialize() (fastr.core.provenance.Provenance method), 163
SERIALIZERS (fastr.core.serializable.Serializable attribute), 170
 server (fastr.plugins.XNATStorage attribute), 115
 set_code() (fastr.core.baseplugin.BasePlugin class method), 119
 set_data() (fastr.__init__.ConstantNode method), 75
 set_data() (fastr.__init__.SourceNode method), 76
 set_data() (fastr.core.node.ConstantNode method), 153
 set_data() (fastr.core.node.SourceNode method), 159
 set_data() (fastr.execution.networkrun.NetworkRun method), 216
 set_data() (fastr.execution.sinknoderun.SinkNodeRun method), 219
 set_data() (fastr.execution.sourcenoderun.ConstantNodeRun method), 222
 set_data() (fastr.execution.sourcenoderun.SourceNodeRun method), 221
 set_field() (fastr.configmanager.Config method), 78
 set_result() (fastr.execution.flownoderun.AdvancedFlowNodeRun method), 191
 set_result() (fastr.execution.flownoderun.FlowNodeRun method), 191
 set_result() (fastr.execution.noderun.NodeRun method), 218
 set_result() (fastr.execution.sinknoderun.SinkNodeRun method), 220
 set_status() (fastr.core.baseplugin.BasePlugin class method), 119
 setdefault() (fastr.core.inputgroup.InputGroup method), 125
 setup() (fastr.core.ioplugin.IOPlugin method), 144
 setup() (fastr.plugins.VirtualFileSystem method), 111
 sha1_checksum() (in module fastr.utils.checksum), 225
 show_jobs() (fastr.execution.executionpluginmanager.ExecutionPlugin class method), 63
 shutdown() (in module fastr.web.views), 240
 shutdown_server() (in module fastr.web.views), 240
 sink_data() (in module fastr.examples.add_ints), 183
 sink_data() (in module fastr.examples.add_ints_s3), 183
 sink_data() (in module fastr.examples.collapse), 183
 sink_data() (in module fastr.examples.collapse_expand), 183
 sink_data() (in module fastr.examples.cross_validation), 184
 sink_data() (in module fastr.examples.elastix_nipype), 184
 sink_data() (in module fastr.examples.expand), 184
 sink_data() (in module fastr.examples.failing_network), 184
 sink_data() (in module fastr.examples.filecopy), 184
 sink_data() (in module fastr.examples.input_groups), 184
 sink_data() (in module fastr.examples.macro_node), 185
 sink_data() (in module fastr.examples.macro_node2), 185
 sink_data() (in module fastr.examples.shift_links), 185
 sink_data() (in module fastr.examples.source_sink), 185
SINK_DUMP_FILE_NAME (fastr.__init__.Network attribute), 66
SINK_DUMP_FILE_NAME (fastr.core.network.Network attribute), 148
SINK_DUMP_FILE_NAME (fastr.execution.networkrun.NetworkRun attribute), 214
 SinkJob (class in fastr.execution.job), 208
 sinklist (fastr.execution.networkrun.NetworkRun attribute), 216
 SinkNode (class in fastr.__init__), 76
 SinkNode (class in fastr.core.node), 157
SinkNodeRun (class in fastr.__init__), 65
 SinkNodeRun (class in fastr.execution.sinknoderun), 219
 size (fastr.core.dimension.Dimension attribute), 122
 size (fastr.core.dimension.HasDimensions attribute), 123
 size (fastr.execution.inputoutputrun.SourceOutputRun attribute), 198
 size (fastr.execution.linkrun.LinkRun attribute), 212
 solve_broadcast() (fastr.core.inputgroup.InputGroup class method), 125
 source (fastr.__init__.Link attribute), 71
 source (fastr.core.dimension.ForwardsDimensions attribute), 123
 source (fastr.core.inputoutput.Input attribute), 133
 source (fastr.core.inputoutput.SubInput attribute), 138
 source (fastr.core.link.Link attribute), 148
 source (fastr.execution.inputoutputrun.InputRun attribute), 194
 source (fastr.execution.inputoutputrun.SubInputRun attribute), 200
 source (fastr.execution.linkrun.LinkRun attribute), 212
 source (fastr.execution.linkrun.LinkRun attribute), 212

source_code (fastr.core.baseplugin.BasePlugin attribute), 119
source_data() (in module fastr.examples.add_ints), 183
source_data() (in module fastr.examples.add_ints_s3), 183
source_data() (in module fastr.examples.collapse), 183
source_data() (in module fastr.examples.collapse_expand), 183
source_data() (in module fastr.examples.cross_validation), 184
source_data() (in module fastr.examples.elastix_nipype), 184
source_data() (in module fastr.examples.expand), 184
source_data() (in module fastr.examples.failing_network), 184
source_data() (in module fastr.examples.filecopy), 184
source_data() (in module fastr.examples.input_groups), 184
source_data() (in module fastr.examples.macro_node), 185
source_data() (in module fastr.examples.macro_node2), 185
source_data() (in module fastr.examples.shift_links), 185
source_data() (in module fastr.examples.source_sink), 185
SOURCE_DUMP_FILE_NAME (fastr.__init__.Network attribute), 66
SOURCE_DUMP_FILE_NAME (fastr.core.network.Network attribute), 148
SOURCE_DUMP_FILE_NAME (fastr.execution.networkrun.NetworkRun attribute), 214
source_job_limit (fastr.configmanager.Config attribute), 78
source_output (fastr.core.inputoutput.SubInput attribute), 138
source_output (fastr.execution.inputoutputrun.SubInputRun attribute), 200
sourcegroup (fastr.__init__.SourceNode attribute), 76
sourcegroup (fastr.core.node.SourceNode attribute), 159
sourcegroup (fastr.execution.sourcenoderun.SourceNodeRun attribute), 221
SourceJob (class in fastr.execution.job), 209
sourcelist (fastr.execution.networkrun.NetworkRun attribute), 216
SourceNode (class in fastr.__init__), 75
SourceNode (class in fastr.core.node), 158
SourceNodeRun (class in fastr.__init__), 65
SourceNodeRun (class in fastr.execution.sourcenoderun), 220
SourceOutput (class in fastr.core.inputoutput), 135
SourceOutputRun (class in fastr.execution.inputoutputrun), 197
spec_fields (fastr.plugins.DRMAAExecution attribute), 98
split() (in module fastr.data.url), 182
status (fastr.__init__.Link attribute), 71
status (fastr.__init__.Node attribute), 74
status (fastr.core.baseplugin.BasePlugin attribute), 119
status (fastr.core.link.Link attribute), 148
status (fastr.core.node.Node attribute), 157
status (fastr.core.version.Version attribute), 180
status (fastr.execution.job.Job attribute), 205
status (fastr.execution.linkrun.LinkRun attribute), 212
status (fastr.execution.noderun.NodeRun attribute), 218
status() (fastr.web.api.Run method), 238
status_message (fastr.core.baseplugin.BasePlugin attribute), 119
StatusApi (class in fastr.web.api), 239
STDERR_DUMP (fastr.execution.job.Job attribute), 202
stderrfile (fastr.execution.job.Job attribute), 205
stderrurl (fastr.execution.job.Job attribute), 205
stdout (in module fastr.plugins), 115
STDOUT_DUMP (fastr.execution.job.Job attribute), 202
stdoutfile (fastr.execution.job.Job attribute), 205
stdouturl (fastr.execution.job.Job attribute), 205
store() (fastr.utils.filesynchelperFileSyncHelper method), 228
String (class in fastr.datatypes), 86
StrongrExecution (class in fastr.plugins), 109
SubInput (class in fastr.core.inputoutput), 136
SubInputRun (class in fastr.execution.inputoutputrun), 198
submit_jobs() (fastr.plugins.DRMAAExecution method), 98
SubOutput (class in fastr.core.inputoutput), 138
SubOutputRun (class in fastr.execution.inputoutputrun), 200
substitute() (fastr.execution.job.SinkJob method), 209
SubUrl (class in fastr.web.api), 239
suffix (fastr.core.version.Version attribute), 180
SUPPORTS_CANCEL (fastr.execution.executionpluginmanager.Execution attribute), 188
SUPPORTS_CANCEL (fastr.plugins.DRMAAExecution attribute), 97
SUPPORTS_DEPENDENCY (fastr.execution.executionpluginmanager.ExecutionPlugin attribute), 188
SUPPORTS_DEPENDENCY (fastr.plugins.DRMAAExecution attribute), 97
SUPPORTS_HOLD_RELEASE (fastr.execution.executionpluginmanager.ExecutionPlugin attribute), 188
SUPPORTS_HOLD_RELEASE (fastr.plugins.DRMAAExecution attribute), 97
swap() (fastr.execution.environmentmodules.EnvironmentModules

method), 187
`switch_sample_sink()` (in module `fastr.utils.cmd.trace`), 236
`sync()` (`fastr.execution.environmentmodules.EnvironmentModule` method), 187
`systemdir` (`fastr.configmanager.Config` attribute), 78
`SystemUsageInfo` (class in `fastr.core.target`), 172

T

`tags` (`fastr.core.tool.Tool` attribute), 176
`Target` (class in `fastr.core.target`), 173
`target` (`fastr.__init__.Link` attribute), 71
`target` (`fastr.core.link.Link` attribute), 148
`target` (`fastr.core.tool.Tool` attribute), 176
`target` (`fastr.datatypes.Deferred` attribute), 82
`target` (`fastr.execution.linkrun.LinkRun` attribute), 212
`target` (`fastr.Link` attribute), 64
`TargetManager` (class in `fastr.core.target`), 173
`test()` (`fastr.__init__.Network` class method), 69
`test()` (`fastr.core.baseplugin.BasePlugin` class method), 119
`test()` (`fastr.core.interface.Interface` class method), 141
`test()` (`fastr.core.network.Network` class method), 151
`test()` (`fastr.core.target.Target` class method), 173
`test()` (`fastr.core.tool.Tool` method), 176
`test()` (`fastr.datatypes.BaseDataType` class method), 81
`test()` (`fastr.plugins.DRMAAExecution` class method), 98
`test()` (`fastr.plugins.NipypeInterface` class method), 106
`test()` (`fastr.plugins.ProcessPoolExecution` class method), 107
`test()` (`fastr.plugins.StrongrExecution` class method), 109
`test_plugin()` (`fastr.core.pluginmanager.BasePluginManager` method), 161
`test_spec` (`fastr.core.tool.Tool` attribute), 176
`test_tool()` (`fastr.core.tool.Tool` class method), 176
`tests` (`fastr.core.tool.Tool` attribute), 176
`TifImageFile` (class in `fastr.datatypes`), 86
`timestamp` (`fastr.core.target.SystemUsageInfo` attribute), 173
`tmpurl` (`fastr.execution.job.Job` attribute), 205
`tmpurl` (`fastr.execution.job.SinkJob` attribute), 209
`todict()` (`fastr.core.objectmanager.ObjectManager` method), 160
`Tool` (class in `fastr.core.tool`), 174
`tool` (`fastr.__init__.Node` attribute), 74
`tool` (`fastr.core.node.Node` attribute), 157
`tool` (`fastr.execution.job.Job` attribute), 205
`tool` (`fastr.execution.noderun.NodeRun` attribute), 218
`tool()` (in module `fastr.utils.cmd.test`), 236
`tool()` (in module `fastr.web.views`), 240
`TOOL_REFERENCE_FILE_NAME` (`fastr.core.tool.Tool` attribute), 174
`TOOL_RESULT_FILE_NAME` (`fastr.core.tool.Tool` attribute), 174

`ToolApi` (class in `fastr.web.api`), 239
`toollist` (`fastr` attribute), 61
`toollist` (in module `fastr.__init__`), 65
`ToolList` (in module `fastr.core.toolmanager`), 177
`ToolListApi` (class in `fastr.web.api`), 240
`ToolManager` (class in `fastr.core.toolmanager`), 176
`tools_path` (`fastr.configmanager.Config` attribute), 78
`toolversions()` (`fastr.core.toolmanager.ToolManager` method), 177
`TORQUE_NATIVE_SPEC`
`(fastr.plugins.DRMAAExecution` attribute), 97
`tostring_modvalue()` (`fastr.execution.environmentmodules.EnvironmentModule` static method), 187
`totuple_modvalue()` (`fastr.execution.environmentmodules.EnvironmentModule` static method), 187
`translate_argument()` (`fastr.execution.job.Job` class method), 205
`translate_output_results()` (`fastr.execution.job.Job` static method), 205
`translate_results()` (`fastr.execution.job.Job` method), 205
`TxtFile` (class in `fastr.datatypes`), 86
`TypeGroup` (class in `fastr.datatypes`), 86
`typelist` (`fastr` attribute), 62
`typelist` (in module `fastr.__init__`), 65
`types_path` (`fastr.configmanager.Config` attribute), 78

U

`uninitialized` (`fastr.core.baseplugin.PluginState` attribute), 120
`unload()` (`fastr.execution.environmentmodules.EnvironmentModules` method), 187
`unloaded` (`fastr.core.baseplugin.PluginState` attribute), 120
`unmerge()` (`fastr.core.inputgroupcombiner.BaseInputGroupCombiner` method), 126
`unmerge()` (`fastr.core.inputgroupcombiner.DefaultInputGroupCombiner` method), 127
`unmerge()` (`fastr.core.inputgroupcombiner.MergingInputGroupCombiner` method), 127
`UnsignedInt` (class in `fastr.datatypes`), 88
`update()` (`fastr.configmanager.EmptyDefault` method), 79
`update()` (`fastr.core.inputgroup.InputGroup` method), 125
`update()` (`fastr.core.inputgroupcombiner.BaseInputGroupCombiner` method), 127
`update()` (`fastr.core.inputgroupcombiner.MergingInputGroupCombiner` method), 127
`update()` (`fastr.core.updateable.Updateable` method), 178
`update_input_groups()` (`fastr.__init__.Node` method), 74
`update_input_groups()` (`fastr.core.node.Node` method), 157
`update_input_groups()` (`fastr.execution.noderun.NodeRun` method), 218
`update_job_result()` (in module `fastr.web.api`), 240

update_size() (fastr.core.dimension.Dimension method), 123
 update_status() (in module fastr.web.api), 240
 Updateable (class in fastr.core.updateable), 177
 UpdateableMeta (class in fastr.core.updateable), 178
 updatetrigger() (fastr.core.updateable.UpdateableMeta static method), 179
 upload() (fastr.plugins.XNATStorage static method), 115
 url (fastr.core.tool.Tool attribute), 176
 url_to_path() (fastr.core.ioplugin.IOPlugin method), 144
 url_to_path() (fastr.core.ioplugin.IOPluginManager method), 145
 url_to_path() (fastr.plugins.FileSystem method), 102
 url_to_path() (fastr.plugins.VirtualFileSystem method), 111
 URLType (class in fastr.datatypes), 87
 usage_type (fastr.core.target.ProcessUsageCollection attribute), 172
 userdir (fastr.configmanager.Config attribute), 78

V

valid (fastr.__init__.SourceNode attribute), 76
 valid (fastr.core.inputoutput.Output attribute), 135
 valid (fastr.core.node.SourceNode attribute), 159
 valid (fastr.core.updateable.Updateable attribute), 178
 valid (fastr.datatypes.BaseDataType attribute), 81
 valid (fastr.datatypes.URLType attribute), 88
 valid (fastr.execution.inputoutputrun.OutputRun attribute), 197
 valid (fastr.execution.sourcenoderun.SourceNodeRun attribute), 221
 validate_results() (fastr.execution.job.Job method), 205
 validate_results() (fastr.execution.job.SinkJob method), 209
 validate_results() (fastr.execution.job.SourceJob method), 209
 value (fastr.datatypes.BaseDataType attribute), 81
 value (fastr.datatypes.Boolean attribute), 81
 value (fastr.datatypes.Deferred attribute), 82
 value (fastr.datatypes.Float attribute), 84
 value (fastr.datatypes.Int attribute), 84
 value (fastr.datatypes.UnsignedInt attribute), 88
 ValueType (class in fastr.datatypes), 88
 verify_resource_loading() (in module fastr.utils.verify), 234
 verify_tool() (in module fastr.utils.verify), 234
 Version (class in fastr.core.version), 179
 version (fastr.core.tool.Tool attribute), 176
 version (fastr.datatypes.BaseDataType attribute), 81
 version (fastr.datatypes.EnumType attribute), 83
 version_matcher (fastr.core.version.Version attribute), 180
 VirtualFileSystem (class in fastr.plugins), 109

VirtualFileSystemRegularExpression (class in fastr.plugins), 111
 VirtualFileSystemValueList (class in fastr.plugins), 112
 vmem (fastr.core.target.SystemUsageInfo attribute), 173

W

wait_for_file() (fastr.utils.filesynchelperFileSyncHelper method), 228
 wait_for_job() (fastr.utils.filesynchelperFileSyncHelper method), 228
 wait_for_pickle() (fastr.utils.filesynchelperFileSyncHelper method), 228
 wait_for_vfs_url() (fastr.utils.filesynchelperFileSyncHelper method), 228
 warn_develop (fastr.configmanager.Config attribute), 78
 web_hostname (fastr.configmanager.Config attribute), 78
 web_port (fastr.configmanager.Config attribute), 78
 web_secret_key (fastr.configmanager.Config attribute), 78
 web_url() (fastr.configmanager.Config method), 78
 websocket_client() (in module fastr.web.views), 240
 which() (in module fastr.utils.procutils), 231
 write() (fastr.execution.job.Job method), 206
 write_bytes (fastr.core.target.SystemUsageInfo attribute), 173

X

x (fastr.configmanager.Config attribute), 78
 xnat (fastr.plugins.XNATStorage attribute), 115
 XNATStorage (class in fastr.plugins), 113